

Free Pascal supplied units :
Reference guide.

Reference guide for standard Free Pascal units.

1.8

December 2000

Michaël Van Canneyt
Florian Klämpfl

Contents

1	The CRT unit.	25
1.1	Types, Variables, Constants	25
1.2	Procedures and Functions	26
	AssignCrt	26
	CursorBig	27
	ClrEol	27
	ClrScr	28
	CursorOff	28
	CursorOn	28
	Delay	28
	DelLine	29
	GotoXY	29
	HighVideo	30
	InsLine	30
	KeyPressed	31
	LowVideo	31
	NormVideo	32
	NoSound	32
	ReadKey	33
	Sound	33
	TextBackground	33
	TextColor	34
	TextMode	34
	WhereX	35
	WhereY	35
	Window	35
2	The DOS unit.	37
2.1	Types, Variables, Constants	37
	Constants	37
	Types	38

	Variables	39
2.2	Function list by category	40
	File handling	40
	Directory and disk handling	40
	Process handling	41
	System information	41
2.3	Functions and Procedures	41
	AddDisk	41
	DiskFree	42
	DiskSize	42
	DosExitCode	43
	DosVersion	43
	EnvCount	44
	EnvStr	44
	Exec	45
	FExpand	45
	FindClose	45
	FindFirst	46
	FindNext	47
	FSearch	47
	FSplit	47
	GetCBreak	48
	GetDate	48
	GetEnv	49
	GetFAttr	49
	GetFTime	50
	GetIntVec	51
	GetLongName	51
	GetShortName	51
	GetTime	51
	GetVerify	52
	Intr	52
	Keep	52
	MSDos	53
	PackTime	53
	SetCBreak	54
	SetDate	54
	SetFAttr	54
	SetFTime	54
	SetIntVec	55

SetTime	55
SetVerify	55
SwapVectors	55
UnPackTime	55
3 The DXELOAD unit	56
3.1 Introduction	56
3.2 Constants, types and variables	56
Constants	56
Types	56
3.3 Functions and Procedures	56
dx_load	56
4 The EMU387 unit	58
4.1 Functions and procedures	58
npxsetup	58
5 The GETOPTS unit.	59
5.1 Types, Constants and variables :	59
Constants	59
Types	59
Variables	60
5.2 Procedures and functions	60
GetLongOpts	60
Getopt	60
6 The GPM unit	63
6.1 Introduction	63
6.2 Constants, types and variables	63
constants	63
Types	64
Variables	65
6.3 Functions and procedures	65
Gpm_AnyDouble	65
Gpm_AnySingle	66
Gpm_AnyTriple	66
Gpm_Close	66
Gpm_FitValues	66
Gpm_FitValuesM	66
Gpm_GetEvent	67
Gpm_GetLibVersion	68

Gpm_GetServerVersion	68
Gpm_GetSnapshot	68
Gpm_LowerRoi	69
Gpm_Open	69
Gpm_PopRoi	69
Gpm_PushRoi	69
Gpm_RaiseRoi	70
Gpm_Repeat	70
Gpm_StrictDouble	70
Gpm_StrictSingle	70
Gpm_StrictTriple	71
7 The GO32 unit	72
7.1 Introduction	72
7.2 Protected mode memory organization	72
What is DPMI	72
Selectors and descriptors	72
FPC specialities	73
DOS memory access	73
I/O port access	73
Processor access	73
Interrupt redirection	73
Handling interrupts with DPMI	74
Protected mode interrupts vs. Real mode interrupts	74
Creating own interrupt handlers	74
Disabling interrupts	74
Hardware interrupts	74
Software interrupts	76
Real mode callbacks	78
7.3 Types, Variables and Constants	79
Constants	79
Predefined types	79
Variables.	81
7.4 Functions and Procedures	81
allocate_ldt_descriptors	81
allocate_memory_block	83
copyfromdos	83
copytodos	83
create_code_segment_alias_descriptor	84
disable	84

dosmemfillchar	84
dosmemfillword	85
dosmemget	86
dosmemmove	86
dosmemput	86
enable	87
free_ldt_descriptor	87
free_memory_block	87
free_rm_callback	87
get_cs	88
get_descriptor_access_rights	88
get_ds	88
get_linear_addr	88
get_meminfo	89
get_next_selector_increment_value	90
get_page_size	90
get_pm_interrupt	90
get_rm_callback	91
get_rm_interrupt	93
get_run_mode	94
get_segment_base_address	94
get_segment_limit	95
get_ss	95
global_dos_alloc	95
global_dos_free	97
inportb	97
inportl	97
inportw	97
lock_code	98
lock_data	98
lock_linear_region	98
outportb	99
outportl	99
outportw	99
realintr	100
seg_fillchar	100
seg_fillword	101
segment_to_descriptor	101
seg_move	102
set_descriptor_access_rights	102

set_pm_interrupt	102
set_rm_interrupt	103
set_segment_base_address	104
set_segment_limit	104
tb_size	104
transfer_buffer	105
unlock_code	105
unlock_data	105
unlock_linear_region	105
8 The GRAPH unit.	106
8.1 Introduction	106
Requirements	106
A word about mode selection	106
8.2 Constants, Types and Variables	111
Types	111
8.3 Function list by category	111
Initialization	111
screen management	112
Color management	112
Drawing primitives	113
Filled drawings	113
Text and font handling	114
8.4 Functions and procedures	114
Arc	114
Bar	114
Bar3D	114
Circle	115
ClearDevice	115
ClearViewPort	115
CloseGraph	115
DetectGraph	115
DrawPoly	116
Ellipse	116
FillEllipse	116
FillPoly	116
FloodFill	116
GetArcCoords	117
GetAspectRatio	117
GetBkColor	117

GetColor	117
GetDefaultPalette	117
GetDriverName	117
GetFillPattern	118
GetFillSettings	118
GetGraphMode	118
GetImage	118
GetLineSettings	118
GetMaxColor	118
GetMaxMode	119
GetMaxX	119
GetMaxY	119
GetModeName	119
GetModeRange	119
GetPalette	120
GetPaletteSize	120
GetPixel	120
GetTextSettings	120
GetViewSettings	120
GetX	120
GetY	121
GraphDefaults	121
GraphErrorMsg	121
GraphResult	121
ImageSize	122
InitGraph	122
InstallUserDriver	122
InstallUserFont	123
Line	123
LineRel	123
LineTo	123
MoveRel	123
MoveTo	124
OutText	124
OutTextXY	124
PieSlice	124
PutImage	124
PutPixel	125
Rectangle	125
RegisterBGIDriver	125

RegisterBGIFont	125
RestoreCRTMode	125
Sector	126
SetActivePage	126
SetAllPalette	126
SetAspectRatio	126
SetBkColor	126
SetColor	127
SetFillPattern	127
SetFillStyle	127
SetGraphBufSize	127
SetGraphMode	128
SetLineStyle	128
SetPalette	128
SetRGBPalette	128
SetTextJustify	129
SetTextStyle	129
SetUserCharSize	129
SetViewPort	130
SetVisualPage	130
SetWriteMode	130
TextHeight	130
TextWidth	130
8.5 Target specific issues	131
DOS	131
WINDOWS	131
LINUX	131
9 The HEAPTRC unit.	132
9.1 Purpose	132
9.2 Usage	132
9.3 Constants, Types and variables	133
9.4 Functions and procedures	134
DumpHeap	134
MarkHeap	134
SetExtraInfo	135
SetHeapTraceOutput	136
10 The IPC unit.	137
10.1 Types, Constants and variables :	137
Variables	137

Constants	137
Types	138
10.2 Functions and procedures	142
ftok	142
msgget	142
msgsnd	142
msgrcv	143
msgctl	143
semget	146
semop	146
semctl	147
shmget	151
shmat	152
shmdt	152
shmctl	152
11 The LINUX unit.	155
11.1 Type, Variable and Constant declarations	155
Types	155
Variables	158
Constants	159
11.2 Function list by category	162
File Input/Output routines	162
General File handling routines	163
Pipes, FIFOs and streams	164
Directory handling routines	164
Process handling	164
Signals	165
System information	165
Terminal functions	166
Port input/output	166
Utility routines	166
11.3 Functions and procedures	167
Access	167
Alarm	168
AssignPipe	168
AssignStream	169
BaseName	171
CFMakeRaw	171
CFSetISpeed	172

CFSetOSpeed	172
Chown	172
Chmod	173
Clone	174
CloseDir	176
CreateShellArgV	176
DirName	177
Dup	177
Dup2	178
EpochToLocal	179
Execl	179
Execle	180
Execlp	181
Execv	182
Execve	182
Execvp	183
FD_ZERO	184
FD_Clr	184
FD_IsSet	185
FD_Set	185
fdClose	185
fdFlush	185
fdOpen	186
fdRead	187
fdSeek	188
fdTruncate	188
fdWrite	188
FExpand	189
FLock	189
FNMatch	189
FSearch	190
FSplit	190
FSSStat	191
FStat	192
Fcntl	193
Fcntl	193
Fork	194
FRename	194
GetDate	195
GetDateTime	195

GetDomainName	196
GetEGid	196
GetEUid	197
GetEnv	197
GetEpochTime	197
GetFS	198
GetGid	198
GetHostName	199
GetLocalTimezone	199
GetPid	199
GetPPid	200
GetPriority	200
GetTime	201
GetTimeOfDay	201
GetTimeOfDay	201
GetTimezoneFile	202
GetUid	202
Glob	202
GlobFree	203
IOCtl	203
IOPerm	204
IsATTY	204
S_ISBLK	204
S_ISCHR	205
S_ISDIR	205
S_ISFIFO	205
S_ISLNK	205
S_ISREG	206
S_ISSOCK	206
Kill	206
LStat	207
Link	208
LocalToEpoch	209
MkFifo	210
MMap	210
MUnMap	211
Nice	212
Octal	212
OpenDir	213
pause	214

PClose	214
POpen	214
ReadDir	215
ReadLink	215
ReadPort	217
ReadPortB	217
ReadPortL	217
ReadPortW	218
ReadTimezoneFile	218
SeekDir	218
Select	218
SelectText	219
SetPriority	220
Shell	220
SigAction	221
SigPending	222
SigProcMask	222
SigRaise	222
SigSuspend	223
Signal	223
StringToPPchar	224
SymLink	225
SysInfo	226
TCDrain	227
TCFlow	227
TCFlush	228
TCGetAttr	228
TCGetPGrp	229
TCSendBreak	229
TCSetAttr	229
TCSetPGrp	230
TTYName	230
TellDir	230
Umask	230
Uname	231
UnLink	231
Utime	231
WaitPid	232
WritePort	233
WritePortB	233

WritePortL	233
WritePortW	234
12 The MATH unit	235
12.1 Constants and types	235
12.2 Function list by category	236
Min/max determination	236
Angle conversion	236
Trigonometric functions	236
Hyperbolic functions	237
Exponential and logarithmic functions	237
Number converting	237
Statistical functions	237
Geometrical functions	238
12.3 Functions and Procedures	238
arccos	238
arcosh	238
arcsin	239
arctan2	240
arsinh	240
artanh	241
ceil	241
cosh	242
cotan	242
cycletorad	242
degtograd	243
degtorad	243
floor	244
frexp	244
gradtodeg	245
gradtorad	245
hypot	246
intpower	246
ldexp	247
lnxp1	247
log10	248
log2	248
logn	249
max	249
maxIntValue	250

maxvalue	250
mean	251
meanandstddev	252
min	253
minIntValue	253
minvalue	254
momentskewkurtosis	255
norm	255
popnstddev	256
popnvariance	257
power	257
radto cycle	258
radto deg	258
radto grad	259
randg	259
sincos	260
sinh	261
stddev	261
sum	262
sumofsquares	262
sumsandsquares	263
tan	264
tanh	264
totalvariance	265
variance	265
13 The MMX unit	267
13.1 Variables, Types and constants	267
13.2 Functions and Procedures	268
Emms	268
14 The MsMouse unit	269
14.1 Constants, types and variables	269
14.2 Functions and procedures	270
GetLastButtonPress	270
GetLastButtonRelease	271
GetMouseState	271
HideMouse	272
InitMouse	273
LPressed	273
MPressed	274

RPressed	274
SetMouseAscii	274
SetMouseHideWindow	275
SetMousePos	275
SetMouseShape	276
SetMouseSpeed	277
SetMouseWindow	277
SetMouseXRange	278
SetMouseYRange	278
ShowMouse	278
15 The Objects unit.	280
15.1 Constants	280
15.2 Types	281
15.3 Procedures and Functions	282
NewStr	282
DisposeStr	283
Abstract	283
RegisterObjects	283
RegisterType	283
LongMul	285
LongDiv	285
15.4 TRect	285
TRect.Empty	286
TRect.Equals	286
TRect.Contains	287
TRect.Copy	287
TRect.Union	287
TRect.Intersect	288
TRect.Move	289
TRect.Grow	289
TRect.Assign	290
15.5 TObject	290
TObject.Init	290
TObject.Free	291
TObject.Done	291
15.6 TStream	292
TStream.Get	292
TStream.StrRead	293
TStream.GetPos	294

TStream.GetSize	294
TStream.ReadStr	295
TStream.Open	295
TStream.Close	295
TStream.Reset	296
TStream.Flush	296
TStream.Truncate	296
TStream.Put	296
TStream.StrWrite	297
TStream.WriteStr	297
TStream.Seek	297
TStream.Error	297
TStream.Read	298
TStream.Write	298
TStream.CopyFrom	298
15.7 TDosStream	299
TDosStream.Init	300
TDosStream.Done	300
TDosStream.Close	300
TDosStream.Truncate	301
TDosStream.Seek	301
TDosStream.Open	302
TDosStream.Read	303
TDosStream.Write	303
15.8 TBufStream	303
TBufStream.Init	304
TBufStream.Done	304
TBufStream.Close	305
TBufStream.Flush	305
TBufStream.Truncate	306
TBufStream.Seek	306
TBufStream.Open	306
TBufStream.Read	306
TBufStream.Write	307
15.9 TMemoryStream	307
TMemoryStream.Init	307
TMemoryStream.Done	308
TMemoryStream.Truncate	308
TMemoryStream.Read	308
TMemoryStream.Write	309

15.10TCollection	309
TCollection.Init	310
TCollection.Load	310
TCollection.Done	311
TCollection.At	311
TCollection.IndexOf	312
TCollection.GetItem	313
TCollection.LastThat	313
TCollection.FirstThat	314
TCollection.Pack	314
TCollection.FreeAll	315
TCollection.DeleteAll	316
TCollection.Free	317
TCollection.Insert	317
TCollection.Delete	318
TCollection.AtFree	318
TCollection.FreeItem	319
TCollection.AtDelete	319
TCollection.ForEach	320
TCollection.SetLimit	321
TCollection.Error	321
TCollection.AtPut	321
TCollection.AtInsert	322
TCollection.Store	322
TCollection.PutItem	323
15.11TSortedCollection	323
TSortedCollection.Init	324
TSortedCollection.Load	324
TSortedCollection.KeyOf	324
TSortedCollection.IndexOf	325
TSortedCollection.Compare	325
TSortedCollection.Search	326
TSortedCollection.Insert	327
TSortedCollection.Store	328
15.12TStringCollection	328
TStringCollection.GetItem	328
TStringCollection.Compare	329
TStringCollection.FreeItem	329
TStringCollection.PutItem	330
15.13TStrCollection	330

TStrCollection.GetItem	330
TStrCollection.Compare	330
TStrCollection.FreeItem	331
TStrCollection.PutItem	331
15.14 TUnSortedStrCollection	332
TUnSortedStrCollection.Insert	332
15.15 TResourceCollection	333
TResourceCollection.KeyOf	333
TResourceCollection.GetItem	333
TResourceCollection.FreeItem	334
TResourceCollection.PutItem	334
15.16 TResourceFile	334
TResourceFile Fields	334
TResourceFile.Init	335
TResourceFile.Done	335
TResourceFile.Count	335
TResourceFile.KeyAt	335
TResourceFile.Get	335
TResourceFile.SwitchTo	336
TResourceFile.Flush	336
TResourceFile.Delete	336
TResourceFile.Put	336
15.17 TStringList	336
TStringList.Load	337
TStringList.Done	337
TStringList.Get	337
15.18 TStrListMaker	337
TStrListMaker.Init	338
TStrListMaker.Done	338
TStrListMaker.Put	338
TStrListMaker.Store	338
16 The PORTS unit	339
16.1 Introduction	339
16.2 Types, constants and variables	339
Types	339
variables	340
17 The PRINTER unit.	341
17.1 Types, Constants and variables :	341
17.2 Procedures and functions	341

AssignLst	341
18 The SOCKETS unit.	343
18.1 Types, Constants and variables :	343
18.2 Functions and Procedures	344
Accept	344
Accept	346
Accept	346
Accept	346
Bind	346
Bind	347
Connect	347
Connect	348
Connect	348
Connect	348
GetPeerName	349
GetSocketName	349
GetSocketOptions	350
Listen	350
Recv	351
Send	351
SetSocketOptions	352
Shutdown	352
Sock2File	352
Sock2Text	353
Socket	353
SocketPair	353
Str2UnixSockAddr	353
19 The STRINGS unit.	354
19.1 Functions and procedures.	354
StrAlloc	354
StrCat	354
StrComp	355
StrCopy	355
StrDispose	356
StrECopy	356
StrEnd	357
StrIComp	357
StrLCat	358
StrLComp	358

StrLCopy	359
StrLen	359
StrLComp	360
StrLower	360
StrMove	361
StrNew	361
StrPas	362
StrPCopy	362
StrPos	363
StrRScan	363
StrScan	363
StrUpper	364
20 The SYSUTILS unit.	365
20.1 Constants and types	365
20.2 Function list by category	368
String functions	368
Formatting strings	369
File input/output routines	370
File handling routines	370
Date/time routines	371
20.3 Miscellaneous conversion routines	372
20.4 Date and time functions	372
Date and time formatting characters	372
TDateTime	373
Date	373
DateTimeToFileDate	374
DateTimeToStr	374
DateTimeToString	375
DateTimeToSystemTime	376
DateTimeToTimeStamp	376
DateToStr	377
DayOfWeek	377
DecodeDate	377
DecodeTime	378
EncodeDate	378
EncodeTime	379
FileDateToDateTime	380
FormatDateTime	380
IncMonth	381

IsLeapYear	381
MSecsToTimeStamp	382
Now	382
StrToDate	383
StrToDateTime	383
StrToTime	384
SystemTimeToDateTime	385
Time	385
TimeStampToDateTime	386
TimeStampToMSecs	386
TimeToStr	387
20.5 Disk functions	387
AddDisk (Linux only)	387
CreateDir	387
DiskFree	388
DiskSize	389
GetCurrentDir	389
RemoveDir	390
SetCurrentDir	390
20.6 File handling functions	390
ChangeFileExt	390
DeleteFile	391
DoDirSeparators	391
ExpandFileName	392
ExpandUNCFileName	392
ExtractFileDir	393
ExtractFileDrive	393
ExtractFileExt	393
ExtractFileName	394
ExtractFilePath	394
ExtractRelativePath	394
FileAge	395
FileClose	395
FileCreate	396
FileExists	397
FileGetAttr	397
FileGetDate	398
FileOpen	399
FileRead	399
FileSearch	399

FileSeek	400
FileSetAttr (Not on Linux)	401
FileSetDate (Not on Linux)	401
FileTruncate	401
FileWrite	401
FindClose	402
FindFirst	402
FindNext	403
GetDirs	403
RenameFile	403
SetDirSeparators	404
20.7 PChar functions	404
Introduction	404
StrAlloc	405
StrBufSize	406
StrDispose	406
StrPCopy	406
StrPLCopy	407
StrPas	407
20.8 String handling functions	407
AdjustLineBreaks	407
AnsiCompareStr	408
AnsiCompareText	408
AnsiExtractQuotedStr	409
AnsiLastChar	410
AnsiLowerCase	410
AnsiQuotedStr	411
AnsiStrComp	411
AnsiStrIComp	412
AnsiStrLastChar	413
AnsiStrLComp	413
AnsiStrLIComp	414
AnsiStrLower	415
AnsiStrUpper	416
AnsiUpperCase	416
AppendStr	417
AssignStr	417
BCDToInt	418
CompareMem	419
CompareStr	419

CompareText	420
DisposeStr	421
FloatToStr	421
FloatToStrF	422
FloatToText	423
FmtStr	424
Format	424
FormatBuf	430
IntToHex	430
IntToStr	431
IsValidIdent	431
LastDelimiter	432
LeftStr	432
LoadStr	433
LowerCase	433
NewStr	433
QuotedStr	434
RightStr	434
StrFmt	435
StrLFmt	435
StrToInt	436
StrToIntDef	436
Trim	437
TrimLeft	437
TrimRight	438
UpperCase	439

About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with Free Pascal.

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

Declaration The exact declaration of the function.

Description What does the procedure exactly do ?

Errors What errors can occur.

See Also Cross references to other related functions/commands.

The cross-references come in two flavors:

- References to other functions in this manual. In the printed copy, a number will appear after this reference. It refers to the page where this function is explained. In the on-line help pages, this is a hyperlink, on which you can click to jump to the declaration.
- References to Unix manual pages. (For Linux related things only) they are printed in `type-writer` font, and the number after it is the Unix manual section.

The chapters are ordered alphabetically. The functions and procedures in most cases also, but don't count on it. Use the table of contents for quick lookup.

Chapter 1

The CRT unit.

This chapter describes the CRT unit for Free Pascal, both under DOS LINUX and WINDOWS. The unit was first written for DOS by Florian klämpfl. The unit was ported to LINUX by Mark May¹, and enhanced by Michaël Van Canneyt and Peter Vreman. It works on the LINUX console, and in xterm and rxvt windows under X-Windows. The functionality for both is the same, except that under LINUX the use of an early implementation (versions 0.9.1 and earlier of the compiler) the crt unit automatically cleared the screen at program startup. This chapter is divided in two sections.

- The first section lists the pre-defined constants, types and variables.
- The second section describes the functions which appear in the interface part of the CRT unit.

1.1 Types, Variables, Constants

Color definitions :

```
Black = 0;
Blue = 1;
Green = 2;
Cyan = 3;
Red = 4;
Magenta = 5;
Brown = 6;
LightGray = 7;
DarkGray = 8;
LightBlue = 9;
LightGreen = 10;
LightCyan = 11;
LightRed = 12;
LightMagenta = 13;
Yellow = 14;
White = 15;
Blink = 128;
```

Miscellaneous constants

```
TextAttr: Byte = $07;
```

¹Current e-mail address mmay@dnaco.net

```
TextChar: Char = ' ';
CheckBreak: Boolean = True;
CheckEOF: Boolean = False;
CheckSnow: Boolean = False;
DirectVideo: Boolean = False;
LastMode: Word = 3;
WindMin: Word = $0;
WindMax: Word = $184f;
ScreenWidth = 80;
ScreenHeight = 25;
```

Some variables for compatibility with Turbo Pascal. However, they're not used by Free Pascal.

```
var
  checkbreak : boolean;
  checkeof : boolean;
  checksnow : boolean;
```

The following constants define screen modes on a DOS system:

```
Const
  bw40 = 0;
  co40 = 1;
  bw80 = 2;
  co80 = 3;
  mono = 7;
```

The `TextAttr` variable controls the attributes with which characters are written to screen.

```
var TextAttr : byte;
```

The `DirectVideo` variable controls the writing to the screen. If it is `True`, the the cursor is set via direct port access. If `False`, then the BIOS is used. This is defined under DOS only.

```
var DirectVideo : Boolean;
```

The `Lastmode` variable tells you which mode was last selected for the screen. It is defined on DOS only.

```
var lastmode : Word;
```

1.2 Procedures and Functions

AssignCrt

Declaration: `Procedure AssignCrt (Var F: Text);`

Description: `AssignCrt` Assigns a file `F` to the console. Everything written to the file `F` goes to the console instead. If the console contains a window, everything is written to the window instead.

Errors: None.

See also: [Window \(35\)](#)

Listing: crtex/ex1.pp

```
Program Example1;
uses Crt;

{ Program to demonstrate the AssignCrt function . }

var
  F : Text;
begin
  AssignCrt(F);
  Rewrite(F); { Don't forget to open for output! }
  WriteLn(F, ' This is written to the Assigned File ');
  Close(F);
end.
```

CursorBig

Declaration: Procedure CursorBig ;

Description: Makes the cursor a big rectangle. Not implemented on LINUX.

Errors: None.

See also: CursorOn ([28](#)), CursorOff ([28](#))

ClrEol

Declaration: Procedure ClrEol ;

Description: ClrEol clears the current line, starting from the cursor position, to the end of the window. The cursor doesn't move

Errors: None.

See also: DelLine ([29](#)), InsLine ([30](#)), ClrScr ([28](#))

Listing: crtex/ex9.pp

```
Program Example9;
uses Crt;

{ Program to demonstrate the ClrEol function . }

begin
  Write(' This line will be cleared from the ',
        ' cursor position until the right of the screen ');
  GotoXY(27, WhereY);
  ReadKey;
  ClrEol;
  WriteLn;
end.
```

ClrScr

Declaration: Procedure `ClrScr` ;

Description: `ClrScr` clears the current window (using the current colors), and sets the cursor in the top left corner of the current window.

Errors: None.

See also: [Window \(35\)](#)

Listing: `crtex/ex8.pp`

```
Program Example8;  
uses Crt ;  
  
{ Program to demonstrate the ClrScr function . }  
  
begin  
  Writeln ( ' Press_any_key_to_clear_the_screen ' );  
  ReadKey;  
  ClrScr;  
  Writeln ( ' Have_fun_with_the_cleared_screen ' );  
end.
```

CursorOff

Declaration: Procedure `CursorOff` ;

Description: Switches the cursor off (i.e. the cursor is no longer visible). Not implemented on LINUX.

Errors: None.

See also: [CursorOn \(28\)](#), [CursorBig \(27\)](#)

CursorOn

Declaration: Procedure `CursorOn` ;

Description: Switches the cursor on. Not implemented on LINUX.

Errors: None.

See also: [CursorBig \(27\)](#), [CursorOff \(28\)](#)

Delay

Declaration: Procedure `Delay` (`DTime: Word`);

Description: `Delay` waits a specified number of milliseconds. The number of specified seconds is an approximation, and may be off a lot, if system load is high.

Errors: None

See also: [Sound \(33\)](#), [NoSound \(32\)](#)

Listing: `crtex/ex15.pp`

```
Program Example15;  
uses Crt;  
  
{ Program to demonstrate the Delay function . }  
var  
    i : longint;  
begin  
    WriteLn(' Counting_Down' );  
    for i:=10 downto 1 do  
        begin  
            WriteLn(i);  
            Delay(1000); {Wait one second}  
        end;  
    WriteLn(' BOOM!!!' );  
end.
```

DelLine

Declaration: Procedure DelLine ;

Description: DelLine removes the current line. Lines following the current line are scrolled 1 line up, and an empty line is inserted at the bottom of the current window. The cursor doesn't move.

Errors: None.

See also: ClrEol ([27](#)), InsLine ([30](#)), ClrScr ([28](#))

Listing: crtex/ex11.pp

```
Program Example10;  
uses Crt;  
  
{ Program to demonstrate the InsLine function . }  
  
begin  
    ClrScr;  
    WriteLn;  
    WriteLn(' Line _1' );  
    WriteLn(' Line _2' );  
    WriteLn(' Line _2' );  
    WriteLn(' Line _3' );  
    WriteLn;  
    WriteLn(' Oops, _Line_2_is_listed_twice ,',  
            ' _let ''s_delete_the_line_at_the_cursor_position' );  
    GotoXY(1,3);  
    ReadKey;  
    DelLine;  
    GotoXY(1,10);  
end.
```

GotoXY

Declaration: Procedure GotoXY (X: Byte; Y: Byte);

Description: Positions the cursor at (X,Y), X in horizontal, Y in vertical direction relative to the origin of the current window. The origin is located at (1,1), the upper-left corner of the window.

Errors: None.

See also: WhereX ([35](#)), WhereY ([35](#)), Window ([35](#))

Listing: crtex/ex6.pp

```
Program Example6;  
uses Crt;  
  
{ Program to demonstrate the GotoXY function . }  
  
begin  
  ClrScr;  
  GotoXY(10,10);  
  Write('10,10');  
  GotoXY(70,20);  
  Write('70,20');  
  GotoXY(1,22);  
end.
```

HighVideo

Declaration: Procedure HighVideo ;

Description: HighVideo switches the output to highlighted text. (It sets the high intensity bit of the video attribute)

Errors: None.

See also: TextColor ([34](#)), TextBackground ([33](#)), LowVideo ([31](#)), NormVideo ([32](#))

Listing: crtex/ex14.pp

```
Program Example14;  
uses Crt;  
  
{ Program to demonstrate the LowVideo , HighVideo , NormVideo functions . }  
  
begin  
  LowVideo;  
  WriteLn(' This _is _written _with _LowVideo' );  
  HighVideo;  
  WriteLn(' This _is _written _with _HighVideo' );  
  NormVideo;  
  WriteLn(' This _is _written _with _NormVideo' );  
end.
```

InsLine

Declaration: Procedure InsLine ;

Description: InsLine inserts an empty line at the current cursor position. Lines following the current line are scrolled 1 line down, causing the last line to disappear from the window. The cursor doesn't move.

Errors: None.

See also: [ClrEol \(27\)](#), [DelLine \(29\)](#), [ClrScr \(28\)](#)

Listing: crtex/ex10.pp

```
Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function . }

begin
  ClrScr;
  WriteLn;
  WriteLn(' Line _1');
  WriteLn(' Line _3');
  WriteLn;
  WriteLn(' Oops, _ forgot _Line _2, _ let ' ' s _insert _at _the _cursor _postion ');
  GotoXY(1,3);
  ReadKey;
  InsLine;
  Write(' Line _2');
  GotoXY(1,10);
end.
```

KeyPressed

Declaration: Function KeyPressed : Boolean;

Description: The Keypressed function scans the keyboard buffer and sees if a key has been pressed. If this is the case, **True** is returned. If not, **False** is returned. The **Shift**, **Alt**, **Ctrl** keys are not reported. The key is not removed from the buffer, and can hence still be read after the **KeyPressed** function has been called.

Errors: None.

See also: [ReadKey \(33\)](#)

Listing: crtex/ex2.pp

```
Program Example2;
uses Crt;

{ Program to demonstrate the KeyPressed function . }

begin
  WriteLn(' Waiting _until _a _key _is _pressed ');
  repeat
    until KeyPressed;
  { The key is not Read,
    so it should also be outputted at the commandline }
end.
```

LowVideo

Declaration: Procedure LowVideo ;

Description: LowVideo switches the output to non-highlighted text. (It clears the high intensity bit of the video attribute)

Errors: None.

See also: TextColor (34), TextBackground (33), HighVideo (30), NormVideo (32)

For an example, see HighVideo (30)

NormVideo

Declaration: Procedure NormVideo ;

Description: NormVideo switches the output to the defaults, read at startup. (The defaults are read from the cursor position at startup)

Errors: None.

See also: TextColor (34), TextBackground (33), LowVideo (31), HighVideo (30)

For an example, see HighVideo (30)

NoSound

Declaration: Procedure NoSound ;

Description: Stops the speaker sound. This is not supported in LINUX

Errors: None.

See also: Sound (33)

Listing: crtex/ex16.pp

```
Program Example16;
uses Crt;

{ Program to demonstrate the Sound and NoSound function . }

var
  i : longint;
begin
  WriteLn(' You_will _hear_some_tones_from_your_speaker' );
  while ( i < 15000) do
    begin
      inc( i , 500);
      Sound( i );
      Delay( 100);
    end;
  WriteLn(' Quiet_now!' );
  NoSound; { Stop noise }
end.
```

ReadKey

Declaration: Function ReadKey : Char;

Description: The ReadKey function reads 1 key from the keyboard buffer, and returns this. If an extended or function key has been pressed, then the zero ASCII code is returned. You can then read the scan code of the key with a second ReadKey call. **Remark.** Key mappings under Linux can cause the wrong key to be reported by ReadKey, so caution is needed when using ReadKey.

Errors: None.

See also: KeyPressed ([31](#))

Listing: crtex/ex3.pp

```
Program Example3;
uses Crt;

{ Program to demonstrate the ReadKey function . }

var
  ch : char;
begin
  writeln ( ' Press _Left / Right , _Esc=Quit ' );
  repeat
    ch:=ReadKey;
    case ch of
      #0 : begin
        ch:=ReadKey; {Read ScanCode}
        case ch of
          #75 : WriteLn( ' Left ' );
          #77 : WriteLn( ' Right ' );
        end;
      end;
      #27 : WriteLn( ' ESC' );
    end;
  until ch=#27 {Esc}
end.
```

Sound

Declaration: Procedure Sound (hz : word);

Description: Sounds the speaker at a frequency of hz. This is not supported in LINUX

Errors: None.

See also: NoSound ([32](#))

TextBackground

Declaration: Procedure TextBackground (CL: Byte);

Description: TextBackground sets the background color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: TextColor ([34](#)), HighVideo ([30](#)), LowVideo ([31](#)), NormVideo ([32](#))

Listing: crtex/ex13.pp

```
Program Example13;  
uses Crt;  
  
{ Program to demonstrate the TextBackground function . }  
  
begin  
  TextColor ( White );  
  WriteLn ( ' This _is _written _in _with _the _default _background _color ' );  
  TextBackground ( Green );  
  WriteLn ( ' This _is _written _in _with _a _Green _background ' );  
  TextBackground ( Brown );  
  WriteLn ( ' This _is _written _in _with _a _Brown _background ' );  
  TextBackground ( Black );  
  WriteLn ( ' Back _with _a _black _background ' );  
end.
```

TextColor

Declaration: Procedure TextColor (CL: Byte);

Description: TextColor sets the foreground color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: TextBackground ([33](#)), HighVideo ([30](#)), LowVideo ([31](#)), NormVideo ([32](#))

Listing: crtex/ex12.pp

```
Program Example12;  
uses Crt;  
  
{ Program to demonstrate the TextColor function . }  
  
begin  
  WriteLn ( ' This _is _written _in _the _default _color ' );  
  TextColor ( Red );  
  WriteLn ( ' This _is _written _in _Red ' );  
  TextColor ( White );  
  WriteLn ( ' This _is _written _in _White ' );  
  TextColor ( LightBlue );  
  WriteLn ( ' This _is _written _in _Light _Blue ' );  
end.
```

TextMode

Declaration: procedure TextMode(Mode: Integer);

Description: TextMode sets the textmode of the screen (i.e. the number of lines and columns of the screen).

The lower byte is use to set the VGA text mode.

This procedure is only implemented on DOS.

Errors: None.

See also: Window ([35](#))

WhereX

Declaration: Function WhereX : Byte;

Description: WhereX returns the current X-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: GotoXY ([29](#)), WhereY ([35](#)), Window ([35](#))

Listing: crtex/ex7.pp

```
Program Example7;  
uses Crt;  
  
{ Program to demonstrate the WhereX and WhereY functions . }  
  
begin  
  WriteLn ( ' Cursor _postion : _X=' , WhereX, ' _Y=' , WhereY);  
end.
```

WhereY

Declaration: Function WhereY : Byte;

Description: WhereY returns the current Y-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: GotoXY ([29](#)), WhereX ([35](#)), Window ([35](#))

Listing: crtex/ex7.pp

```
Program Example7;  
uses Crt;  
  
{ Program to demonstrate the WhereX and WhereY functions . }  
  
begin  
  WriteLn ( ' Cursor _postion : _X=' , WhereX, ' _Y=' , WhereY);  
end.
```

Window

Declaration: Procedure Window (X1, Y1, X2, Y2: Byte);

Description: Window creates a window on the screen, to which output will be sent. (X1, Y1) are the coordinates of the upper left corner of the window, (X2, Y2) are the coordinates of the bottom right corner of the window. These coordinates are relative to the entire screen, with the top left corner equal to (1, 1) Further coordinate operations, except for the next Window call, are relative to the window's top left corner.

Errors: None.

See also: GotoXY ([29](#)), WhereX ([35](#)), WhereY ([35](#)), ClrScr ([28](#))

Listing: crtex/ex5.pp

```
Program Example5;
uses Crt;

{ Program to demonstrate the Window function . }

begin
  ClrScr;
  WriteLn( ' Creating _a_window_from_30,10_to_50,20' );
  Window(30,10,50,20);
  WriteLn( ' We_are_now_writing_in_this_small_window_we_just_created,_we_+'
    ' can''t_get_outside_it_when_writing_long_lines_like_this_one' );
  Write( ' Press_any_key_to_clear_the_window' );
  ReadKey;
  ClrScr;
  Write( ' The_window_is_cleared,_press_any_key_to_restore_to_fullscreen' );
  ReadKey;
  { Full Screen is 80x25 }
  Window(1,1,80,25);
  Clrscr;
  WriteLn( ' Back_in_Full_Screen' );
end.
```

Chapter 2

The DOS unit.

This chapter describes the `DOS` unit for Free pascal, both under `DOS`, `OS/2`, `WINDOWS` and `LINUX`. The unit was first written for `DOS` by Florian klämpfl. It was ported to `LINUX` by Mark May¹, and enhanced by Michaël Van Canneyt.

Under non-DOS systems, some of the functionality is lost, as it is either impossible or meaningless to implement it. Other than that, the functionality for all operating systems is the same.

This chapter is divided in three sections:

- The first section lists the pre-defined constants, types and variables.
- The second section gives an overview of all functions available, grouped by category.
- The third section describes the functions which appear in the interface part of the `DOS` unit.

2.1 Types, Variables, Constants

Constants

The `DOS` unit implements the following constants:

```
{Bitmasks for CPU Flags}
fcarry =    $0001;
fparity =   $0004;
fauxiliary = $0010;
fzero =     $0040;
fsign =     $0080;
foverflow = $0800;
{Bitmasks for file attribute}
readonly =  $01;
hidden =    $02;
sysfile =   $04;
volumeid =  $08;
directory = $10;
archive =   $20;
anyfile =   $3F;
fmclosed =  $D7B0;
fminput =   $D7B1;
```

¹Current e-mail address mmay@dnaco.net

```
fmoutput =    $D7B2;
fminout  =    $D7B3;
```

Types

The following string types are defined for easy handling of filenames :

```
ComStr  = String[255];    { For command-lines }
PathStr = String[255];    { For full path for file names }
DirStr  = String[255];    { For Directory and (DOS) drive string }
NameStr = String[255];    { For Name of file }
ExtStr  = String[255];    { For Extension of file }
```

```
SearchRec = Packed Record
  Fill : array[1..21] of byte;
  { Fill replaced with declarations below, for Linux}
  Attr : Byte; {attribute of found file}
  Time : LongInt; {last modify date of found file}
  Size : LongInt; {file size of found file}
  Reserved : Word; {future use}
  Name : String[255]; {name of found file}
  SearchSpec: String[255]; {search pattern}
  NamePos: Word; {end of path, start of name position}
End;
```

Under LINUX, the Fill array is replaced with the following:

```
SearchNum: LongInt; {to track which search this is}
SearchPos: LongInt; {directory position}
DirPtr: LongInt; {directory pointer for reading directory}
SearchType: Byte; {0=normal, 1=open will close}
SearchAttr: Byte; {attribute we are searching for}
Fill: Array[1..07] of Byte; {future use}
```

This is because the searching mechanism on Unix systems is substantially different from DOS's, and the calls have to be mimicked.

```
const
  filerecnamelength = 255;
type
  FileRec = Packed Record
    Handle,
    Mode,
    RecSize : longint;
    _private : array[1..32] of byte;
    UserData : array[1..16] of byte;
    name : array[0..filerecnamelength] of char;
  End;
```

FileRec is used for internal representation of typed and untyped files. Text files are handled by the following types :

```
const
```

```
TextRecNameLength = 256;
TextRecBufSize    = 256;
type
  TextBuf = array[0..TextRecBufSize-1] of char;
  TextRec = Packed Record
    Handle,
    Mode,
    bufsize,
    _private,
    bufpos,
    bufend    : longint;
    bufptr    : ^textbuf;
    openfunc,
    inoutfunc,
    flushfunc,
    closefunc : pointer;
    UserData  : array[1..16] of byte;
    name      : array[0..textrecnamelength-1] of char;
    buffer    : textbuf;
  End;
```

Remark that this is not binary compatible with the Turbo Pascal definition of `TextRec`, since the sizes of the different fields are different.

```
Registers = record
  case i : integer of
    0 : (ax, f1, bx, f2, cx, f3, dx, f4, bp, f5, si,
         f51, di, f6, ds, f7, es, f8, flags, fs, gs : word);
    1 : (al, ah, f9, f10, bl, bh, f11, f12,
         cl, ch, f13, f14, dl, dh : byte);
    2 : (eax, ebx, ecx, edx, ebp, esi, edi : longint);
  End;
```

The `Registers` type is used in the MSDOS call.

```
DateTime = record
  Year: Word;
  Month: Word;
  Day: Word;
  Hour: Word;
  Min: Word;
  Sec: word;
  End;
```

The `DateTime` type is used in `PackTime` ([53](#)) and `UnPackTime` ([55](#)) for setting/reading file times with `GetFTime` ([50](#)) and `SetFTime` ([54](#)).

Variables

```
DosError : integer;
```

The `DosError` variable is used by the procedures in the DOS unit to report errors. It can have the following values :

2	File not found.
3	path not found.
5	Access denied.
6	Invalid handle.
8	Not enough memory.
10	Invalid environment.
11	Invalid format.
18	No more files.

Other values are possible, but are not documented.

2.2 Function list by category

What follows is a listing of the available functions, grouped by category. For each function there is a reference to the page where you can find the function.

File handling

Routines to handle files on disk.

Name	Description	Page
FExpand	Expand filename to full path	45
FindClose	Close finfirst/findnext session	45
FindFirst	Start find of file	46
FindNext	Find next file	47
FSearch	Search for file in a path	47
FSplit	Split filename in parts	47
GetFAttr	Return file attributes	49
GetFTime	Return file time	50
GetLongName	Convert short filename to long filename	51
GetShortName	Convert long filename to short filename	51
SetFAttr	Set file attributes	54
SetFTime	Set file time	54

Directory and disk handling

Routines to handle disk information.

Name	Description	Page
AddDisk	Add disk to list of disks	41
DiskFree	Return size of free disk space	42
DiskSize	Return total disk size	42

Process handling

Functions to handle process information and starting new processes.

Name	Description	Page
DosExitCode	Exit code of last executed program	43
EnvCount	Return number of environment variables	44
EnvStr	Return environment string pair	44
Exec	Execute program	45
GetEnv	Return specified environment string	49

System information

Functions for retrieving and setting general system information such as date and time.

Name	Description	Page
DosVersion	Get OS version	43
GetCBreak	Get setting of control-break handling flag	48
GetDate	Get system date	48
GetIntVec	Get interrupt vector status	51
GetTime	Get system time	51
GetVerify	Get verify flag	52
Intr	Execute an interrupt	52
Keep	Keep process in memory and exit	52
MSDos	Execute MS-dos function call	53
PackTime	Pack time for file time	53
SetCBreak	Set control-break handling flag	54
SetDate	Set system date	54
SetIntVec	Set interrupt vectors	55
SetTime	Set system time	55
SetVerify	Set verify flag	55
SwapVectors	Swap interrupt vectors	55
UnPackTime	Unpack file time	55

2.3 Functions and Procedures

AddDisk

Declaration: Procedure AddDisk (Const S : String);

Description: AddDisk adds a filename S to the internal list of disks. It is implemented for LINUX only. This list is used to determine which disks to use in the DiskFree ([42](#)) and DiskSize ([42](#)) calls. The DiskFree ([42](#)) and DiskSize ([42](#)) functions need a file on the specified drive, since this is required for the statfs system call. The names are added sequentially. The dos initialization code presets the first three disks to:

- ' . ' for the current drive,
- ' /fd0/ . ' for the first floppy-drive.
- ' /fd1/ . ' for the second floppy-drive.
- ' / ' for the first hard disk.

The first call to `AddDisk` will therefore add a name for the second harddisk, The second call for the third drive, and so on until 23 drives have been added (corresponding to drives 'D:' to 'Z:')

Errors: None

See also: `DiskFree` ([42](#)), `DiskSize` ([42](#))

DiskFree

Declaration: `Function DiskFree (Drive: byte) : Int64;`

Description: `DiskFree` returns the number of free bytes on a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the free space on the current drive. Typically, the free space is the size of a disk block, multiplied by the number of free blocks on the disk. **For LINUX only:**

The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the dos unit, and have been preset to :

- ' . ' for the current drive,
- ' /fd0/ . ' for the first floppy-drive.
- ' /fd1/ . ' for the second floppy-drive.
- ' / ' for the first hard disk.

There is room for 1-26 drives. You can add a drive with the `AddDisk` ([41](#)) procedure. These settings can be coded in `dos.pp`, in the initialization part.

Errors: -1 when a failure occurs, or an invalid `drivenr` is given.

See also: `DiskSize` ([42](#)), `AddDisk` ([41](#))

Listing: `dosex/ex6.pp`

```
Program Example6;  
uses Dos;  
  
{ Program to demonstrate the DiskSize and DiskFree function . }  
  
begin  
  WriteLn(' This partition size has ', DiskSize(0), ' bytes ');  
  WriteLn(' Currently ', DiskFree(0), ' bytes are free ');  
end.
```

DiskSize

Declaration: `Function DiskSize (Drive: byte) : Int64;`

Description: `DiskSize` returns the total size (in bytes) of a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy `a:`, 2 for floppy `b:`, etc. A value of 0 returns the size of the current drive. **For LINUX only:**

The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the dos unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive.
- `'/fd1/.'` for the second floppy-drive.
- `'/'` for the first hard disk.

There is room for 1-26 drives. You can add a drive with the `AddDisk` (41) procedure. These settings can be coded in `dos.pp`, in the initialization part.

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: `DiskFree` (42), `AddDisk` (41)

For an example, see `DiskFree` (42).

DosExitCode

Declaration: `Function DosExitCode : Word;`

Description: `DosExitCode` contains (in the low byte) the exit-code of a program executed with the `Exec` call.

Errors: None.

See also: `Exec` (45)

Listing: `dosex/ex5.pp`

```
Program Example5;
uses Dos;

{ Program to demonstrate the Exec and DosExitCode function . }

begin
  {$IFDEF LINUX}
    WriteLn( ' Executing _/ bin / ls _la ' );
    Exec( ' / bin / ls ', '-la' );
  {$ELSE}
    WriteLn( ' Executing _Dir ' );
    Exec( GetEnv( 'COMSPEC' ), ' / C_dir ' );
  {$ENDIF}
  WriteLn( ' Program_returned _with _ExitCode _', DosExitCode );
end.
```

DosVersion

Declaration: `Function DosVersion : Word;`

Description: `DosVersion` returns the DOS version number. On LINUX systems, it returns the Linux version (The first 2 numbers, e.g Linux version 2.1.76 will give you `DosVersion` 2.1)

Errors: None.

See also:

Listing: dosex/ex1.pp

```
Program Example1;
uses Dos;

{ Program to demonstrate the DosVersion function . }

var
    OS      : string [32];
    Version : word;
begin
    {$IFDEF LINUX}
        OS:= 'Linux' ;
    {$ENDIF}
    {$IFDEF DOS}
        OS:= 'Dos' ;
    {$ENDIF}
    Version := DosVersion ;
    WriteLn( ' Current_',OS, '_ version_ is_', Lo( Version ), '.', Hi( Version ));
end.
```

EnvCount

Declaration: Function EnvCount : longint;

Description: EnvCount returns the number of environment variables.

Errors: None.

See also: EnvStr (44), Dos:GetEnv (49)

EnvStr

Declaration: Function EnvStr (Index: integer) : string;

Description: EnvStr returns the Index-th Name=Value pair from the list of environment variables. The index of the first pair is zero.

Errors: The length is limited to 255 characters. This may cause problems under LINUX. The LINUX unit solves this problem.

See also: EnvCount (44), Dos:GetEnv (49)

Listing: dosex/ex13.pp

```
Program Example13;
uses Dos;

{ Program to demonstrate the EnvCount and EnvStr function . }

var
    i : Longint;
```

```
begin
  WriteLn( ' Current_Environment_ is : ' );
  for i := 1 to EnvCount do
    WriteLn( EnvStr( i ) );
end.
```

Exec

Declaration: Procedure Exec (const Path: pathstr; const ComLine: comstr);

Description: Exec executes the program in Path, with the options given by ComLine. After the program has terminated, the procedure returns. The Exit value of the program can be consulted with the DosExitCode function.

Errors: Errors are reported in DosError.

See also: DosExitCode ([43](#))

For an example, see DosExitCode ([43](#))

FExpand

Declaration: Function FExpand (const path: pathstr) : pathstr;

Description: FExpand takes its argument and expands it to a complete filename, i.e. a filename starting from the root directory of the current drive, prepended with the drive-letter (under DOS). The resulting name is converted to uppercase on DOS systems. Under LINUX, the name is left as it is. (filenames are case sensitive under Unix)

Errors: FSplit ([47](#))

See also:

```
Program Example5;
uses Dos;

{ Program to demonstrate the Exec and DosExitCode function . }

begin
{$IFDEF LINUX}
  WriteLn( ' Executing _/ bin / ls _-la ' );
  Exec( ' / bin / ls ', '-la' );
{$ELSE}
  WriteLn( ' Executing _Dir ' );
  Exec( GetEnv( ' COMSPEC ' ), ' / C _dir ' );
{$ENDIF}
  WriteLn( ' Program_returned _with _ExitCode _', DosExitCode );
end.
```

FindClose

Declaration: Procedure FindClose (Var F: SearchRec);

Description: LINUX, WINDOWS and OS/2 **only** FindClose frees any resources associated with the search record F.

Under LINUX, WINDOWS and OS/2 the findfirst/findnext calls have to be mimicked. This call is needed to free any internal resources allocated by the FindFirst ([402](#)) or FindNext ([403](#)) calls.

E.g. on LINUX, an internal table of file descriptors is kept. When using different `searchrecs` at the same time, the system may run out of file descriptors for directories.

The LINUX implementation of the DOS unit therefore keeps a table of open directories, and when the table is full, closes one of the directories, and reopens another. This system is adequate but slow if you use a lot of `searchrecs`. So, to speed up the `findfirst/findnext` system, the `FindClose` call was implemented. When you don't need a `searchrec` any more, you can tell this to the DOS unit by issuing a `FindClose` call. The directory which is kept open for this `searchrec` is then closed, and the table slot freed.

It is recommended to use the LINUX call `Glob` when looking for files on LINUX.

Errors: None.

See also: `Glob` ([202](#)).

FindFirst

Declaration: `Procedure FindFirst (const Path: pathstr; Attr: word; var F: SearchRec);`

Description: `FindFirst` searches the file specified in `Path`, checks the attributes specified in `Attr`. It returns a `SearchRec` record for further searching in `F`. `Path` can contain the wildcard characters `?` (matches any single character) and `*` (matches 0 or more arbitrary characters). In this case `FindFirst` will return the first file which matches the specified criteria. If `DosError` is different from zero, no file(s) matching the criteria was(were) found.

On OS/2, you cannot issue two different `FindFirst` calls. That is, you must close any previous search operation with `FindClose` ([45](#)) before starting a new one. Failure to do so will end in a Run-Time Error 6 (Invalid file handle)

Also, on OS/2, the boolean variable `FileNameCaseSensitive` indicates whether searches are conducted case-sensitive or not. By default, searches are not case sensitive. If the variable is set to `True`, searches on OS/2 are case sensitive.

Errors: Errors are reported in `DosError`.

See also: `FindNext` ([47](#)), `FindClose` ([45](#))

Listing: `dosex/ex7.pp`

```
Program Example7;
uses Dos;

{ Program to demonstrate the FindFirst and FindNext function. }

var
  Dir : SearchRec;
begin
  FindFirst( '*.*', $20, Dir );
  WriteLn( ' FileName'+Space(32), ' FileSize ':9);
  while ( DosError=0) do
    begin
      WriteLn( Dir.Name+Space(40-Length( Dir.Name)), Dir.Size :9);
      FindNext( Dir );
    end;
  FindClose( Dir );
end.
```

FindNext

Declaration: Procedure FindNext (var f: searchRec);

Description: FindNext takes as an argument a SearchRec from a previous FindNext call, or a FindFirst call, and tries to find another file which matches the criteria, specified in the FindFirst call. If DosError is different from zero, no more files matching the criteria were found.

Errors: DosError is used to report errors.

See also: FindFirst (46), FindClose (45)

For an example, see FindFirst (46).

FSearch

Declaration: Function FSearch (Path: pathstr; DirList: string) : pathstr;

Description: FSearch searches the file Path in all directories listed in DirList. The full name of the found file is returned. DirList must be a list of directories, separated by semi-colons (or colons under LINUX). When no file is found, an empty string is returned.

Errors: None.

See also: FExpand (45)

Listing: dosex/ex10.pp

```
Program Example10;
uses Dos;

{ Program to demonstrate the FSearch function. }

var
  s : string;
begin
  s:=FSearch(ParamStr(1), GetEnv('PATH'));
  if s='' then
    WriteLn(ParamStr(1), ' _not_Found_in_PATH')
  else
    WriteLn(ParamStr(1), ' _Found_in_PATH_at_', s);
end.
```

FSplit

Declaration: Procedure FSplit (path: pathstr;
var dir: dirstr; var name: namestr; var ext: extstr);

Description: FSplit splits a full file name into 3 parts : A Path, a Name and an extension (in ext.) The extension is taken to be all letters after the *last* dot (.). For DOS, however, an exception is made when LFNSupport=False, then the extension is defined as all characters after the *first* dot.

Errors: None.

See also: FSearch (47)

Listing: dosex/ex12.pp

```
Program Example12;
uses Dos;

{ Program to demonstrate the FSplit function . }

var
    Path,Name,Ext : string;
begin
    FSplit ( ParamStr(1), Path,Name, Ext );
    WriteLn ( ' Splitted _', ParamStr(1), '_ in : ' );
    WriteLn ( ' Path _', Path );
    WriteLn ( ' Name _', Name );
    WriteLn ( ' Extension : _', Ext );
end.
```

GetCBreak

Declaration: Procedure GetCBreak (var breakvalue: boolean);

Description: GetCBreak gets the status of CTRL-Break checking under DOS. When BreakValue is false, then DOS only checks for the CTRL-Break key-press when I/O is performed. When it is set to True, then a check is done at every system call.

Errors: Under Linux, this exists but is not implemented, i.e. the call does nothing.

See also: SetCBreak ([54](#))

GetDate

Declaration: Procedure GetDate (var year, month, mday, wday: word);

Description: GetDate returns the system's date. Year is a number in the range 1980..2099.mday is the day of the month, wday is the day of the week, starting with Sunday as day 0.

Errors: None.

See also: GetTime ([51](#)),SetDate ([54](#))

Listing: dosex/ex2.pp

```
Program Example2;
uses Dos;

{ Program to demonstrate the GetDate function . }

const
    DayStr: array [0..6] of string [3] = ( 'Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat' );
    MonthStr: array [1..12] of string [3] = ( 'Jan', 'Feb', 'Mar', 'Apr', 'May', 'Jun',
                                              'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec' );

var
    Year, Month, Day, WDay : word;
begin
    GetDate ( Year, Month, Day, WDay );
    WriteLn ( ' Current _date ' );
    WriteLn ( DayStr [WDay], ' _', Day, ' _', MonthStr [Month], ' _', Year, ' . ' );
end.
```

GetEnv

Declaration: `Function GetEnv (EnvVar: String) : String;`

Description: `GetEnv` returns the value of the environment variable `EnvVar`. Under `LINUX`, case is important when looking for `EnvVar`. When there is no environment variable `EnvVar` defined, an empty string is returned.

Errors: None.

See also: `EnvCount` ([44](#)), `EnvStr` ([44](#))

Listing: `dosex/ex14.pp`

```
Program Example14;  
uses Dos;  
  
{ Program to demonstrate the GetEnv function . }  
  
begin  
  WriteLn( ' Current_PATH_is _' , GetEnv( ' PATH' ) );  
end.
```

GetFAttr

Declaration: `Procedure GetFAttr (var F; var Attr: word);`

Description: `GetFAttr` returns the file attributes of the file-variable `f`. `F` can be a untyped or typed file, or of type `Text`. `f` must have been assigned, but not opened. The attributes can be examined with the following constants :

- `ReadOnly` = 01h
- `Hidden` = 02h
- `SysFile` = 04h
- `VolumeId` = 08h
- `Directory` = 10h
- `Archive` = 20h

Under `LINUX`, supported attributes are:

- `Directory`
- `ReadOnly` if the current process doesn't have access to the file.
- `Hidden` for files whose name starts with a dot (`' . '`).

Errors: Errors are reported in `DosError`

See also: `SetFAttr` ([54](#))

Listing: `dosex/ex8.pp`

```
Program Example8;  
uses Dos;  
  
{ Program to demonstrate the GetFAttr function . }
```

```
var
  Attr : Word;
  f     : File;
begin
  Assign(f, ParamStr(1));
  GetFAttr(f, Attr);
  WriteLn(' File _', ParamStr(1), '_ has _attribute _', Attr);
  if (Attr and $20) <> 0 then WriteLn('_Archive');
  if (Attr and $10) <> 0 then WriteLn('_Directory');
  if (Attr and $4) <> 0 then WriteLn('_Read-Only');
  if (Attr and $2) <> 0 then WriteLn('_System');
  if (Attr and $1) <> 0 then WriteLn('_Hidden');
end.
```

GetFTime

Declaration: Procedure GetFTime (var F; var Time: longint);

Description: GetFTime returns the modification time of a file. This time is encoded and must be decoded with UnPackTime. F must be a file type, which has been assigned, and opened.

Errors: Errors are reported in DosError

See also: SetFTime ([54](#)), PackTime ([53](#)), UnPackTime ([55](#))

Listing: dosex/ex9.pp

```
Program Example9;
uses Dos;

{ Program to demonstrate the GetFTime function . }

Function L0(w: word): string;
var
  s : string;
begin
  Str(w, s);
  if w < 10 then
    L0 := '0' + s
  else
    L0 := s;
end;

var
  f     : File;
  Time  : Longint;
  DT    : DateTime;
begin
  Assign(f, ParamStr(1));
  Reset(f);
  GetFTime(f, Time);
  Close(f);
  UnPackTime(Time, DT);
  Write (' File _', ParamStr(1), '_ is _last _modified _on _');
  Writeln ( L0(DT.Month), '-', L0(DT.Day), '-', DT.Year,
            '_ at _', L0(DT.Hour), ':', L0(DT.Min));
end.
```

GetIntVec

Declaration: `Procedure GetIntVec (IntNo: byte; var Vector: pointer);`

Description: `GetIntVec` returns the address of interrupt vector `IntNo`.

Errors: Under non- DOS operating systems, this call does nothing.

See also: `SetIntVec` ([55](#))

GetLongName

Declaration: `function GetLongName(var p : String) : boolean;`

Description: This function is only implemented in the GO32V2 version of Free Pascal.

`GetLongName` changes the filename `p` to a long filename if the DOS call to do this is successful. The resulting string is the long file name corresponding to the short filename `p`.

The function returns `True` if the DOS call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the DOS call was not successful, `False` is returned.

See also: `GetShortName` ([51](#))

GetShortName

Declaration: `function GetShortName(var p : String) : boolean;`

Description: This function is only implemented in the GO32V2 version of Free Pascal.

`GetShortName` changes the filename `p` to a short filename if the DOS call to do this is successful. The resulting string is the short file name corresponding to the long filename `p`.

The function returns `True` if the DOS call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the DOS call was not successful, `False` is returned.

See also: `GetLongName` ([51](#))

GetTime

Declaration: `Procedure GetTime (var hour, minute, second, sec100: word);`

Description: `GetTime` returns the system's time. `Hour` is on a 24-hour time scale. `sec100` is in hundredth of a second.

Errors: None.

See also: `GetDate` ([48](#)), `SetTime` ([55](#))

Listing: `dosex/ex3.pp`

```
Program Example3;
uses Dos;

{ Program to demonstrate the GetTime function . }

Function L0(w: word): string ;
var
    s : string ;
begin
    Str(w, s);
    if w<10 then
        L0:= '0' +s
    else
        L0:=s;
    end;

var
    Hour, Min, Sec, HSec : word;
begin
    GetTime ( Hour , Min , Sec, HSec);
    WriteLn ( ' Current_time ' );
    WriteLn ( L0(Hour), ':' , L0( Min), ':' , L0( Sec));
end.
```

GetVerify

Declaration: Procedure GetVerify (var verify: boolean);

Description: GetVerify returns the status of the verify flag under DOS. When Verify is True, then DOS checks data which are written to disk, by reading them after writing. If Verify is False, then data written to disk are not verified.

Errors: Under LINUX, Verify is always True.

See also: SetVerify ([55](#))

Intr

Declaration: Procedure Intr (IntNo: byte; var Regs: registers);

Description: Intr executes a software interrupt number IntNo (must be between 0 and 255), with processor registers set to Regs. After the interrupt call returned, the processor registers are saved in Regs.

Errors: Under LINUX this call does nothing, because interrupts are managed by the kernel. The only allowed interrupt is 80h, the Linux kernel entry interrupt.

See also: MSDos ([53](#)), see the LINUX unit.

Keep

Declaration: Procedure Keep (ExitCode: word);

Description: Keep terminates the program, but stays in memory. This is used for TSR (Terminate Stay Resident) programs which catch some interrupt. ExitCode is the same parameter as the Halt function takes.

Errors: Under non-DOS operating systems, this call does nothing.

See also: `Halt ()`

MSDos

Declaration: `Procedure MSDos (var regs: registers);`

Description: `MSDos` executes an MS-DOS call (int 21h). This is the same as doing a `Intr` call with an interrupt number of 21h.

Errors: None.

See also: `Intr` ([52](#))

PackTime

Declaration: `Procedure PackTime (var T: datetime; var P: longint);`

Description: `UnPackTime` converts the date and time specified in `T` to a packed-time format which can be fed to `SetFTime`.

Errors: None.

See also: `SetFTime` ([54](#)), `FindFirst` ([46](#)), `FindNext` ([47](#)), `UnPackTime` ([55](#))

Listing: `dosex/ex4.pp`

```
Program Example4;
uses Dos;

{ Program to demonstrate the PackTime and UnPackTime functions. }

var
  DT   : DateTime;
  Time : longint;
begin
  with DT do
    begin
      Year:=1998;
      Month:=11;
      Day:=11;
      Hour:=11;
      Min:=11;
      Sec:=11;
    end;
  PackTime(DT, Time);
  WriteLn(' Packed_Time _:_', Time);
  UnPackTime(Time, DT);
  WriteLn(' Unpacked_Again :' );
  with DT do
    begin
      WriteLn(' Year_ _', Year);
      WriteLn(' Month_ _', Month);
      WriteLn(' Day_ _ _', Day);
      WriteLn(' Hour_ _ _', Hour);
      WriteLn(' Min_ _ _', Min);
      WriteLn(' Sec_ _ _', Sec);
    end;
end.
```

SetCBreak

Declaration: Procedure SetCBreak (breakvalue: boolean);

Description: SetCBreak sets the status of CTRL-Break checking under DOS. When BreakValue is false, then DOS only checks for the CTRL-Break key-press when I/O is performed. When it is set to True, then a check is done at every system call.

Errors: Under Linux, this call exists but is not implemented, i.e. it does nothing.

See also: GetCBreak ([48](#))

SetDate

Declaration: Procedure SetDate (year, month, day: word);

Description: SetDate sets the system's internal date. Year is a number between 1980 and 2099.

Errors: On a LINUX machine, this is not implemented (although a procedure exists, it just doesn't do anything. The setting of the date is a root-only privilege, and is hence not implemented.

See also: Dos:GetDate ([48](#)), SetTime ([55](#))

SetFAttr

Declaration: Procedure SetFAttr (var F; Attr: word);

Description: SetFAttr sets the file attributes of the file-variable F. F can be a untyped or typed file, or of type Text. F must have been assigned, but not opened. The attributes can be a sum of the following constants:

- ReadOnly = 01h
- Hidden = 02h
- SysFile = 04h
- VolumeId = 08h
- Directory = 10h
- Archive = 20h
- AnyFile = 3fh

Errors: Errors are reported in DosError. Under LINUX the call exists, but is not implemented, i.e. it does nothing.

See also: GetFAttr ([49](#))

SetFTime

Declaration: Procedure SetFTime (var F; Time: longint);

Description: SetFTime sets the modification time of a file, this time is encoded and must be encoded with PackTime. F must be a file type, which has been assigned, and opened.

Errors: Errors are reported in DosError

See also: GetFTime ([50](#)), PackTime ([53](#)), UnPackTime ([55](#))

SetIntVec

Declaration: Procedure SetIntVec (IntNo: byte; Vector: pointer);

Description: SetIntVec sets interrupt vector IntNo to Vector. Vector should point to an interrupt procedure.

Errors: Under non- DOS operating systems, this call does nothing.

See also: GetIntVec ([51](#))

SetTime

Declaration: Procedure SetTime (hour, minute, second, sec100: word);

Description: SetTime sets the system's internal clock. The Hour parameter is on a 24-hour time scale.

Errors: this call exists, but is not implemented on LINUX, as setting the time is a root-only privilege.

See also: Dos:GetTime ([51](#)), SetDate ([54](#))

SetVerify

Declaration: Procedure SetVerify (verify: boolean);

Description: SetVerify sets the status of the verify flag under DOS. When Verify is True, then DOS checks data which are written to disk, by reading them after writing. If Verify is False, then data written to disk are not verified.

Errors: Under LINUX, Verify is always True.

See also: SetVerify ([55](#))

SwapVectors

Declaration: Procedure SwapVectors ;

Description: SwapVectors swaps the contents of the internal table of interrupt vectors with the current contents of the interrupt vectors. This is called typically in before and after an Exec call.

Errors: Under LINUX this call does nothing, as the interrupt vectors are managed by the kernel.

See also: Exec ([45](#)), SetIntVec ([55](#))

UnPackTime

Declaration: Procedure UnPackTime (p: longint; var T: datetime);

Description: UnPackTime converts the file-modification time in p to a DateTime record. The file-modification time can be returned by GetFTime, FindFirst or FindNext calls.

Errors: None.

See also: GetFTime ([50](#)), FindFirst ([46](#)), FindNext ([47](#)), PackTime ([53](#))

For an example, see PackTime ([53](#)).

Chapter 3

The DXELOAD unit

3.1 Introduction

The dxeload unit was implemented by Pierre Müller for DOS, it allows to load a DXE file (an object file with 1 entry point) into memory and return a pointer to the entry point.

It exists only for DOS.

3.2 Constants, types and variables

Constants

The following constant is the magic number, found in the header of a DXE file.

```
DXE_MAGIC = $31455844;
```

Types

The following record describes the header of a DXE file. It is used to determine the magic number of the DXE file and number of relocations that must be done when the object file is loaded in memory.

```
dx_header = record
    magic,
    symbol_offset,
    element_size,
    nrelocs      : longint;
end;
```

3.3 Functions and Procedures

dx_load

Declaration: `function dx_load(filename : string) : pointer;`

Description: `dx_load` loads the contents of the file `filename` into memory. It performs the necessary relocations in the object code, and returns then a pointer to the entry point of the code.

Errors: If an error occurs during the load or relocations, `Nil` is returned.

For an example, see the `emu387` unit in the RTL.

Chapter 4

The EMU387 unit

The `emu387` unit was written by Pierre Müller for DOS. It sets up the coprocessor emulation for FPC under DOS. It is not necessary to use this unit on other OS platforms because they either simply do not run on a machine without coprocessor, or they provide the coprocessor emulation themselves.

It shouldn't be necessary to use the function in this unit, it should be enough to place this unit in the `uses` clause of your program to enable the coprocessor emulation under DOS. The unit initialization code will try and load the coprocessor emulation code and initialize it.

4.1 Functions and procedures

npxsetup

Declaration: `procedure npxsetup(prog_name : string);`

Description: `npxsetup` checks whether a coprocessor is found. If not, it loads the file `wmemu387.dxe` into memory and initializes the code in it.

If the environment variable `387` is set to `N`, then the emulation will be loaded, even if there is a coprocessor present. If the variable doesn't exist, or is set to any other value, the unit will try to detect the presence of a coprocessor unit.

The function searches the file `wmemu387.dxe` in the following way:

- 1.If the environment variable `EMU387` is set, then it is assumed to point at the `wmemu387.dxe` file.
- 2.if the environment variable `EMU387` does not exist, then the function will take the path part of `prog_name` and look in that directory for the file `wmemu387.dxe`.

It should never be necessary to call this function, because the initialization code of the unit contains a call to the function with as an argument `paramstr(0)`. This means that you should deliver the file `wmemu387.dxe` together with your program.

Errors: If there is an error, an error message is printed to standard error, and the program is halted, since any floating-point code is bound to fail anyhow.

Chapter 5

The GETOPTS unit.

This document describes the GETOPTS unit for Free Pascal. It was written for LINUX by Michaël Van Canneyt. It now also works for all supported platforms.

The getopt unit provides a mechanism to handle command-line options in a structured way, much like the GNU getopt mechanism. It allows you to define the valid options for your program, and the unit will then parse the command-line options for you, and inform you of any errors.

The chapter is divided in 2 sections:

- The first section lists types, constants and variables from the interface part of the unit.
- The second section describes the functions defined in the unit.

5.1 Types, Constants and variables :

Constants

`No_Argument=0` : Specifies that a long option does not take an argument.

`Required_Argument=1` : Specifies that a long option needs an argument.

`Optional_Argument=2` : Specifies that a long option optionally takes an argument.

`EndOfOptions=#255` : Returned by `getopt`, `getlongopts` to indicate that there are no more options.

Types

```
TOption = record
  Name      : String;
  Has_arg   : Integer;
  Flag      : PChar;
  Value     : Char;
end;
POption = ^TOption;
```

The `option` type is used to communicate the long options to `GetLongOpts`. The `Name` field is the name of the option. `Has_arg` specifies if the option wants an argument, `Flag` is a pointer to a `char`, which is set to `Value`, if it is non-nil. `POption` is a pointer to a `Option` record. It is used as an argument to the `GetLongOpts` function.

Variables

OptArg: String Is set to the argument of an option, if the option needs one.

Optind: Longint Is the index of the current `paramstr()`. When all options have been processed, `optind` is the index of the first non-option parameter. This is a read-only variable. Note that it can become equal to `paramcount+1`

OptErr: Boolean Indicates whether `getopt()` prints error messages.

OptOpt: Char In case of an error, contains the character causing the error.

5.2 Procedures and functions

GetLongOpts

Declaration: `Function GetLongOpts (Shortopts : String, LongOpts : POption; var Longint : Longint) : Char;`

Description: Returns the next option found on the command-line, taking into account long options as well. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable. `ShortOptions` is a string containing all possible one-letter options. (see [Getopt \(60\)](#) for its description and use) `LongOpts` is a pointer to the first element of an array of `Option` records, the last of which needs a name of zero length. The function tries to match the names even partially (i.e. `-app` will match e.g. the `append` option), but will report an error in case of ambiguity. If the option needs an argument, set `Has_arg` to `Required_argument`, if the option optionally has an argument, set `Has_arg` to `Optional_argument`. If the option needs no argument, set `Has_arg` to zero. Required arguments can be specified in two ways :

1. Pasted to the option : `-option=value`
2. As a separate argument : `-option value`

Optional arguments can only be specified through the first method.

Errors: see [Getopt \(60\)](#), [getopt \(3\)](#)

See also: [Getopt](#)

Getopt

Declaration: `Function Getopt (Shortopts : String) : Char;`

Description: Returns the next option found on the command-line. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable. `ShortOptions` is a string containing all possible one-letter options. If a letter is followed by a colon (:), then that option needs an argument. If a letter is followed by 2 colons, the option has an optional argument. If the first character of `shortoptions` is a `'+'` then options following a non-option are regarded as non-options (standard Unix behavior). If it is a `'-'`, then all non-options are treated as arguments of a option with character `#0`. This is useful for applications that require their options in the exact order as they appear on the command-line. If the first character of `shortoptions` is none of the above, options and non-options are permuted, so all non-options are behind all options. This allows options and non-options to be in random order on the command line.

Errors: Errors are reported through giving back a `'?'` character. `OptOpt` then gives the character which caused the error. If `OptErr` is `True` then `getopt` prints an error-message to `stdout`.

See also: [GetLongOpts \(60\)](#), [getopt \(3\)](#)

```
program testopt;  
  
{ Program to depmonstrate the getopt function. }  
  
{  
  Valid calls to this program are  
  optex --verbose --add me --delete you  
  optex --append --create child  
  optex -ab -c me -d you  
  and so on  
}  
uses getopt;  
  
var c : char;  
    optionindex : Longint;  
    theopts : array[1..7] of TOption;  
  
begin  
  with theopts[1] do  
    begin  
      name := 'add';  
      has_arg := 1;  
      flag := nil;  
      value := #0;  
    end;  
  with theopts[2] do  
    begin  
      name := 'append';  
      has_arg := 0;  
      flag := nil;  
      value := #0;  
    end;  
  with theopts[3] do  
    begin  
      name := 'delete';  
      has_arg := 1;  
      flag := nil;  
      value := #0;  
    end;  
  with theopts[4] do  
    begin  
      name := 'verbose';  
      has_arg := 0;  
      flag := nil;  
      value := #0;  
    end;  
  with theopts[5] do  
    begin  
      name := 'create';  
      has_arg := 1;  
      flag := nil;  
      value := 'c';  
    end;  
  with theopts[6] do  
    begin  
      name := 'file';  
      has_arg := 1;
```

```
    flag := nil ;
    value := #0;
end;
with theopts [7] do
begin
    name:= '' ;
    has_arg:=0;
    flag := nil ;
end;
c:=#0;
repeat
    c:=getlongopts ( 'abc:d:012' , @theargs [1], optionindex );
    case c of
        '1', '2', '3', '4', '5', '6', '7', '8', '9' :
            begin
                writeln ( 'Got_optind _:_', c)
            end;
        #0 : begin
                write ( 'Long_option _:_', theopts [ optionindex ]. name);
                if theopts [ optionindex ]. has_arg>0 then
                    writeln ( '_ With_value _:_', optarg )
                else
                    writeln
                end;
            'a' : writeln ( ' Option_a.' );
            'b' : writeln ( ' Option_b.' );
            'c' : writeln ( ' Option_c:_:', optarg );
            'd' : writeln ( ' Option_d:_:', optarg );
            '?', ':' : writeln ( ' Error _with_opt _:_', optopt );
        end; { case }
    until c=endofoptions;
if optind<=paramcount then
begin
    write ( ' Non_options _:_');
    while optind<=paramcount do
        begin
            write ( paramstr ( optind ), ' _' );
            inc ( optind )
        end;
    writeln
end
end.
```

Chapter 6

The GPM unit

6.1 Introduction

The GPM unit implements an interface to `filelibgpm`, the console program for mouse handling. This unit was created by Peter Vreman, and is only available on `LINUX`.

When this unit is used, your program is linked to the C libraries, so you must take care of the C library version. Also, it will only work with version 1.17 or higher of the `libgpm` library.

6.2 Constants, types and variables

constants

The following constants are used to denote filenames used by the library:

```
_PATH_VARRUN = '/var/run/';  
_PATH_DEV    = '/dev/';  
GPM_NODE_DIR = _PATH_VARRUN;  
GPM_NODE_DIR_MODE = 0775;  
GPM_NODE_PID  = '/var/run/gpm.pid';  
GPM_NODE_DEV  = '/dev/gpmctl';  
GPM_NODE_CTL  = GPM_NODE_DEV;  
GPM_NODE_FIFO = '/dev/gpmdata';
```

The following constants denote the buttons on the mouse:

```
GPM_B_LEFT    = 4;  
GPM_B_MIDDLE  = 2;  
GPM_B_RIGHT   = 1;
```

The following constants define events:

```
GPM_MOVE = 1;  
GPM_DRAG = 2;  
GPM_DOWN = 4;  
GPM_UP   = 8;  
GPM_SINGLE = 16;  
GPM_DOUBLE = 32;
```



```
GPM_TRIPLE = 64;  
GPM_MFLAG = 128;  
GPM_HARD = 256;  
GPM_ENTER = 512;  
GPM_LEAVE = 1024;
```

The following constants are used in defining margins:

```
GPM_TOP = 1;  
GPM_BOT = 2;  
GPM_LFT = 4;  
GPM_RGT = 8;
```

Types

The following general types are defined:

```
TGpmEtype = longint;  
TGpmMargin = longint;
```

The following type describes an event; it is passed in many of the gpm functions.

```
PGpmEvent = ^TGpmEvent;  
TGpmEvent = record  
  buttons : byte;  
  modifiers : byte;  
  vc : word;  
  dx : word;  
  dy : word;  
  x : word;  
  y : word;  
  EventType : TGpmEType;  
  clicks : longint;  
  margin : TGpmMargin;  
end;  
TGpmHandler=function(var event:TGpmEvent;clientdata:pointer):longint;cdecl;
```

The following types are used in connecting to the gpm server:

```
PGpmConnect = ^TGpmConnect;  
TGpmConnect = record  
  eventMask : word;  
  defaultMask : word;  
  minMod : word;  
  maxMod : word;  
  pid : longint;  
  vc : longint;  
end;
```

The following type is used to define *regions of interest*

```
PGpmRoi = ^TGpmRoi;  
TGpmRoi = record
```

```
xMin : integer;  
xMax : integer;  
yMin : integer;  
yMax : integer;  
minMod : word;  
maxMod : word;  
eventMask : word;  
owned : word;  
handler : TGpmHandler;  
clientdata : pointer;  
prev : PGpmRoi;  
next : PGpmRoi;  
end;
```

Variables

The following variables are imported from the `gpm` library

```
gpm_flag          : longint;cvar;external;  
gpm_fd            : longint;cvar;external;  
gpm_hflag         : longint;cvar;external;  
gpm_morekeys     : Longbool;cvar;external;  
gpm_zerobased    : Longbool;cvar;external;  
gpm_visiblepointer : Longbool;cvar;external;  
gpm_mx           : longint;cvar;external;  
gpm_my           : longint;cvar;external;  
gpm_timeout      : TTimeVal;cvar;external;  
_gpm_buf         : array[0..0] of char;cvar;external;  
_gpm_arg         : ^word;cvar;external;  
gpm_handler      : TGpmHandler;cvar;external;  
gpm_data         : pointer;cvar;external;  
gpm_roi_handler  : TGpmHandler;cvar;external;  
gpm_roi_data     : pointer;cvar;external;  
gpm_roi          : PGpmRoi;cvar;external;  
gpm_current_roi  : PGpmRoi;cvar;external;  
gpm_consolefd    : longint;cvar;external;  
Gpm_HandleRoi    : TGpmHandler;cvar;external;
```

6.3 Functions and procedures

Gpm_AnyDouble

Declaration: `function Gpm_AnyDouble(EventType : longint) : boolean;`

Description: `Gpm_AnyDouble` returns `True` if `EventType` contains the `GPM_DOUBLE` flag, `False` otherwise.

Errors: None.

See also: `Gpm_StrictSingle` ([70](#)), `Gpm_AnySingle` ([66](#)), `Gpm_StrictDouble` ([70](#)), `Gpm_StrictTriple` ([71](#)), `Gpm_AnyTriple` ([66](#))

Gpm_AnySingle

Declaration: `function Gpm_AnySingle(EventType : longint) : boolean;`

Description: `Gpm_AnySingle` returns `True` if `EventType` contains the `GPM_SINGLE` flag, `False` otherwise.

Errors:

See also: `Gpm_StrictSingle` (70), `Gpm_AnyDouble` (65), `Gpm_StrictDouble` (70), `Gpm_StrictTriple` (71), `Gpm_AnyTriple` (66)

Gpm_AnyTriple

Declaration: `function Gpm_AnyTriple(EventType : longint) : boolean;`

Description:

Errors:

See also: `Gpm_StrictSingle` (70), `Gpm_AnyDouble` (65), `Gpm_StrictDouble` (70), `Gpm_StrictTriple` (71), `Gpm_AnySingle` (66)

Gpm_Close

Declaration: `function Gpm_Close:longint;cdecl;external;`

Description: `Gpm_Close` closes the current connection, and pops the connection stack; this means that the previous connection becomes active again.

The function returns -1 if the current connection is not the last one, and it returns 0 if the current connection is the last one.

Errors: None.

See also: `Gpm_Open` (69)

for an example, see `Gpm_GetEvent` (67).

Gpm_FitValues

Declaration: `function Gpm_FitValues(var x,y:longint):longint;cdecl;external;`

Description: `Gpm_fitValues` changes `x` and `y` so they fit in the visible screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValuesM` (66),

Gpm_FitValuesM

Declaration: `function Gpm_FitValuesM(var x,y:longint; margin:longint):longint;cdecl;external;`

Description: `Gpm_FitValuesM` changes `x` and `y` so they fit in the margin indicated by `margin`. If `margin` is -1, then the values are fitted to the screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValues` (66),

Gpm_GetEvent

Declaration: `function Gpm_GetEvent(var Event:TGpmEvent):longint;cdecl;external;`

Description: `Gpm_GetEvent` Reads an event from the file descriptor `gpm_fd`. This file is only for internal use and should never be called by a client application.

It returns 1 on succes, and -1 on failue.

Errors: On error, -1 is returned.

See also: `seeflGpm_GetSnapshotGpmGetSnapshot`

Listing: gpmex/gpmex.pp

```
program gpmex;

{
  Example program to demonstrate the use of the gpm unit.
}

uses gpm;

var
  connect : TGPMConnect;
  event : tgpmevent;

begin
  connect.EventMask:=GPM_MOVE or GPM_DRAG or GPM_DOWN or GPM_UP;
  connect.DefaultMask:=0;
  connect.MinMod:=0;
  connect.MaxMod:=0;
  if Gpm_Open(connect,0)=-1 then
    begin
      Writeln('No_mouse_handler_present. ');
      Halt(1);
    end;
  Writeln('Click_right_button_to_end. ');
  Repeat
    gpm_getevent(Event);
    With Event do
      begin
        Write('Pos_=( ' , X , ' , ' , Y , ' )_Buttons_:_(' );
        if ( buttons and Gpm_b_left)<>0 then
          write(' left ');
        if ( buttons and Gpm_b_right)<>0 then
          write(' right ');
        if ( buttons and Gpm_b_middle)<>0 then
          Write(' middle ');
        Write(')_Event_:_(' );
        Case EventType and $F of
          GPM_MOVE: write(' Move' );
          GPM_DRAG: write(' Drag' );
          GPM_DOWN: write(' Down' );
          GPM_UP: write(' Up' );
        end;
        Writeln;
      end;
  Until ( Event.Buttons and gpm_b_right)<>0;
  gpm_close;
```

end.

Gpm_GetLibVersion

Declaration: `function Gpm_GetLibVersion(var where:longint):pchar;cdecl;external;`

Description: `Gpm_GetLibVersion` returns a pointer to a version string, and returns in `where` an integer representing the version. The version string represents the version of the gpm library.

The return value is a `pchar`, which should not be deallocated, i.e. it is not on the heap.

Errors: None.

See also: `Gpm_GetServerVersion` ([68](#))

Gpm_GetServerVersion

Declaration: `function Gpm_GetServerVersion(var where:longint):pchar;cdecl;external;`

Description: `Gpm_GetServerVersion` returns a pointer to a version string, and returns in `where` an integer representing the version. The version string represents the version of the gpm server program.

The return value is a `pchar`, which should not be deallocated, i.e. it is not on the heap.

Errors: If the gpm program is not present, then the function returns `Nil`

See also: `Gpm_GetLibVersion` ([68](#))

Gpm_GetSnapshot

Declaration: `function Gpm_GetSnapshot(var Event:TGpmEvent):longint;cdecl;external;`

Description: `Gpm_GetSnapshot` returns the picture that the server has of the current situation in `Event`. This call will not read the current situation from the mouse file descriptor, but returns a buffered version. The meaning of the fields is as follows:

x,ycurrent position of the cursor.

dx,dysize of the window.

vcnumber of the virtual console.

modifierskeyboard shift state.

buttonsbuttons which are currently pressed.

clicksnumber of clicks (0,1 or 2).

The function returns the number of mouse buttons, or -1 if this information is not available.

Errors: None.

See also: `Gpm_GetEvent` ([67](#))

Gpm_LowerRoi

Declaration: `function Gpm_LowerRoi(which:PGpmRoi; after:PGpmRoi):PGpmRoi;cdecl;external;`

Description: `Gpm_LowerRoi` lowers the region of interest which after `after`. If `after` is `Nil`, the region of interest is moved to the bottom of the stack.

The return value is the new top of the region-of-interest stack.

Errors: None.

See also: `Gpm_RaiseRoi` (70), `Gpm_PopRoi` (69), `Gpm_PushRoi` (69)

Gpm_Open

Declaration: `function Gpm_Open(var Conn:TGpmConnect; Flag:longint):longint;cdecl;external;`

Description: `Gpm_Open` opens a new connection to the mouse server. The connection is described by the fields of the `Conn` record:

EventMaskA bitmask of the events the program wants to receive.

DefaultMaskA bitmask to tell the library which events get their default treatment (text selection).

minModthe minimum amount of modifiers needed by the program.

maxModthe maximum amount of modifiers needed by the program.

if `Flag` is 0, then the application only receives events that come from its own terminal device. If it is negative it will receive all events. If the value is positive then it is considered a console number to which to connect.

The return value is -1 on error, or the file descriptor used to communicate with the client. Under an X-Term the return value is -2.

Errors: On Error, the return value is -1.

See also: `Gpm_Open` (69)

for an example, see `Gpm_GetEvent` (67).

Gpm_PopRoi

Declaration: `function Gpm_PopRoi(which:PGpmRoi):PGpmRoi;cdecl;external;`

Description: `Gpm_PopRoi` pops the topmost region of interest from the stack. It returns the next element on the stack, or `Nil` if the current element was the last one.

Errors: None.

See also: `Gpm_RaiseRoi` (70), `Gpm_LowerRoi` (69), `Gpm_PushRoi` (69)

Gpm_PushRoi

Declaration: `function Gpm_PushRoi(x1:longint; y1:longint; X2:longint; Y2:longint; mask:longint; fun:TGpmHandler; xtradata:pointer):PGpmRoi;cdecl;external;`

Description: `Gpm_PushRoi` puts a new *region of interest* on the stack. The region of interest is defined by a rectangle described by the corners (`X1`, `Y1`) and (`X2`, `Y2`).

The `mask` describes which events the handler `fun` will handle; `ExtraData` will be put in the `xtradata` field of the `TGPM_Roi` record passed to the `fun` handler.

Errors: None.

See also: [Gpm_RaiseRoi \(70\)](#), [Gpm_PopRoi \(69\)](#), [Gpm_LowerRoi \(69\)](#)

Gpm_RaiseRoi

Declaration: `function Gpm_RaiseRoi(which:PGpmRoi; before:PGpmRoi):PGpmRoi;cdecl;external;`

Description: `Gpm_RaiseRoi` raises the *region of interest* which till it is on top of region `before`. If `before` is nil then the region is put on top of the stack. The returned value is the top of the stack.

Errors: None.

See also: [Gpm_PushRoi \(69\)](#), [Gpm_PopRoi \(69\)](#), [Gpm_LowerRoi \(69\)](#)

Gpm_Repeat

Declaration: `function Gpm_Repeat(millisecond:longint):longint;cdecl;external;`

Description: `Gpm_Repeat` returns 1 if no mouse event arrives in the next `millisecond` milliseconds, it returns 0 otherwise.

Errors: None.

See also: [Gpm_GetEvent \(67\)](#)

Gpm_StrictDouble

Declaration: `function Gpm_StrictDouble(EventType : longint) : boolean;`

Description: `Gpm_StrictDouble` returns true if `EventType` contains only a doubleclick event, False otherwise.

Errors: None.

See also: [Gpm_StrictSingle \(70\)](#), [Gpm_AnyTriple \(66\)](#), [Gpm_AnyDouble \(65\)](#), [Gpm_StrictTriple \(71\)](#), [Gpm_AnySingle \(66\)](#)

Gpm_StrictSingle

Declaration: `function Gpm_StrictSingle(EventType : longint) : boolean;`

Description: `Gpm_StrictDouble` returns True if `EventType` contains only a singleclick event, False otherwise.

Errors: None.

See also: [Gpm_AnyTriple \(66\)](#), [Gpm_StrictDouble \(70\)](#), [Gpm_AnyDouble \(65\)](#), [Gpm_StrictTriple \(71\)](#), [Gpm_AnySingle \(66\)](#)

Gpm_StrictTriple

Declaration: `function Gpm_StrictTriple(EventType : longint) : boolean;`

Description: `Gpm_StrictTriple` returns true if `EventType` contains only a triple click event, False otherwise.

Errors: None.

See also: `Gpm_AnyTriple` ([66](#)), `Gpm_StrictDouble` ([70](#)), `Gpm_AnyDouble` ([65](#)), `Gpm_StrictSingle` ([70](#)), `Gpm_AnySingle` ([66](#))

Chapter 7

The GO32 unit

This chapter of the documentation describe the GO32 unit for the Free Pascal compiler under DOS. It was donated by Thomas Schatzl (tom_at_work@geocities.com), for which my thanks. This unit was first written for DOS by Florian Klaempfl. This chapter is divided in four sections. The first two sections are an introduction to the GO32 unit. The third section lists the pre-defined constants, types and variables. The last section describes the functions which appear in the interface part of the GO32 unit.

7.1 Introduction

These docs contain information about the GO32 unit. Only the GO32V2 DPMI mode is discussed by me here due to the fact that new applications shouldn't be created with the older GO32V1 model. The go32v2 version is much more advanced and better. Additionally a lot of functions only work in DPMI mode anyway. I hope the following explanations and introductions aren't too confusing at all. If you notice an error or bug send it to the FPC mailing list or directly to me. So let's get started and happy and error free coding I wish you....

Thomas Schatzl, 25. August 1998

7.2 Protected mode memory organization

What is DPMI

The DOS Protected Mode Interface helps you with various aspects of protected mode programming. These are roughly divided into descriptor handling, access to DOS memory, management of interrupts and exceptions, calls to real mode functions and other stuff. Additionally it automatically provides swapping to disk for memory intensive applications. A DPMI host (either a Windows DOS box or CWSDPMI.EXE) provides these functions for your programs.

Selectors and descriptors

Descriptors are a bit like real mode segments; they describe (as the name implies) a memory area in protected mode. A descriptor contains information about segment length, its base address and the attributes of it (i.e. type, access rights, ...). These descriptors are stored internally in a so-called descriptor table, which is basically an array of such descriptors. Selectors are roughly an index into this table. Because these 'segments' can be up to 4 GB in size, 32 bits aren't sufficient anymore to describe a single memory location like in real mode. 48 bits are now needed to do this, a 32 bit address and a 16 bit sized selector. The GO32 unit provides the tseginfo record to store such a

pointer. But due to the fact that most of the time data is stored and accessed in the %ds selector, FPC assumes that all pointers point to a memory location of this selector. So a single pointer is still only 32 bits in size. This value represents the offset from the data segment base address to this memory location.

FPC specialities

The %ds and %es selector MUST always contain the same value or some system routines may crash when called. The %fs selector is preloaded with the DOSMEMSELECTOR variable at startup, and it MUST be restored after use, because again FPC relies on this for some functions. Luckily we asm programmers can still use the %gs selector for our own purposes, but for how long ? See also: [get_cs \(88\)](#), [get_ds \(88\)](#), [gett_ss \(95\)](#), [allocate_ldt_descriptors \(81\)](#), [free_ldt_descriptor \(87\)](#), [segment_to_descriptor \(101\)](#), [get_next_selector_increment_value \(90\)](#), [get_segment_base_address \(94\)](#), [set_segment_base_address \(104\)](#), [set_segment_limit \(104\)](#), [create_code_segment_alias_descriptor \(84\)](#)

DOS memory access

DOS memory is accessed by the predefined `dosmemselector` selector; the GO32 unit additionally provides some functions to help you with standard tasks, like copying memory from heap to DOS memory and the likes. Because of this it is strongly recommended to use them, but you are still free to use the provided standard memory accessing functions which use 48 bit pointers. The third, but only thought for compatibility purposes, is using the `mem[]`-arrays. These arrays map the whole 1 Mb DOS space. They shouldn't be used within new programs. To convert a segment:offset real mode address to a protected mode linear address you have to multiply the segment by 16 and add its offset. This linear address can be used in combination with the DOSMEMSELECTOR variable. See also: [dosmemget \(86\)](#), [dosmemput \(86\)](#), [dosmemmove \(86\)](#), [dosmemfillchar \(84\)](#), [dosmemfillword \(85\)](#), `mem[]`-arrays, [seg_move \(102\)](#), [seg_fillchar \(100\)](#), [seg_fillword \(101\)](#).

I/O port access

The I/O port access is done via the various [inportb \(97\)](#), [outportb \(99\)](#) functions which are available. Additionally Free Pascal supports the Turbo Pascal `PORT[]`-arrays but it is by no means recommended to use them, because they're only for compatibility purposes. See also: [outportb \(99\)](#), [inportb \(97\)](#), `PORT[]`-arrays

Processor access

These are some functions to access various segment registers (%cs, %ds, %ss) which makes your work a bit easier. See also: [get_cs \(88\)](#), [get_ds \(88\)](#), [get_ss \(95\)](#)

Interrupt redirection

Interrupts are program interruption requests, which in one or another way get to the processor; there's a distinction between software and hardware interrupts. The former are explicitly called by an 'int' instruction and are a bit comparable to normal functions. Hardware interrupts come from external devices like the keyboard or mouse. Functions that handle hardware interrupts are called handlers.

Handling interrupts with DPMI

The interrupt functions are real-mode procedures; they normally can't be called in protected mode without the risk of a protection fault. So the DPMI host creates an interrupt descriptor table for the application. Initially all software interrupts (except for int 31h, 2Fh and 21h function 4Ch) or external hardware interrupts are simply directed to a handler that reflects the interrupt in real-mode, i.e. the DPMI host's default handlers switch the CPU to real-mode, issue the interrupt and switch back to protected mode. The contents of general registers and flags are passed to the real mode handler and the modified registers and flags are returned to the protected mode handler. Segment registers and stack pointer are not passed between modes.

Protected mode interrupts vs. Real mode interrupts

As mentioned before, there's a distinction between real mode interrupts and protected mode interrupts; the latter are protected mode programs, while the former must be real mode programs. To call a protected mode interrupt handler, an assembly 'int' call must be issued, while the other is called via the `realintr()` or `intr()` function. Consequently, a real mode interrupt then must either reside in DOS memory (<1MB) or the application must allocate a real mode callback address via the `get_rm_callback()` function.

Creating own interrupt handlers

Interrupt redirection with FPC pascal is done via the `set_pm_interrupt()` for protected mode interrupts or via the `set_rm_interrupt()` for real mode interrupts.

Disabling interrupts

The GO32 unit provides the two procedures `disable()` and `enable()` to disable and enable all interrupts.

Hardware interrupts

Hardware interrupts are generated by hardware devices when something unusual happens; this could be a keypress or a mouse move or any other action. This is done to minimize CPU time, else the CPU would have to check all installed hardware for data in a big loop (this method is called 'polling') and this would take much time. A standard IBM-PC has two interrupt controllers, that are responsible for these hardware interrupts: both allow up to 8 different interrupt sources (IRQs, interrupt requests). The second controller is connected to the first through IRQ 2 for compatibility reasons, e.g. if controller 1 gets an IRQ 2, he hands the IRQ over to controller 2. Because of this up to 15 different hardware interrupt sources can be handled. IRQ 0 through IRQ 7 are mapped to interrupts 8h to Fh and the second controller (IRQ 8 to 15) is mapped to interrupt 70h to 77h. All of the code and data touched by these handlers MUST be locked (via the various locking functions) to avoid page faults at interrupt time. Because hardware interrupts are called (as in real mode) with interrupts disabled, the handler has to enable them before it returns to normal program execution. Additionally a hardware interrupt must send an EOI (end of interrupt) command to the responsible controller; this is accomplished by sending the value 20h to port 20h (for the first controller) or A0h (for the second controller). The following example shows how to redirect the keyboard interrupt.

```
{ $ASMMODE ATT }  
{ $MODE FPC }
```

uses

`crt ,`

```
go32;

const
    kbdint = $9;

var
    oldint9_handler : tseginfo;
    newint9_handler : tseginfo;

    clickproc : pointer;
    backupDS : Word; external name '___v2prt0_ds_alias';

procedure int9_handler; assembler;
asm
    cli
    pushl %ds
    pushl %es
    pushl %fs
    pushl %gs
    pushal
    movw %cs:backupDS, %ax
    movw %ax, %ds
    movw %ax, %es
    movw dosmemselector, %ax
    movw %ax, %fs
    call *clickproc
    popal
    popl %gs
    popl %fs
    popl %es
    popl %ds
    ljmp %cs:oldint9_handler
end;
procedure int9_dummy; begin end;

procedure clicker;
begin
    sound(500); delay(10); nosound;
end;
procedure clicker_dummy; begin end;

procedure install_click;
begin
    clickproc := @clicker;
    lock_data(clickproc, sizeof(clickproc));
    lock_data(dosmemselector, sizeof(dosmemselector));

    lock_code(@clicker,
        longint(@clicker_dummy) - longint(@clicker));
    lock_code(@int9_handler,
        longint(@int9_dummy) - longint(@int9_handler));
    newint9_handler.offset := @int9_handler;
    newint9_handler.segment := get_cs;
    get_pm_interrupt(kbdint, oldint9_handler);
    set_pm_interrupt(kbdint, newint9_handler);
end;

procedure remove_click;
```

```
begin
    set_pm_interrupt(kbdint, oldint9_handler);
    unlock_data(dosmemselector, sizeof(dosmemselector));
    unlock_data(clickproc, sizeof(clickproc));

    unlock_code(@clicker,
                longint(@clicker_dummy) - longint(@clicker));
    unlock_code(@int9_handler,
                longint(@int9_dummy) - longint(@int9_handler));
end;

var
    ch : char;

begin
    install_click;
    Writeln('Enter any message. Press return when finished');
    while (ch <> #13) do begin
        ch := readkey; write(ch);
    end;
    remove_click;
end.
```

Software interrupts

Ordinarily, a handler installed with `set_pm_interrupt` (102) only services software interrupts that are executed in protected mode; real mode software interrupts can be redirected by `set_rm_interrupt` (103). See also `set_rm_interrupt` (103), `get_rm_interrupt` (93), `set_pm_interrupt` (102), `get_pm_interrupt` (90), `lock_data` (98), `lock_code` (98), `enable` (87), `disable` (84), `outportb` (99) Executing software interrupts Simply execute a `realintr()` call with the desired interrupt number and the supplied register data structure. But some of these interrupts require you to supply them a pointer to a buffer where they can store data to or obtain data from in memory. These interrupts are real mode functions and so they only can access the first Mb of linear address space, not FPC's data segment. For this reason FPC supplies a pre-initialized DOS memory location within the GO32 unit. This buffer is internally used for DOS functions too and so it's contents may change when calling other procedures. It's size can be obtained with `tb_size` (104) and it's linear address via `transfer_buffer` (105). Another way is to allocate a completely new DOS memory area via the `global_dos_alloc` (95) function for your use and supply its real mode address. See also: `tb_size` (104), `transfer_buffer` (105), `global_dos_alloc` (95), `global_dos_free` (97), `realintr` (100) The following examples illustrate the use of software interrupts.

```
uses
    go32;

var
    r : trealregs;

begin
    r.ah := $30;
    r.al := $01;
    realintr($21, r);
    Writeln('DOS_v', r.al, '.', r.ah, '_detected');
end.
```

```
uses
```

```
    crt ,
    go32;

var
    r : trealregs;
    axreg : Word;

    oldint21h : tseginfo;
    newint21h : tseginfo;
procedure int21h_handler; assembler;
asm
    cmpw $0x3001, %ax
    jne . LCallOld
    movw $0x3112, %ax
    iret

.LCallOld:
    ljmp %cs: oldint21h
end;

procedure resume;
begin
    Writeln;
    Write('--_press_any_key_to_resume_--'); readkey;
    gotoxy(1, wherey); clrEOL;
end;

begin
    clrscr;
    Writeln('Executing_real_mode_interrupt');
    resume;
    r.ah := $30; r.al := $01; realintr($21, r);
    Writeln('DOS_v', r.al, '.', r.ah, '_detected');
    resume;
    Writeln('Executing_protected_mode_interrupt_without_our_own',
            '_handler');
    Writeln;
    asm
        movb $0x30, %ah
        movb $0x01, %al
        int $0x21
        movw %ax, axreg
    end;
    Writeln('DOS_v', r.al, '.', r.ah, '_detected');
    resume;
    Writeln('As_you_can_see_the_DPMI_hosts_default_protected_mode',
            '_handler');
    Writeln('simply_redirects_it_to_the_real_mode_handler');
    resume;
    Writeln('Now_exchanging_the_protected_mode_interrupt_with_our_',
            'own_handler');
    resume;

    newint21h.offset := @int21h_handler;
    newint21h.segment := get_cs;
    get_pm_interrupt($21, oldint21h);
    set_pm_interrupt($21, newint21h);
```

```
Writeln ( ' Executing _real _mode _interrupt _again ' );
resume;
r.ah := $30; r.al := $01; realintr ($21, r);
Writeln ( 'DOS_v', r.al, '.', r.ah, '_detected' );
Writeln;
Writeln ( ' See, _it _didn''t _change _in _any _way.' );
resume;
Writeln ( ' Now _calling _protected _mode _interrupt ' );
resume;
asm
    movb $0x30, %ah
    movb $0x01, %al
    int $0x21
    movw %ax, axreg
end;
Writeln ( 'DOS_v', lo ( axreg ), '.', hi ( axreg ), '_detected' );
Writeln;
Writeln ( ' Now _you _can _see _that _there''s _a _distinction _between_',
    ' the _two _ways _of _calling _interrupts ... ' );
set_pm_interrupt ($21, oldint21h);
end.
```

Real mode callbacks

The callback mechanism can be thought of as the converse of calling a real mode procedure (i.e. interrupt), which allows your program to pass information to a real mode program, or obtain services from it in a manner that's transparent to the real mode program. In order to make a real mode callback available, you must first get the real mode callback address of your procedure and the selector and offset of a register data structure. This real mode callback address (this is a segment:offset address) can be passed to a real mode program via a software interrupt, a DOS memory block or any other convenient mechanism. When the real mode program calls the callback (via a far call), the DPMS host saves the registers contents in the supplied register data structure, switches into protected mode, and enters the callback routine with the following settings:

- interrupts disabled
- %CS:%EIP = 48 bit pointer specified in the original call to `get_rm_callback` ([91](#))
- %DS:%ESI = 48 bit pointer to to real mode SS:SP
- %ES:%EDI = 48 bit pointer of real mode register data structure.
- %SS:%ESP = locked protected mode stack
- All other registers undefined

The callback procedure can then extract its parameters from the real mode register data structure and/or copy parameters from the real mode stack to the protected mode stack. Recall that the segment register fields of the real mode register data structure contain segment or paragraph addresses that are not valid in protected mode. Far pointers passed in the real mode register data structure must be translated to virtual addresses before they can be used with a protected mode program. The callback procedure exits by executing an IRET with the address of the real mode register data structure in %ES:%EDI, passing information back to the real mode caller by modifying the contents of the real mode register data structure and/or manipulating the contents of the real mode stack. The callback procedure is responsible for setting the proper address for resumption of real mode execution into the real mode register data structure; typically, this is accomplished by extracting the return address from

the real mode stack and placing it into the %CS:%EIP fields of the real mode register data structure. After the IRET, the DPMI host switches the CPU back into real mode, loads ALL registers with the contents of the real mode register data structure, and finally returns control to the real mode program. All variables and code touched by the callback procedure **MUST** be locked to prevent page faults. See also: [get_rm_callback \(91\)](#), [free_rm_callback \(87\)](#), [lock_code \(98\)](#), [lock_data \(98\)](#)

7.3 Types, Variables and Constants

Constants

Constants returned by `get_run_mode`

Tells you under what memory environment (e.g. memory manager) the program currently runs.

```
rm_unknown = 0; { unknown }
rm_raw     = 1; { raw (without HIMEM) }
rm_xms     = 2; { XMS (for example with HIMEM, without EMM386) }
rm_vcpi    = 3; { VCPI (for example HIMEM and EMM386) }
rm_dpmi    = 4; { DPMI (for example \dos box or 386Max) }
```

Note: GO32V2 *always* creates DPMI programs, so you need a suitable DPMI host like CWS-DPMI.EXE or a Windows DOS box. So you don't need to check it, these constants are only useful in GO32V1 mode.

Processor flags constants

They are provided for a simple check with the flags identifier in the `trealregs` type. To check a single flag, simply do an AND operation with the flag you want to check. It's set if the result is the same as the flag value.

```
const carryflag = $001;
parityflag      = $004;
auxcarryflag    = $010;
zeroflag        = $040;
signflag        = $080;
trapflag        = $100;
interruptflag   = $200;
directionflag   = $400;
overflowflag    = $800;
```

Predefined types

```
type tmeminfo = record
    available_memory : Longint;
    available_pages  : Longint;
    available_lockable_pages : Longint;
    linear_space     : Longint;
    unlocked_pages   : Longint;
    available_physical_pages : Longint;
    total_physical_pages : Longint;
    free_linear_space : Longint;
    max_pages_in_paging_file : Longint;
```



```
        reserved : array[0..2] of Longint;  
end;
```

Holds information about the memory allocation, etc. NOTE: The value of a field is -1 (0ffffffh) if

Table 7.1: Record description

Record entry	Description
available_memory	Largest available free block in bytes.
available_pages	Maximum unlocked page allocation in pages
available_lockable_pages	Maximum locked page allocation in pages.
linear_space	Linear address space size in pages.
unlocked_pages	Total number of unlocked pages.
available_physical_pages	Total number of free pages.
total_physical_pages	Total number of physical pages.
free_linear_space	Free linear address space in pages.
max_pages_in_paging_file	Size of paging file/partition in pages.

the value is unknown, it's only guaranteed, that `available_memory` contains a valid value. The size of the pages can be determined by the `get_page_size()` function.

```
type  
trealregs = record  
  case Integer of  
    1: { 32-bit }  
      (EDI, ESI, EBP, Res, EBX, EDX, ECX, EAX: Longint;  
       Flags, ES, DS, FS, GS, IP, CS, SP, SS: Word);  
    2: { 16-bit }  
      (DI, DI2, SI, SI2, BP, BP2, R1, R2: Word;  
       BX, BX2, DX, DX2, CX, CX2, AX, AX2: Word);  
    3: { 8-bit }  
      (stuff: array[1..4] of Longint;  
       BL, BH, BL2, BH2, DL, DH, DL2, DH2, CL,  
       CH, CL2, CH2, AL, AH, AL2, AH2: Byte);  
    4: { Compat }  
      (RealEDI, RealESI, RealEBP, RealRES, RealEBX,  
       RealEDX, RealECX, RealEAX: Longint;  
       RealFlags, RealES, RealDS, RealFS, RealGS,  
       RealIP, RealCS, RealSP, RealSS: Word);  
  end;  
registers = trealregs;
```

These two types contain the data structure to pass register values to a interrupt handler or real mode callback.

```
type tseginfo = record  
  offset : Pointer; segment : Word; end;
```

This record is used to store a full 48-bit pointer. This may be either a protected mode selector:offset address or in real mode a segment:offset address, depending on application. See also: Selectors and descriptors, DOS memory access, Interrupt redirection

Variables.

```
var dosmemselector : Word;
```

Selector to the DOS memory. The whole DOS memory is automatically mapped to this single descriptor at startup. This selector is the recommended way to access DOS memory.

```
var int31error : Word;
```

This variable holds the result of a DPMI interrupt call. Any nonzero value must be treated as a critical failure.

7.4 Functions and Procedures

allocate_ldt_descriptors

Declaration: Function `allocate_ldt_descriptors` (`count` : `Word`) : `Word`;

Description: Allocates a number of new descriptors. Parameters:

count: specifies the number of requested unique descriptors.

Return value: The base selector. Notes: The descriptors allocated must be initialized by the application with other function calls. This function returns descriptors with a limit and size value set to zero. If more than one descriptor was requested, the function returns a base selector referencing the first of a contiguous array of descriptors. The selector values for subsequent descriptors in the array can be calculated by adding the value returned by the `get_next_selector_increment_value` (90) function.

Errors: Check the `int31error` variable.

See also: `free_ldt_descriptor` (87), `get_next_selector_increment_value` (90), `segment_to_descriptor` (101), `create_code_segment_alias_descriptor` (84), `set_segment_limit` (104), `set_segment_base_address` (104)

```
{ $mode delphi }  
uses  
    crt ,  
    go32;  
  
const  
    maxx = 80;  
    maxy = 25;  
    bytespercell = 2;  
    screensize = maxx * maxy * bytespercell;  
  
    linB8000 = $B800 * 16;  
  
type  
    string80 = string [80];  
  
var  
    text_save : array [0.. screensize - 1] of byte;  
    text_oldx , text_oldy : Word;  
  
    text_sel : Word;
```

```
procedure status(s : string80);
begin
    gotoxy(1, 1); clreol; write(s); readkey;
end;

procedure selinfo(sel : Word);
begin
    gotoxy(1, 24);
    clreol; writeln(' Descriptor_base_address_:_'$,
        hexstr(get_segment_base_address(sel), 8));
    clreol; write(' Descriptor_limit_:_'$, get_segment_limit(sel));
end;

function makechar(ch : char; color : byte) : Word;
begin
    result := byte(ch) or (color shl 8);
end;

begin
    seg_move(dosmemselector, linB8000, get_ds, longint(@text_save),
        screensize);
    text_oldx := wherex; text_oldy := wherey;
    seg_fillword(dosmemselector, linB8000, screensize div 2,
        makechar('_', Black or (Black shl 4)));
    status(' Creating_selector_' ' text_sel_' ' to_a_part_of_' +
        ' text_screen_memory');
    text_sel := allocate_ldt_descriptors(1);
    set_segment_base_address(text_sel,
        linB8000 + bytespercell * maxx * 1);
    set_segment_limit(text_sel, screensize - 1 - bytespercell *
        maxx * 3);
    selinfo(text_sel);

    status('and_clearing_entire_memory_selected_by_' ' text_sel_' ' +
        ' descriptor');
    seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
        makechar('_', LightBlue shl 4));

    status(' Notice_that_only_the_memory_described_by_the_' +
        ' descriptor_changed_nothing_else');

    status(' Now_reducing_it_' ' s_limit_and_base_and_setting_it_' ' s_' +
        ' described_memory');
    set_segment_base_address(text_sel,
        get_segment_base_address(text_sel) + bytespercell * maxx);
    set_segment_limit(text_sel,
        get_segment_limit(text_sel) - bytespercell * maxx * 2);
    selinfo(text_sel);
    status(' Notice_that_the_base_addr_increased_by_one_line_but_' +
        ' the_limit_decreased_by_2_lines');
    status(' This_should_give_you_the_hint_that_the_limit_is_' +
        ' relative_to_the_base');
    seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
        makechar(#176, LightMagenta or Brown shl 4));

    status(' Now_let_' ' s_get_crazy_and_copy_10_lines_of_data_from_' +
        ' the_previously_saved_screen');
    seg_move(get_ds, longint(@text_save), text_sel,
```

```
maxx * bytespercell * 2, maxx * bytespercell * 10);

status('At last freeing the descriptor and restoring the old '+
      'screen contents..');
status('I hope this little program may give you some hints on '+
      'working with descriptors');
free_ldt_descriptor(text_sel);
seg_move(get_ds, longint(@text_save), dosmemselector,
        linB8000, screensize);
gotoxy(text_oldx, text_oldy);
end.
```

allocate_memory_block

Declaration: Function allocate_memory_block (size:Longint) : Longint;

Description: Allocates a block of linear memory. Parameters:

size: Size of requested linear memory block in bytes.

Returned values: blockhandle - the memory handle to this memory block. Linear address of the requested memory. Notes: WARNING: According to my DPMI docs this function is not implemented correctly. Normally you should also get a blockhandle to this block after successful operation. This handle can then be used to free the memory block afterwards or use this handle for other purposes. Since the function isn't implemented correctly, and doesn't return a blockhandle, the block can't be deallocated and is hence unusable ! This function doesn't allocate any descriptors for this block, it's the applications responsibility to allocate and initialize for accessing this memory.

Errors: Check the int31error variable.

See also: free_memory_block ([87](#))

copyfromdos

Declaration: Procedure copyfromdos (var addr; len : Longint);

Description: Copies data from the pre-allocated DOS memory transfer buffer to the heap. Parameters:

addr: data to copy to.

len: number of bytes to copy to heap.

Notes: Can only be used in conjunction with the DOS memory transfer buffer.

Errors: Check the int31error variable.

See also: tb_size ([104](#)), transfer_buffer ([105](#)), copytodos ([83](#))

copytodos

Declaration: Procedure copytodos (var addr; len : Longint);

Description: Copies data from heap to the pre-allocated DOS memory buffer. Parameters:

addr: data to copy from.

len: number of bytes to copy to DOS memory buffer.

Notes: This function fails if you try to copy more bytes than the transfer buffer is in size. It can only be used in conjunction with the transfer buffer.

Errors: Check the `int31error` variable.

See also: `tb_size` (104), `transfer_buffer` (105), `copyfromdos` (83)

create_code_segment_alias_descriptor

Declaration: Function `create_code_segment_alias_descriptor (seg : Word) : Word;`

Description: Creates a new descriptor that has the same base and limit as the specified descriptor. Parameters:

seg: Descriptor.

Return values: The data selector (alias). Notes: In effect, the function returns a copy of the descriptor. The descriptor alias returned by this function will not track changes to the original descriptor. In other words, if an alias is created with this function, and the base or limit of the original segment is then changed, the two descriptors will no longer map the same memory.

Errors: Check the `int31error` variable.

See also: `allocate_ldt_descriptors` (81), `set_segment_limit` (104), `set_segment_base_address` (104)

disable

Declaration: Procedure `disable ;`

Description: Disables all hardware interrupts by execution a CLI instruction. Parameters: None.

Errors: None.

See also: `enable` (87)

dosmemfillchar

Declaration: Procedure `dosmemfillchar (seg, ofs : Word; count : Longint; c : char);`

Description: Sets a region of DOS memory to a specific byte value. Parameters:

seg: real mode segment.

ofs: real mode offset.

count: number of bytes to set.

c: value to set memory to.

Notes: No range check is performed.

Errors: None.

See also: `dosmempset` (86), `dosmemget` (86), `dosmemmove` (86), `dosmemmove`, `dosmemfillword` (85), `seg_move` (102), `seg_fillchar` (100), `seg_fillword` (101)

```
uses
    crt ,
    go32;

const
    columns = 80;
    rows = 25;
    screensize = rows*columns*2;

    text = '!_ Hello _world _!';

var
    textofs : Longint;
    save_screen : array [0.. screensize-1] of byte;
    curx, cury : Integer;

begin
    randomize;
    dosmemget($B800, 0, save_screen, screensize);
    curx := wherex; cury := wherey;
    gotoxy(1, 1); Write(text);
    textofs := screensize + length(text)*2;
    dosmemmove($B800, 0, $B800, textofs, length(text)*2);
    dosmemfillchar($B800, 0, screensize, #0);
    while (not keypressed) do begin
        dosmemfillchar($B800, textofs + random(length(text))*2 + 1,
            1, char(random(255)));
        dosmemmove($B800, textofs, $B800,
            random(columns)*2+random(rows)*columns*2,
            length(text)*2);
        delay(1);
    end;
    readkey;
    readkey;
    dosmemput($B800, 0, save_screen, screensize);
    gotoxy(curx, cury);
end.
```

dosmemfillword

Declaration: Procedure dosmemfillword (seg, ofs : Word; count : Longint; w : Word);

Description: Sets a region of DOS memory to a specific word value. Parameters:

seg: real mode segment.

ofs: real mode offset.

count: number of words to set.

w: value to set memory to.

Notes: No range check is performed.

Errors: None.

See also: dosmemput (86), dosmemget (86), dosmemmove (86), dosmemfillchar (84), seg_move (102), seg_fillchar (100), seg_fillword (101)

dosmemget

Declaration: Procedure dosmemget (seg : Word; ofs : Word; var data; count : Longint);

Description: Copies data from the DOS memory onto the heap. Parameters:

seg: source real mode segment.

ofs: source real mode offset.

data: destination.

count: number of bytes to copy.

Notes: No range checking is performed.

Errors: None.

See also: dosmempout (86), dosmemmove (86), dosmemfillchar (84), dosmemfillword (85), seg_move (102), seg_fillchar (100), seg_fillword (101)

For an example, see global_dos_alloc (95).

dosmemmove

Declaration: Procedure dosmemmove (sseg, sofs, dseg, dofs : Word; count : Longint);

Description: Copies count bytes of data between two DOS real mode memory locations. Parameters:

sseg: source real mode segment.

sofs: source real mode offset.

dseg: destination real mode segment.

dofs: destination real mode offset.

count: number of bytes to copy.

Notes: No range check is performed in any way.

Errors: None.

See also: dosmempout (86), dosmemget (86), dosmemfillchar (84), dosmemfillword (85), seg_move (102), seg_fillchar (100), seg_fillword (101)

For an example, see seg_fillchar (100).

dosmempout

Declaration: Procedure dosmempout (seg : Word; ofs : Word; var data; count : Longint);

Description: Copies heap data to DOS real mode memory. Parameters:

seg: destination real mode segment.

ofs: destination real mode offset.

data: source.

count: number of bytes to copy.

Notes: No range checking is performed.

Errors: None.

See also: dosmemget (86), dosmemmove (86), dosmemfillchar (84), dosmemfillword (85), seg_move (102), seg_fillchar (100), seg_fillword (101)

For an example, see global_dos_alloc (95).

enable

Declaration: Procedure `enable` ;

Description: Enables all hardware interrupts by executing a STI instruction. Parameters: None.

Errors: None.

See also: `disable` (84)

free_ldt_descriptor

Declaration: Function `free_ldt_descriptor` (`des` : `Word`) : `boolean`;

Description: Frees a previously allocated descriptor. Parameters:

des: The descriptor to be freed.

Return value: `True` if successful, `False` otherwise. Notes: After this call this selector is invalid and must not be used for any memory operations anymore. Each descriptor allocated with `allocate_ldt_descriptors` (81) must be freed individually with this function, even if it was previously allocated as a part of a contiguous array of descriptors.

Errors: Check the `int31error` variable.

See also: `allocate_ldt_descriptors` (81), `get_next_selector_increment_value` (90)

For an example, see `allocate_ldt_descriptors` (81).

free_memory_block

Declaration: Function `free_memory_block` (`blockhandle` : `Longint`) : `boolean`;

Description: Frees a previously allocated memory block. Parameters:

`blockhandle`: the handle to the memory area to free.

Return value: `True` if successful, `false` otherwise. Notes: Frees memory that was previously allocated with `allocate_memory_block` (83) . This function doesn't free any descriptors mapped to this block, it's the application's responsibility.

Errors: Check `int31error` variable.

See also: `allocate_memory_block` (83)

free_rm_callback

Declaration: Function `free_rm_callback` (`var intaddr` : `tseginfo`) : `boolean`;

Description: Releases a real mode callback address that was previously allocated with the `get_rm_callback` (91) function. Parameters:

intaddr: real mode address buffer returned by `get_rm_callback` (91) .

Return values: `True` if successful, `False` if not

Errors: Check the `int31error` variable.

See also: `set_rm_interrupt` (103), `get_rm_callback` (91)

For an example, see `get_rm_callback` (91).

get_cs

Declaration: Function `get_cs` : Word;

Description: Returns the cs selector. Parameters: None. Return values: The content of the cs segment register.

Errors: None.

See also: `get_ds` (88), `get_ss` (95)

For an example, see `set_pm_interrupt` (102).

get_descriptor_access_rights

Declaration: Function `get_descriptor_access_rights` (d : Word) : Longint;

Description: Gets the access rights of a descriptor. Parameters:

d selector to descriptor.

Return value: Access rights bit field.

Errors: Check the `int31error` variable.

See also: `set_descriptor_access_rights` (102)

get_ds

Declaration: Function `get_ds` : Word;

Description: Returns the ds selector. Parameters: None. Return values: The content of the ds segment register.

Errors: None.

See also: `get_cs` (88), `get_ss` (95)

get_linear_addr

Declaration: Function `get_linear_addr` (phys_addr : Longint; size : Longint) : Longint;

Description: Converts a physical address into a linear address. Parameters:

phys_addr: physical address of device.

size: Size of region to map in bytes.

Return value: Linear address that can be used to access the physical memory. Notes: It's the applications responsibility to allocate and set up a descriptor for access to the memory. This function shouldn't be used to map real mode addresses.

Errors: Check the `int31error` variable.

See also: `allocate_ldt_descriptors` (81), `set_segment_limit` (104), `set_segment_base_address` (104)

get_meminfo

Declaration: Function `get_meminfo (var meminfo : tmeminfo) : boolean;`

Description: Returns information about the amount of available physical memory, linear address space, and disk space for page swapping. Parameters:

meminfo: buffer to fill memory information into.

Return values: Due to an implementation bug this function always returns `False`, but it always succeeds. Notes: Only the first field of the returned structure is guaranteed to contain a valid value. Any fields that are not supported by the DPML host will be set by the host to `-1 (0FFFFFFFFH)` to indicate that the information is not available. The size of the pages used by the DPML host can be obtained with the `get_page_size (90)` function.

Errors: Check the `int31error` variable.

See also: `get_page_size (90)`

```

uses
    go32;

var
    meminfo : tmeminfo;

begin
    get_meminfo(meminfo);
    if (int31error <> 0) then begin
        Writeln('Error getting DPML memory information ... Halting');
        Writeln('DPML error number:', int31error);
    end else begin
        with meminfo do begin
            Writeln('Largest available free block:',
                available_memory div 1024, ' kbytes');
            if (available_pages <> -1) then
                Writeln('Maximum available unlocked pages:',
                    available_pages);
            if (available_lockable_pages <> -1) then
                Writeln('Maximum lockable available pages:',
                    available_lockable_pages);
            if (linear_space <> -1) then
                Writeln('Linear address space size:',
                    linear_space * get_page_size div 1024, ' kbytes');
            if (unlocked_pages <> -1) then
                Writeln('Total number of unlocked pages:',
                    unlocked_pages);
            if (available_physical_pages <> -1) then
                Writeln('Total number of free pages:',
                    available_physical_pages);
            if (total_physical_pages <> -1) then
                Writeln('Total number of physical pages:',
                    total_physical_pages);
            if (free_linear_space <> -1) then
                Writeln('Free linear address space:',
                    free_linear_space * get_page_size div 1024,
                    ' kbytes');
            if (max_pages_in_paging_file <> -1) then
                Writeln('Maximum size of paging file:',

```

```
max_pages_in_paging_file * get_page_size div 1024,  
    '_kbytes' );  
    end;  
end;
```

get_next_selector_increment_value

Declaration: Function `get_next_selector_increment_value` : `Word`;

Description: Returns the selector increment value when allocating multiple subsequent descriptors via `allocate_ldt_descriptors` (81). Parameters: None. Return value: Selector increment value. Notes: Because `allocate_ldt_descriptors` (81) only returns the selector for the first descriptor and so the value returned by this function can be used to calculate the selectors for subsequent descriptors in the array.

Errors: Check the `int31error` variable.

See also: `allocate_ldt_descriptors` (81), `free_ldt_descriptor` (87)

get_page_size

Declaration: Function `get_page_size` : `Longint`;

Description: Returns the size of a single memory page. Return value: Size of a single page in bytes. Notes: The returned size is typically 4096 bytes.

Errors: Check the `int31error` variable.

See also: `get_meminfo` (89)

For an example, see `get_meminfo` (89).

get_pm_interrupt

Declaration: Function `get_pm_interrupt` (`vector` : `byte`; `var intaddr` : `tseginfo`) : `boolean`;

Description: Returns the address of a current protected mode interrupt handler. Parameters:

vector: interrupt handler number you want the address to.

intaddr: buffer to store address.

Return values: `True` if successful, `False` if not. Notes: The returned address is a protected mode selector:offset address.

Errors: Check the `int31error` variable.

See also: `set_pm_interrupt` (102), `set_rm_interrupt` (103), `get_rm_interrupt` (93)

For an example, see `set_pm_interrupt` (102).

get_rm_callback

Declaration: `Function get_rm_callback (pm_func : pointer; const reg : trealregs;
var rmcb: tseginfo) : boolean;`

Description: Returns a unique real mode `segment:offset` address, known as a "real mode callback," that will transfer control from real mode to a protected mode procedure. Parameters:

pm_func: pointer to the protected mode callback function.

reg: supplied registers structure.

rmcb: buffer to real mode address of callback function.

Return values: `True` if successful, otherwise `False`. Notes: Callback addresses obtained with this function can be passed by a protected mode program for example to an interrupt handler, device driver, or TSR, so that the real mode program can call procedures within the protected mode program or notify the protected mode program of an event. The contents of the supplied regs structure is not valid after function call, but only at the time of the actual callback.

Errors: Check the `int31error` variable.

See also: `free_rm_callback` ([87](#))

```
{ $ASMMODE ATT }  
{ $MODE FPC }  
  
uses  
    crt ,  
    go32;  
  
const  
    mouseint = $33;  
  
var  
    mouse_regs      : trealregs; external name '___v2prt0_rmcb_regs';  
    mouse_seginfo   : tseginfo;  
  
var  
    mouse_numbuttons : longint;  
  
    mouse_action : word;  
    mouse_x, mouse_y : Word;  
    mouse_b : Word;  
  
    userproc_installed : Longbool;  
    userproc_length : Longint;  
    userproc_proc : pointer;  
  
procedure callback_handler; assembler;  
asm  
    pushw %ds  
    pushl %eax  
    movw %es, %ax  
    movw %ax, %ds  
  
    cmpl $1, USERPROC_INSTALLED  
    jne .LNoCallback  
    pushal
```

```
    movw DOSmemSELECTOR, %ax
    movw %ax, %fs
    call *USERPROC_PROC
    popal
.LNoCallback:

    popl %eax
    popw %ds

    pushl %eax
    movl (%esi), %eax
    movl %eax, %es:42(%edi)
    addw $4, %es:46(%edi)
    popl %eax
    iret
end;
procedure mouse_dummy; begin end;

procedure textuserproc;
begin
    mouse_b := mouse_regs.bx;
    mouse_x := (mouse_regs.cx shr 3) + 1;
    mouse_y := (mouse_regs.dx shr 3) + 1;
end;

procedure install_mouse(userproc : pointer; userproclen : longint);
var r : trealregs;
begin
    r.eax := $0; realintr(mouseint, r);
    if (r.eax <> $FFFF) then begin
        Writeln('No_Microsoft_compatible_mouse_found');
        Writeln('A_Microsoft_compatible_mouse_driver_is_necessary_',
            'to_run_this_example');
        halt;
    end;
    if (r.bx = $ffff) then mouse_numbuttons := 2
    else mouse_numbuttons := r.bx;
    Writeln(mouse_numbuttons, ' button_Microsoft_compatible_mouse_',
        'found. ');
    if (userproc <> nil) then begin
        userproc_proc := userproc;
        userproc_installed := true;
        userproc_length := userproclen;
        lock_code(userproc_proc, userproc_length);
    end else begin
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    lock_data(mouse_x, sizeof(mouse_x));
    lock_data(mouse_y, sizeof(mouse_y));
    lock_data(mouse_b, sizeof(mouse_b));
    lock_data(mouse_action, sizeof(mouse_action));

    lock_data(userproc_installed, sizeof(userproc_installed));
    lock_data(userproc_proc, sizeof(userproc_proc));

    lock_data(mouse_regs, sizeof(mouse_regs));
```

```
    lock_data (mouse_seginfo, sizeof (mouse_seginfo));
    lock_code (@callback_handler,
               longint (@mouse_dummy)-longint (@callback_handler));
    get_rm_callback (@callback_handler, mouse_regs, mouse_seginfo);
    r.eax := $0c; r.ecx := $7f;
    r.edx := longint (mouse_seginfo.offset);
    r.es := mouse_seginfo.segment;
    realintr (mouseint, r);
    r.eax := $01;
    realintr (mouseint, r);
end;

procedure remove_mouse;
var
    r : trealregs;
begin
    r.eax := $02; realintr (mouseint, r);
    r.eax := $0c; r.ecx := 0; r.edx := 0; r.es := 0;
    realintr (mouseint, r);
    free_rm_callback (mouse_seginfo);
    if (userproc_installed) then begin
        unlock_code (userproc_proc, userproc_length);
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    unlock_data (mouse_x, sizeof (mouse_x));
    unlock_data (mouse_y, sizeof (mouse_y));
    unlock_data (mouse_b, sizeof (mouse_b));
    unlock_data (mouse_action, sizeof (mouse_action));

    unlock_data (userproc_proc, sizeof (userproc_proc));
    unlock_data (userproc_installed, sizeof (userproc_installed));

    unlock_data (mouse_regs, sizeof (mouse_regs));
    unlock_data (mouse_seginfo, sizeof (mouse_seginfo));
    unlock_code (@callback_handler,
                 longint (@mouse_dummy)-longint (@callback_handler));
    fillchar (mouse_seginfo, sizeof (mouse_seginfo), 0);
end;

begin
    install_mouse (@textuserproc, 400);
    Writeln ('Press_any_key_to_exit ... ');
    while (not keypressed) do begin
        gotoxy (1, wherey);
        write ('MouseX:_:', mouse_x:2, ' MouseY:_:', mouse_y:2,
              ' Buttons _:_:', mouse_b:2);
    end;
    remove_mouse;
end.
```

get_rm_interrupt

Declaration: Function get_rm_interrupt (vector : byte; var intaddr : tseginfo)
: boolean;

Description: Returns the contents of the current machine's real mode interrupt vector for the specified interrupt.

Parameters:

vector: interrupt vector number.

intaddr: buffer to store real mode `segment:offset` address.

Return values: `True` if successful, `False` otherwise. Notes: The returned address is a real mode segment address, which isn't valid in protected mode.

Errors: Check the `int31error` variable.

See also: `set_rm_interrupt` (103), `set_pm_interrupt` (102), `get_pm_interrupt` (90)

get_run_mode

Declaration: `Function get_run_mode : Word;`

Description: Returns the current mode your application runs with. Return values: One of the constants used by this function.

Errors: None.

See also: constants returned by `get_run_mode` (94)

```
uses
    go32;

begin
    case ( get_run_mode ) of
        rm_unknown :
            WriteLn ( ' Unknown_environment_found ' );
        rm_raw :
            WriteLn ( ' You_are_currently_running_in_raw_mode_',
                '( without_HIMEM ) ' );
        rm_xms :
            WriteLn ( ' You_are_currently_using_HIMEM.SYS_only ' );
        rm_vcpi :
            WriteLn ( ' VCPI_server_detected . You ' ' re_using_HIMEM_and_',
                ' EMM386 ' );
        rm_dpml :
            WriteLn ( ' DPML_detected . You ' ' re_using_a_DPML_host_like_',
                ' a_windows_DOS_box_or_CWSDPML ' );
    end;
end.
```

get_segment_base_address

Declaration: `Function get_segment_base_address ( d : Word ) : Longint;`

Description: Returns the 32-bit linear base address from the descriptor table for the specified segment. Parameters:

d: selector of the descriptor you want the base address of.

Return values: Linear base address of specified descriptor.

Errors: Check the `int31error` variable.

See also: [allocate_ldt_descriptors \(81\)](#), [set_segment_base_address \(104\)](#), [allocate_ldt_descriptors \(81\)](#), [set_segment_limit \(104\)](#), [get_segment_limit \(95\)](#)

For an example, see [allocate_ldt_descriptors \(81\)](#).

get_segment_limit

Declaration: `Function get_segment_limit (d : Word) : Longint;`

Description: Returns a descriptors segment limit. Parameters:

d: selector.

Return value: Limit of the descriptor in bytes.

Errors: Returns zero if descriptor is invalid.

See also: [allocate_ldt_descriptors \(81\)](#), [set_segment_limit \(104\)](#), [set_segment_base_address \(104\)](#), [get_segment_base_address \(94\)](#),

get_ss

Declaration: `Function get_ss : Word;`

Description: Returns the ss selector. Parameters: None. Return values: The content of the ss segment register.

Errors: None.

See also: [get_ds \(88\)](#), [get_cs \(88\)](#)

global_dos_alloc

Declaration: `Function global_dos_alloc (bytes : Longint) : Longint;`

Description: Allocates a block of DOS real mode memory. Parameters:

bytes: size of requested real mode memory.

Return values: The low word of the returned value contains the selector to the allocated DOS memory block, the high word the corresponding real mode segment value. The offset value is always zero. This function allocates memory from DOS memory pool, i.e. memory below the 1 MB boundary that is controlled by DOS. Such memory blocks are typically used to exchange data with real mode programs, TSRs, or device drivers. The function returns both the real mode segment base address of the block and one descriptor that can be used by protected mode applications to access the block. This function should only be used for temporary buffers to get real mode information (e.g. interrupts that need a data structure in ES:(E)DI), because every single block needs a unique selector. The returned selector should only be freed by a [global_dos_free \(97\)](#) call.

Errors: Check the `int31error` variable.

See also: [global_dos_free \(97\)](#)


```
uses
    go32;

procedure dosalloc(var selector : word;
    var segment : word; size : longint);
var
    res : longint;
begin
    res := global_dos_alloc(size);
    selector := word(res);
    segment := word(res shr 16);
end;

procedure dosfree(selector : word);
begin
    global_dos_free(selector);
end;

type
    VBEInfoBuf = packed record
        Signature : array [0..3] of char;
        Version : Word;
        reserved : array [0..505] of byte;
    end;

var
    selector,
    segment : Word;

    r : trealregs;
    infobuf : VBEInfoBuf;

begin
    fillchar(r, sizeof(r), 0);
    fillchar(infobuf, sizeof(VBEInfoBuf), 0);
    dosalloc(selector, segment, sizeof(VBEInfoBuf));
    if (int31error <> 0) then begin
        Writeln('Error while allocating real mode memory, halting');
        halt;
    end;
    infobuf.Signature := 'VBE2';
    dosmemput(segment, 0, infobuf, sizeof(infobuf));
    r.ax := $4f00; r.es := segment;
    realintr($10, r);
    dosmemget(segment, 0, infobuf, sizeof(infobuf));
    dosfree(selector);
    if (r.ax <> $4f) then begin
        Writeln('VBE BIOS extension not available, function call',
            ' failed');
        halt;
    end;
    if (infobuf.signature[0] = 'V') and
        (infobuf.signature[1] = 'E') and
        (infobuf.signature[2] = 'S') and
        (infobuf.signature[3] = 'A') then begin
        Writeln('VBE version ', hi(infobuf.version), '.',
            lo(infobuf.version), ' detected');
```

end;
end.

global_dos_free

Declaration: Function `global_dos_free (selector :Word) : boolean;`

Description: Frees a previously allocated DOS memory block. Parameters:

selector: selector to the DOS memory block.

Return value: `True` if successful, `False` otherwise. Notes: The descriptor allocated for the memory block is automatically freed and hence invalid for further use. This function should only be used for memory allocated by `global_dos_alloc` (95).

Errors: Check the `int31error` variable.

See also: `global_dos_alloc` (95)

For an example, see `global_dos_alloc` (95).

inportb

Declaration: Function `inportb (port : Word) : byte;`

Description: Reads 1 byte from the selected I/O port. Parameters:

port: the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (99), `inportw` (97), `inportl` (97)

inportl

Declaration: Function `inportl (port : Word) : Longint;`

Description: Reads 1 longint from the selected I/O port. Parameters:

port: the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (99), `inportb` (97), `inportw` (97)

inportw

Declaration: Function `inportw (port : Word) : Word;`

Description: Reads 1 word from the selected I/O port. Parameters:

port: the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportw` (99), `inportb` (97), `inportl` (97)

lock_code

Declaration: `Function lock_code (functionaddr : pointer; size : Longint) : boolean;`

Description: Locks a memory range which is in the code segment selector. Parameters:

functionaddr: address of the function to be locked.

size: size in bytes to be locked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` variable.

See also: `lock_linear_region` (98), `lock_data` (98), `unlock_linear_region` (105), `unlock_data` (105), `unlock_code` (105)

For an example, see `get_rm_callback` (91).

lock_data

Declaration: `Function lock_data (var data; size : Longint) : boolean;`

Description: Locks a memory range which resides in the data segment selector. Parameters:

data: address of data to be locked.

size: length of data to be locked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` variable.

See also: `lock_linear_region` (98), `lock_code` (98), `unlock_linear_region` (105), `unlock_data` (105), `unlock_code` (105)

For an example, see `get_rm_callback` (91).

lock_linear_region

Declaration: `Function lock_linear_region (linearaddr, size : Longint) : boolean;`

Description: Locks a memory region to prevent swapping of it. Parameters:

linearaddr: the linear address of the memory are to be locked.

size: size in bytes to be locked.

Return value: `True` if successful, `False` otherwise.

Errors: Check the `int31error` variable.

See also: `lock_data` (98), `lock_code` (98), `unlock_linear_region` (105), `unlock_data` (105), `unlock_code` (105)

outportb

Declaration: Procedure outportb (port : Word; data : byte);

Description: Sends 1 byte of data to the specified I/O port. Parameters:

port: the I/O port number to send data to.

data: value sent to I/O port.

Return values: None.

Errors: None.

See also: inportb ([97](#)), outportl ([99](#)), outportw ([99](#))

uses

crt ,
go32;

begin

outportb (\$61, \$ff);
delay (50);
outportb (\$61, \$0);

end.

outportl

Declaration: Procedure outportl (port : Word; data : Longint);

Description: Sends 1 longint of data to the specified I/O port. Parameters:

port: the I/O port number to send data to.

data: value sent to I/O port.

Return values: None.

Errors: None.

See also: inportl ([97](#)), outportw ([99](#)), outportb ([99](#))

For an example, see outportb ([99](#)).

outportw

Declaration: Procedure outportw (port : Word; data : Word);

Description: Sends 1 word of data to the specified I/O port. Parameters:

port: the I/O port number to send data to.

data: value sent to I/O port.

Return values: None.

Errors: None.

See also: inportw ([97](#)), outportl ([99](#)), outportb ([99](#))

For an example, see outportb ([99](#)).

realintr

Declaration: Function `realintr (intrnr: Word; var regs : trealregs) : boolean;`

Description: Simulates an interrupt in real mode. Parameters:

intrnr: interrupt number to issue in real mode.

regs: registers data structure.

Return values: The supplied registers data structure contains the values that were returned by the real mode interrupt. **True** if successful, **False** if not. Notes: The function transfers control to the address specified by the real mode interrupt vector of `intrnr`. The real mode handler must return by executing an `IRET`.

Errors: Check the `int31error` variable.

See also:

```
uses
    go32;

var
    r : trealregs;

begin
    r.ax := $5300;
    r.bx := 0;
    realintr($15, r);
    if ((r.flags and carryflag)=0) then begin
        WriteLn('APM_v', (r.ah and $f), '.',
                (r.al shr 4), (r.al and $f), '_detected');
    end else
        WriteLn('APM_not_present');
end.
```

seg_fillchar

Declaration: Procedure `seg_fillchar (seg : Word; ofs : Longint; count : Longint; c : char);`

Description: Sets a memory area to a specific value. Parameters:

seg: selector to memory area.

ofs: offset to memory.

count: number of bytes to set.

c: byte data which is set.

Return values: None. Notes: No range check is done in any way.

Errors: None.

See also: `seg_move` ([102](#)), `seg_fillword` ([101](#)), `dosmemfillchar` ([84](#)), `dosmemfillword` ([85](#)), `dosmemget` ([86](#)), `dosmemput` ([86](#)), `dosmemmove` ([86](#))

```
uses
    go32;

var
    vgasel : Word;
    r : trealregs;

begin
    r.eax := $13; realintr($10, r);
    vgasel := segment_to_descriptor($A000);
    seg_fillchar(vgasel, 0, 64000, #15);
    readln;
    r.eax := $3; realintr($10, r);
end.
```

seg_fillword

Declaration: Procedure seg_fillword (seg : Word; ofs : Longint; count : Longint; w : Word);

Description: Sets a memory area to a specific value. Parameters:

seg: selector to memory area.

ofs: offset to memory.

count: number of words to set.

w: word data which is set.

Return values: None. Notes: No range check is done in any way.

Errors: None.

See also: seg_move ([102](#)), seg_fillchar ([100](#)), dosmemfillchar ([84](#)), dosmemfillword ([85](#)), dosmemget ([86](#)), dosmempout ([86](#)), dosmemmove ([86](#))

For an example, see allocate_ldt_descriptors ([81](#)).

segment_to_descriptor

Declaration: Function segment_to_descriptor (seg : Word) : Word;

Description: Maps a real mode segment (paragraph) address onto a descriptor that can be used by a protected mode program to access the same memory. Parameters:

seg: the real mode segment you want the descriptor to.

Return values: Descriptor to real mode segment address. Notes: The returned descriptors limit will be set to 64 kB. Multiple calls to this function with the same segment address will return the same selector. Descriptors created by this function can never be modified or freed. Programs which need to examine various real mode addresses using the same selector should use the function allocate_ldt_descriptors ([81](#)) and change the base address as necessary.

Errors: Check the int31error variable.

See also: allocate_ldt_descriptors ([81](#)), free_ldt_descriptor ([87](#)), set_segment_base_address ([104](#))

For an example, see seg_fillchar ([100](#)).

seg_move

Declaration: Procedure seg_move (sseg : Word; source : Longint; dseg : Word; dest : Longint; count : Longint);

Description: Copies data between two memory locations. Parameters:

sseg: source selector.

source: source offset.

dseg: destination selector.

dest: destination offset.

count: size in bytes to copy.

Return values: None. Notes: Overlapping is only checked if the source selector is equal to the destination selector. No range check is done.

Errors: None.

See also: seg_fillchar ([100](#)), seg_fillword ([101](#)), dosmemfillchar ([84](#)), dosmemfillword ([85](#)), dosmemget ([86](#)), dosmempu ([86](#)), dosmemmove ([86](#))

For an example, see allocate_ldt_descriptors ([81](#)).

set_descriptor_access_rights

Declaration: Function set_descriptor_access_rights (d : Word; w : Word) : Longint;

Description: Sets the access rights of a descriptor. Parameters:

d: selector.

w: new descriptor access rights.

Return values: This function doesn't return anything useful.

Errors: Check the int31error variable.

See also: get_descriptor_access_rights ([88](#))

set_pm_interrupt

Declaration: Function set_pm_interrupt (vector : byte; const intaddr : tseginfo) : boolean;

Description: Sets the address of the protected mode handler for an interrupt. Parameters:

vector: number of protected mode interrupt to set.

intaddr: selector:offset address to the interrupt vector.

Return values: True if successful, False otherwise. Notes: The address supplied must be a valid selector:offset protected mode address.

Errors: Check the int31error variable.

See also: get_pm_interrupt ([90](#)), set_rm_interrupt ([103](#)), get_rm_interrupt ([93](#))

```
uses
    crt ,
    go32;

const
    int1c = $1c;

var
    oldint1c : tseginfo;
    newint1c : tseginfo;

    int1c_counter : Longint;

    int1c_ds : Word; external name '___v2prt0_ds_alias';

procedure int1c_handler; assembler;
asm
    cli
    pushw %ds
    pushw %ax
    movw %cs:int1c_ds, %ax
    movw %ax, %ds
    incl int1c_counter
    popw %ax
    popw %ds
    sti
    iret
end;

var i : Longint;

begin
    newint1c.offset := @int1c_handler;
    newint1c.segment := get_cs;
    get_pm_interrupt(int1c, oldint1c);
    Writeln('--_Press_any_key_to_exit_--');
    set_pm_interrupt(int1c, newint1c);
    while (not keypressed) do begin
        gotoxy(1, wherey);
        write('Number_of_interrupts_occured_', int1c_counter);
    end;
    set_pm_interrupt(int1c, oldint1c);
end.
```

set_rm_interrupt

Declaration: Function set_rm_interrupt (vector : byte; const intaddr : tseginfo)
: boolean;

Description: Sets a real mode interrupt handler. Parameters:

vector: the interrupt vector number to set.

intaddr: address of new interrupt vector.

Return values: **True** if successful, otherwise **False**. Notes: The address supplied **MUST** be a real mode segment address, not a **selector:offset** address. So the interrupt handler must either

reside in DOS memory (below 1 Mb boundary) or the application must allocate a real mode callback address with `get_rm_callback` (91).

Errors: Check the `int31error` variable.

See also: `get_rm_interrupt` (93), `set_pm_interrupt` (102), `get_pm_interrupt` (90), `get_rm_callback` (91)

set_segment_base_address

Declaration: Function `set_segment_base_address` (d : Word; s : Longint) : boolean;

Description: Sets the 32-bit linear base address of a descriptor. Parameters:

d: selector.

s: new base address of the descriptor.

Errors: Check the `int31error` variable.

See also: `allocate_ldt_descriptors` (81), `get_segment_base_address` (94), `allocate_ldt_descriptors` (81), `set_segment_limit` (104), `get_segment_base_address` (94), `get_segment_limit` (95)

set_segment_limit

Declaration: Function `set_segment_limit` (d : Word; s : Longint) : boolean;

Description: Sets the limit of a descriptor. Parameters:

d: selector.

s: new limit of the descriptor.

Return values: Returns `True` if successful, else `False`. Notes: The new limit specified must be the byte length of the segment - 1. Segment limits bigger than or equal to 1MB must be page aligned, they must have the lower 12 bits set.

Errors: Check the `int31error` variable.

See also: `allocate_ldt_descriptors` (81), `set_segment_base_address` (104), `get_segment_limit` (95), `set_segment_limit` (104)

For an example, see `allocate_ldt_descriptors` (81).

tb_size

Declaration: Function `tb_size` : Longint;

Description: Returns the size of the pre-allocated DOS memory buffer. Parameters: None. Return values: The size of the pre-allocated DOS memory buffer. Notes: This block always seems to be 16k in size, but don't rely on this.

Errors: None.

See also: `transfer_buffer` (105), `copyfromdos` (83) `copytodos` (83)

transfer_buffer

Declaration: `Function transfer_buffer : Longint;`

Description: `transfer_buffer` returns the offset of the transfer buffer.

Errors: None.

See also: `tb_size` ([104](#))

unlock_code

Declaration: `Function unlock_code (functionaddr : pointer; size : Longint) : boolean;`

Description: Unlocks a memory range which resides in the code segment selector. Parameters:

functionaddr: address of function to be unlocked.

size: size bytes to be unlocked.

Return value: `True` if successful, `False` otherwise.

Errors: Check the `int31error` variable.

See also: `unlock_linear_region` ([105](#)), `unlock_data` ([105](#)), `lock_linear_region` ([98](#)), `lock_data` ([98](#)), `lock_code` ([98](#))

For an example, see `get_rm_callback` ([91](#)).

unlock_data

Declaration: `Function unlock_data (var data; size : Longint) : boolean;`

Description: Unlocks a memory range which resides in the data segment selector. Parameters:

data: address of memory to be unlocked.

size: size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` variable.

See also: `unlock_linear_region` ([105](#)), `unlock_code` ([105](#)), `lock_linear_region` ([98](#)), `lock_data` ([98](#)), `lock_code` ([98](#))

For an example, see `get_rm_callback` ([91](#)).

unlock_linear_region

Declaration: `Function unlock_linear_region (linearaddr, size : Longint) : boolean;`

Description: Unlocks a previously locked linear region range to allow it to be swapped out again if needed.

Parameters:

linearaddr: linear address of the memory to be unlocked.

size: size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` variable.

See also: `unlock_data` ([105](#)), `unlock_code` ([105](#)), `lock_linear_region` ([98](#)), `lock_data` ([98](#)), `lock_code` ([98](#))

Chapter 8

The GRAPH unit.

This document describes the **GRAPH** unit for Free Pascal, for all platforms. The unit was first written for DOS by Florian klämpfl, but was later completely rewritten by Carl-Eric Codere to be completely portable.

This chapter is divided in 4 sections.

- The first section gives an introduction to the graph unit.
- The second section lists the pre-defined constants, types and variables.
- The second section describes the functions which appear in the interface part of the **GRAPH** unit.
- The last part describes some system-specific issues.

8.1 Introduction

Requirements

The unit Graph exports functions and procedures for graphical output. It requires at least a VGA-compatible Card or a VGA-Card with software-driver (min. **512Kb** video memory).

A word about mode selection

The graph unit was implemented for compatibility with the old Turbo Pascal graph unit. For this reason, the mode constants as they were defined in the Turbo Pascal graph unit are retained.

However, since

1. Video cards have evolved very much
2. Free Pascal runs on multiple platforms

it was decided to implement new mode and graphic driver constants, which are more independent of the specific platform the program runs on.

In this section we give a short explanation of the new mode system. the following drivers were defined:

```
D1bit = 11;
D2bit = 12;
D4bit = 13;
D6bit = 14; { 64 colors Half-brite mode - Amiga }
D8bit = 15;
D12bit = 16; { 4096 color modes HAM mode - Amiga }
D15bit = 17;
D16bit = 18;
D24bit = 19; { not yet supported }
D32bit = 20; { not yet supported }
D64bit = 21; { not yet supported }
```

```
lowNewDriver = 11;
highNewDriver = 21;
```

Each of these drivers specifies a desired color-depth.

The following modes have been defined:

```
detectMode = 30000;
m320x200 = 30001;
m320x256 = 30002; { amiga resolution (PAL) }
m320x400 = 30003; { amiga/atari resolution }
m512x384 = 30004; { mac resolution }
m640x200 = 30005; { vga resolution }
m640x256 = 30006; { amiga resolution (PAL) }
m640x350 = 30007; { vga resolution }
m640x400 = 30008;
m640x480 = 30009;
m800x600 = 30010;
m832x624 = 30011; { mac resolution }
m1024x768 = 30012;
m1280x1024 = 30013;
m1600x1200 = 30014;
m2048x1536 = 30015;
```

```
lowNewMode = 30001;
highNewMode = 30015;
```

These modes start at 30000 because Borland specified that the mode number should be ascending with increasing X resolution, and the new constants shouldn't interfere with the old ones.

The above constants can be used to set a certain color depth and resolution, as demonstrated in the following example:

Listing: graphex/inigraph1.pp

```
Program inigraph1;

{ Program to demonstrate static graphics mode selection }

uses graph;

const
    TheLine = 'We_are_now_in_640_x_480_x_256_colors!' +
              '_( press_<Return>_to_continue )';
```

```
var
  gd, gm, lo, hi, error, tw, th: integer;
  found: boolean;

begin
  { We want an 8 bit mode }
  gd := D8bit;
  gm := m640x480;
  initgraph(gd, gm, '');
  { Make sure you always check graphresult! }
  error := graphResult;
  if (error <> grOk) Then
    begin
      writeln('640x480x256_is_not_supported!');
      halt(1);
    end;
  { We are now in 640x480x256 }
  setColor(cyan);
  rectangle(0,0,getmaxx,getmaxy);
  { Write a nice message in the center of the screen }
  setTextStyle(defaultFont, horizDir, 1);
  tw:=TextWidth(TheLine);
  th:=TextHeight(TheLine);
  outTextXY((getMaxX - TW) div 2,
            (getMaxY - TH) div 2, TheLine);
  { Wait for return }
  readln;
  { Back to text mode }
  closegraph;
end.
```

If other modes than the ones above are supported by the graphics card, you will not be able to select them with this mechanism.

For this reason, there is also a 'dynamic' mode number, which is assigned at run-time. This number increases with increasing X resolution. It can be queried with the `getmoderange` call. This call will return the range of modes which are valid for a certain graphics driver. The numbers are guaranteed to be consecutive, and can be used to search for a certain resolution, as in the following example:

Listing: graphex/inigraph2.pp

```
Program inigraph2;

{ Program to demonstrate dynamic graphics mode selection }

uses graph;

const
  TheLine = 'We_are_now_in_640_x_480_x_256_colors!' +
            '_(_press_<Return>_to_continue)';

var
  th, tw, gd, gm, lo, hi, error: integer;
  found: boolean;

begin
  { We want an 8 bit mode }
```

```
gd := D8bit;
{ Get all available resolutions for this bitdepth }
getmoderange(gd, lo, hi);
{ If the highest available mode number is -1,
  no resolutions are supported for this bitdepth }
if hi = -1 then
  begin
    writeln('no_8_bit_modes_supported!');
    halt
  end;
found := false;
{ Search all resolutions for 640x480 }
for gm := lo to hi do
  begin
    initgraph(gd, gm, '');
    { Make sure you always check graphresult! }
    error := graphResult;
    if (error = grOk) and
      (getmaxx = 639) and (getmaxy = 479) then
      begin
        found := true;
        break;
      end;
  end;
if not found then
  begin
    writeln('640x480x256_is_not_supported!');
    halt(1)
  end;
{ We are now in 640x480x256 }
setColor(cyan);
rectangle(0,0,getmaxx,getmaxy);
{ Write a nice message in the center of the screen }
setTextStyle(defaultFont, horizDir, 1);
TW:=TextWidth(TheLine);
TH:=TextHeight(TheLine);
outTextXY((getMaxX - TW) div 2,
          (getMaxY - TH) div 2, TheLine);
{ Wait for return }
readln;
{ Back to text mode }
closegraph;
end.
```

Thus, the `getmoderange` function can be used to detect all available modes and drivers, as in the following example:

Listing: graphex/modrange.pp

Program GetModeRange_Example;

```
{ This program demonstrates how to find all available graph modes }

uses graph;

const
  { Currently, only 4, 8, 15 and 16 bit modes are supported
    but this may change in the future }
  gdnames: array[D4bit..D16bit] of string[6] =
```

```
( '4_bit ', '6_bit ', '8_bit ', '12_bit ', '15_bit ', '16_bit ' );

var
  t: text;
  gd, c, low, high, res: integer;
begin
  assign(t, 'modes.txt ');
  rewrite(t);
  close(t);
  for gd := D4bit to D16bit do
    begin
      { Get the available mode numbers for this driver }
      getModeRange(gd, low, high);
      append(t);
      write(t, gdnames[gd]);
      Writeln(t, ':_ low_mode_nr =_', low, ',_ high_mode_nr =_', high);
      close(t);
      { If high is -1,
        no resolutions are supported for this bitdepth }
      if high = -1 then
        begin
          append(t);
          writeln(t, 'No_modes_supported! ');
          writeln(t);
          close(t);
        end
      else
        { Enter all supported resolutions for this bitdepth
          and write their characteristics to the file }
        for c := low to high do
          begin
            append(t);
            writeln(t, 'testing_mode_nr_', c);
            close(t);
            initgraph(gd, c, '');
            res := graphresult;
            append(t);
            { An error occurred when entering the mode? }
            if res <> grok then
              writeln(t, grapherrormsg(res))
            else
              begin
                write(t, 'maxx:_', getmaxx, ',_ maxy:_', getmaxy);
                Writeln(t, ',_ maxcolor:_', getmaxcolor);
                closegraph;
              end;
            writeln(t);
            close(t);
          end;
        append(t);
        writeln(t);
        close(t);
      end;
    end;
  end.
```

8.2 Constants, Types and Variables

Types

```
ArcCoordsType = record
  X,Y,Xstart,Ystart,Xend,Yend : Integer;
end;
FillPatternType = Array [1..8] of Byte;
FillSettingsType = Record
  Pattern,Color : Word
end;
LineStyleType = Record
  LineStyle,Pattern, Width : Word;
end;
PaletteType = Record
  Size : Byte;
  Colors : array[0..MAXcolor] of shortint;
end;
PointType = Record
  X,Y : Integer;
end;
TextSettingsType = Record
  Font,Direction, CharSize, Horiz, Vert : Word
end;
ViewPortType = Record
  X1,Y1,X2,Y2 : Integer;
  Clip : Boolean
end;
```

8.3 Function list by category

What follows is a listing of the available functions, grouped by category. For each function there is a reference to the page where you can find the function.

Initialization

Initialization of the graphics screen.

Name	Description	Page
ClearDevice	Empty the graphics screen	115
CloseGraph	Finish drawing session, return to text mode	115
DetectGraph	Detect graphical modes	115
GetAspectRatio	Get aspect ratio of screen	117
GetModeRange	Get range of valid modes for current driver	119
GraphDefaults	Set defaults	121
GetDriverName	Return name of graphical driver	117
GetGraphMode	Return current or last used graphics mode	118
GetMaxMode	Get maximum mode for current driver	119

GetModeName	Get name of current mode	119
GraphErrorMsg	String representation of graphical error	121
GraphResult	Result of last drawing operation	121
InitGraph	Initialize graphics drivers	122
InstallUserDriver	Install a new driver	122
RegisterBGIDriver	Register a new driver	125
RestoreCRTMode	Go back to text mode	125
SetGraphBufSize	Set buffer size for graphical operations	127
SetGraphMode	Set graphical mode	128

screen management

General drawing screen management functions.

Name	Description	Page
ClearViewPort	Clear the current viewport	115
GetImage	Copy image from screen to memory	118
GetMaxX	Get maximum X coordinate	119
GetMaxY	Get maximum Y coordinate	119
GetX	Get current X position	120
GetY	Get current Y position	121
ImageSize	Get size of selected image	122
GetViewSettings	Get current viewport settings	120
PutImage	Copy image from memory to screen	124
SetActivePage	Set active video page	126
SetAspectRatio	Set aspect ratio for drawing routines	126
SetViewPort	Set current viewport	130
SetVisualPage	Set visual page	130
SetWriteMode	Set write mode for screen operations	130

Color management

All functions related to color management.

Name	Description	Page
GetBkColor	Get current background color	117
GetColor	Get current foreground color	117
GetDefaultPalette	Get default palette entries	117
GetMaxColor	Get maximum valid color	118
GetPaletteSize	Get size of palette for current mode	120
GetPixel	Get color of selected pixel	120
GetPalette	Get palette entry	120

SetAllPalette	Set all colors in palette	126
SetBkColor	Set background color	126
SetColor	Set foreground color	127
SetPalette	Set palette entry	128
SetRGBPalette	Set palette entry with RGB values	128

Drawing primitives

Functions for simple drawing.

Name	Description	Page
Arc	Draw an arc	114
Circle	Draw a complete circle	115
DrawPoly	Draw a polygon with N points	116
Ellipse	Draw an ellipse	116
GetArcCoords	Get arc coordinates	117
GetLineSettings	Get current line drawing settings	118
Line	Draw line between 2 points	123
LineRel	Draw line relative to current position	123
LineTo	Draw line from current position to absolute position	123
MoveRel	Move cursor relative to current position	123
MoveTo	Move cursor to absolute position	124
PieSlice	Draw a pie slice	124
PutPixel	Draw 1 pixel	125
Rectangle	Draw a non-filled rectangle	125
Sector	Draw a sector	126
SetLineStyle	Set current line drawing style	128

Filled drawings

Functions for drawing filled regions.

Name	Description	Page
Bar3D	Draw a filled 3D-style bar	114
Bar	Draw a filled rectangle	114
FloodFill	Fill starting from coordinate	116
FillEllipse	Draw a filled ellipse	116
FillPoly	Draw a filled polygon	116
GetFillPattern	Get current fill pattern	118
GetFillSettings	Get current fill settings	118
SetFillPattern	Set current fill pattern	127
SetFillStyle	Set current fill settings	127

Text and font handling

Functions to set texts on the screen.

Name	Description	Page
GetTextSettings	Get current text settings	120
InstallUserFont	Install a new font	123
OutText	Write text at current cursor position	124
OutTextXY	Write text at coordinates X,Y	124
RegisterBGIFont	Register a new font	125
SetTextJustify	Set text justification	129
SetTextStyle	Set text style	129
SetUserCharSize	Set text size	129
TextHeight	Calculate height of text	130
TextWidth	Calculate width of text	130

8.4 Functions and procedures

Arc

Declaration: Procedure Arc (X,Y : Integer; start,stop, radius : Word);

Description: Arc draws part of a circle with center at (X,Y), radius **radius**, starting from angle **start**, stopping at angle **stop**. These angles are measured counterclockwise.

Errors: None.

See also: Circle ([115](#)),Ellipse ([116](#)) GetArcCoords ([117](#)),PieSlice ([124](#)), Sector ([126](#))

Bar

Declaration: Procedure Bar (X1,Y1,X2,Y2 : Integer);

Description: Draws a rectangle with corners at (X1,Y1) and (X2,Y2) and fills it with the current color and fill-style.

Errors: None.

See also: Bar3D ([114](#)), Rectangle ([125](#))

Bar3D

Declaration: Procedure Bar3D (X1,Y1,X2,Y2 : Integer; depth : Word; Top : Boolean);

Description: Draws a 3-dimensional Bar with corners at (X1,Y1) and (X2,Y2) and fills it with the current color and fill-style. **Depth** specifies the number of pixels used to show the depth of the bar. If **Top** is true; then a 3-dimensional top is drawn.

Errors: None.

See also: Bar ([114](#)), Rectangle ([125](#))

Circle

Declaration: Procedure Circle (X,Y : Integer; Radius : Word);

Description: Circle draws part of a circle with center at (X, Y), radius radius.

Errors: None.

See also: Ellipse ([116](#)), Arc ([114](#)) GetArcCoords ([117](#)), PieSlice ([124](#)), Sector ([126](#))

ClearDevice

Declaration: Procedure ClearDevice ;

Description: Clears the graphical screen (with the current background color), and sets the pointer at (0, 0)

Errors: None.

See also: ClearViewPort ([115](#)), SetBkColor ([126](#))

ClearViewPort

Declaration: Procedure ClearViewPort ;

Description: Clears the current viewport. The current background color is used as filling color. The pointer is set at (0, 0)

Errors: None.

See also: ClearDevice ([115](#)), SetViewPort ([130](#)), SetBkColor ([126](#))

CloseGraph

Declaration: Procedure CloseGraph ;

Description: Closes the graphical system, and restores the screen modus which was active before the graphical modus was activated.

Errors: None.

See also: InitGraph ([122](#))

DetectGraph

Declaration: Procedure DetectGraph (Var Driver, Modus : Integer);

Description: Checks the hardware in the PC and determines the driver and screen-modus to be used. These are returned in Driver and Modus, and can be fed to InitGraph. See the InitGraph for a list of drivers and modi.

Errors: None.

See also: InitGraph ([122](#))

DrawPoly

Declaration: Procedure DrawPoly (NumberOfPoints : Word; Var PolyPoints;

Description: Draws a polygone with NumberOfPoints corner points, using the current color and line-style. PolyPoints is an array of type PointType.

Errors: None.

See also: Bar ([114](#)), seepBar3D, Rectangle ([125](#))

Ellipse

Declaration: Procedure Ellipse (X,Y : Integer; Start,Stop,XRadius,YRadius : Word);

Description: Ellipse draws part of an ellipse with center at (X,Y). XRadius and Yradius are the horizontal and vertical radii of the ellipse. Start and Stop are the starting and stopping angles of the part of the ellipse. They are measured counterclockwise from the X-axis.

Errors: None.

See also: Arc ([114](#)) Circle ([115](#)), FillEllipse ([116](#))

FillEllipse

Declaration: Procedure FillEllipse (X,Y : Integer; Xradius,YRadius: Word);

Description: Ellipse draws an ellipse with center at (X,Y). XRadius and Yradius are the horizontal and vertical radii of the ellipse. The ellipse is filled with the current color and fill-style.

Errors: None.

See also: Arc ([114](#)) Circle ([115](#)), GetArcCoords ([117](#)),PieSlice ([124](#)), Sector ([126](#))

FillPoly

Declaration: Procedure FillPoly (NumberOfPoints : Word; Var PolyPoints);

Description: Draws a polygone with NumberOfPoints corner points and fills it using the current color and line-style. PolyPoints is an array of type PointType.

Errors: None.

See also: Bar ([114](#)), seepBar3D, Rectangle ([125](#))

FloodFill

Declaration: Procedure FloodFill (X,Y : Integer; BorderColor : Word);

Description: Fills the area containing the point (X,Y), bounded by the color BorderColor.

Errors: None

See also: SetColor ([127](#)), SetBkColor ([126](#))

GetArcCoords

Declaration: Procedure GetArcCoords (Var ArcCoords : ArcCoordsType);

Description: GetArcCoords returns the coordinates of the latest Arc or Ellipse call.

Errors: None.

See also: Arc ([114](#)), Ellipse ([116](#))

GetAspectRatio

Declaration: Procedure GetAspectRatio (Var Xasp, Yasp : Word);

Description: GetAspectRatio determines the effective resolution of the screen. The aspect ration can the be calculated as Xasp/Yasp.

Errors: None.

See also: InitGraph ([122](#)), SetAspectRatio ([126](#))

GetBkColor

Declaration: Function GetBkColor : Word;

Description: GetBkColor returns the current background color (the palette entry).

Errors: None.

See also: GetColor ([117](#)), SetBkColor ([126](#))

GetColor

Declaration: Function GetColor : Word;

Description: GetColor returns the current drawing color (the palette entry).

Errors: None.

See also: GetColor ([117](#)), SetBkColor ([126](#))

GetDefaultPalette

Declaration: Procedure GetDefaultPalette (Var Palette : PaletteType);

Description: Returns the current palette in Palette.

Errors: None.

See also: GetColor ([117](#)), GetBkColor ([117](#))

GetDriverName

Declaration: Function GetDriverName : String;

Description: GetDriverName returns a string containing the name of the current driver.

Errors: None.

See also: GetModeName ([119](#)), InitGraph ([122](#))

GetFillPattern

Declaration: Procedure GetFillPattern (Var FillPattern : FillPatternType);

Description: GetFillPattern returns an array with the current fill-pattern in FillPattern

Errors: None

See also: SetFillPattern ([127](#))

GetFillSettings

Declaration: Procedure GetFillSettings (Var FillInfo : FillSettingsType);

Description: GetFillSettings returns the current fill-settings in FillInfo

Errors: None.

See also: SetFillPattern ([127](#))

GetGraphMode

Declaration: Function GetGraphMode : Integer;

Description: GetGraphMode returns the current graphical modulus

Errors: None.

See also: InitGraph ([122](#))

GetImage

Declaration: Procedure GetImage (X1,Y1,X2,Y2 : Integer, Var Bitmap;

Description: GetImage Places a copy of the screen area (X1,Y1) to X2,Y2 in BitMap

Errors: Bitmap must have enough room to contain the image.

See also: ImageSize ([122](#)), PutImage ([124](#))

GetLineSettings

Declaration: Procedure GetLineSettings (Var LineInfo : LineSettingsType);

Description: GetLineSettings returns the current Line settings in LineInfo

Errors: None.

See also: SetLineStyle ([128](#))

GetMaxColor

Declaration: Function GetMaxColor : Word;

Description: GetMaxColor returns the maximum color-number which can be set with SetColor. Contrary to Turbo Pascal, this color isn't always guaranteed to be white (for instance in 256+ color modes).

Errors: None.

See also: SetColor ([127](#)), GetPaletteSize ([120](#))

GetMaxMode

Declaration: `Function GetMaxMode : Word;`

Description: `GetMaxMode` returns the highest modus for the current driver.

Errors: None.

See also: `InitGraph` ([122](#))

GetMaxX

Declaration: `Function GetMaxX : Word;`

Description: `GetMaxX` returns the maximum horizontal screen length

Errors: None.

See also: `GetMaxY` ([119](#))

GetMaxY

Declaration: `Function GetMaxY : Word;`

Description: `GetMaxY` returns the maximum number of screen lines

Errors: None.

See also: `GetMaxY` ([119](#))

GetModeName

Declaration: `Function GetModeName (Var modus : Integer) : String;`

Description: Returns a string with the name of modus `Modus`

Errors: None.

See also: `GetDriverName` ([117](#)), `InitGraph` ([122](#))

GetModeRange

Declaration: `Procedure GetModeRange (Driver : Integer;
LoModus, HiModus: Integer);`

Description: `GetModeRange` returns the Lowest and Highest modus of the currently installed driver. If no modes are supported for this driver, `HiModus` will be -1.

Errors: None.

See also: `InitGraph` ([122](#))

GetPalette

Declaration: Procedure GetPalette (Var Palette : PaletteType);

Description: GetPalette returns in Palette the current palette.

Errors: None.

See also: GetPaletteSize ([120](#)), SetPalette ([128](#))

GetPaletteSize

Declaration: Function GetPaletteSize : Word;

Description: GetPaletteSize returns the maximum number of entries in the current palette.

Errors: None.

See also: GetPalette ([120](#)), SetPalette ([128](#))

GetPixel

Declaration: Function GetPixel (X,Y : Integer) : Word;

Description: GetPixel returns the color of the point at (X,Y)

Errors: None.

See also:

GetTextSettings

Declaration: Procedure GetTextSettings (Var TextInfo : TextSettingsType);

Description: GetTextSettings returns the current text style settings : The font, direction, size and placement as set with SetTextStyle and SetTextJustify

Errors: None.

See also: SetTextStyle ([129](#)), SetTextJustify ([129](#))

GetViewSettings

Declaration: Procedure GetViewSettings (Var ViewPort : ViewPortType);

Description: GetViewSettings returns the current viewport and clipping settings in ViewPort.

Errors: None.

See also: SetViewPort ([130](#))

GetX

Declaration: Function GetX : Integer;

Description: GetX returns the X-coordinate of the current position of the graphical pointer

Errors: None.

See also: GetY ([121](#))

GetY

Declaration: `Function GetY : Integer;`

Description: `GetY` returns the Y-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetX` ([120](#))

GraphDefaults

Declaration: `Procedure GraphDefaults ;`

Description: `GraphDefaults` resets all settings for viewport, palette, foreground and background pattern, line-style and pattern, filling style, filling color and pattern, font, text-placement and text size.

Errors: None.

See also: `SetViewPort` ([130](#)), `SetFillStyle` ([127](#)), `SetColor` ([127](#)), `SetBkColor` ([126](#)), `SetLineStyle` ([128](#))

GraphErrorMsg

Declaration: `Function GraphErrorMsg (ErrorCode : Integer) : String;`

Description: `GraphErrorMsg` returns a string describing the error `Errorcode`. This string can be used to let the user know what went wrong.

Errors: None.

See also: `GraphResult` ([121](#))

GraphResult

Declaration: `Function GraphResult : Integer;`

Description: `GraphResult` returns an error-code for the last graphical operation. If the returned value is zero, all went well. A value different from zero means an error has occurred. besides all operations which draw something on the screen, the following procedures also can produce a `GraphResult` different from zero:

- `InstallUserFont` ([123](#))
- `SetLineStyle` ([128](#))
- `SetWriteMode` ([130](#))
- `SetFillStyle` ([127](#))
- `SetTextJustify` ([129](#))
- `SetGraphMode` ([128](#))
- `SetTextStyle` ([129](#))

Errors: None.

See also: `GraphErrorMsg` ([121](#))

ImageSize

Declaration: `Function ImageSize (X1,Y1,X2,Y2 : Integer) : Word;`

Description: `ImageSize` returns the number of bytes needed to store the image in the rectangle defined by (X1, Y1) and (X2, Y2).

Errors: None.

See also: `GetImage` ([118](#))

InitGraph

Declaration: `Procedure InitGraph (var GraphDriver, GraphModus : integer;
const PathToDriver : string);`

Description: `InitGraph` initializes the graph package. `GraphDriver` has two valid values: `GraphDriver=0` which performs an auto detect and initializes the highest possible mode with the most colors. 1024x768x64K is the highest possible resolution supported by the driver, if you need a higher resolution, you must edit `MODES.PPI`. If you need another mode, then set `GraphDriver` to a value different from zero and `graphmode` to the mode you wish (VESA modes where 640x480x256 is 101h etc.). `PathToDriver` is only needed, if you use the BGI fonts from Borland.

Errors: None.

See also: Introduction, (page [106](#)), `DetectGraph` ([115](#)), `CloseGraph` ([115](#)), `GraphResult` ([121](#))

Example:

```
var
    gd,gm : integer;
    PathToDriver : string;
begin
    gd:=detect; { highest possible resolution }
    gm:=0; { not needed, auto detection }
    PathToDriver:='C:\PP\BGI'; { path to BGI fonts,
                                drivers aren't needed }

    InitGraph(gd,gm,PathToDriver);
    if GraphResult<>grok then
        halt; ..... { whatever you need }
    CloseGraph; { restores the old graphics mode }
end.
```

InstallUserDriver

Declaration: `Function InstallUserDriver (DriverPath : String;
AutoDetectPtr: Pointer) : Integer;`

Description: `InstallUserDriver` adds the device-driver `DriverPath` to the list of .BGI drivers. `AutoDetectPtr` is a pointer to a possible auto-detect function.

Errors: None.

See also: `InitGraph` ([122](#)), `InstallUserFont` ([123](#))

InstallUserFont

Declaration: `Function InstallUserFont (FontPath : String) : Integer;`

Description: `InstallUserFont` adds the font in `FontPath` to the list of fonts of the .BGI system.

Errors: None.

See also: `InitGraph` ([122](#)), `InstallUserDriver` ([122](#))

Line

Declaration: `Procedure Line (X1,Y1,X2,Y2 : Integer);`

Description: `Line` draws a line starting from (X1, Y1 to (X2, Y2), in the current line style and color. The current position is put to (X2, Y2)

Errors: None.

See also: `LineRel` ([123](#)), `LineTo` ([123](#))

LineRel

Declaration: `Procedure LineRel (DX,DY : Integer);`

Description: `LineRel` draws a line starting from the current pointer position to the point(DX, DY, **relative** to the current position, in the current line style and color. The Current Position is set to the endpoint of the line.

Errors: None.

See also: `Line` ([123](#)), `LineTo` ([123](#))

LineTo

Declaration: `Procedure LineTo (DX,DY : Integer);`

Description: `LineTo` draws a line starting from the current pointer position to the point(DX, DY, **relative** to the current position, in the current line style and color. The Current position is set to the end of the line.

Errors: None.

See also: `LineRel` ([123](#)), `Line` ([123](#))

MoveRel

Declaration: `Procedure MoveRel (DX,DY : Integer;`

Description: `MoveRel` moves the pointer to the point (DX, DY), relative to the current pointer position

Errors: None.

See also: `MoveTo` ([124](#))

MoveTo

Declaration: Procedure MoveTo (X,Y : Integer;

Description: MoveTo moves the pointer to the point (X,Y).

Errors: None.

See also: MoveRel ([123](#))

OutText

Declaration: Procedure OutText (Const TextString : String);

Description: OutText puts TextString on the screen, at the current pointer position, using the current font and text settings. The current position is moved to the end of the text.

Errors: None.

See also: OutTextXY ([124](#))

OutTextXY

Declaration: Procedure OutTextXY (X,Y : Integer; Const TextString : String);

Description: OutText puts TextString on the screen, at position (X,Y), using the current font and text settings. The current position is moved to the end of the text.

Errors: None.

See also: OutText ([124](#))

PieSlice

Declaration: Procedure PieSlice (X,Y : Integer;
Start,Stop,Radius : Word);

Description: PieSlice draws and fills a sector of a circle with center (X,Y) and radius Radius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: Arc ([114](#)), Circle ([115](#)), Sector ([126](#))

PutImage

Declaration: Procedure PutImage (X1,Y1 : Integer; Var Bitmap; How : word) ;

Description: PutImage Places the bitmap in Bitmap on the screen at (X1,Y1). How determines how the bitmap will be placed on the screen. Possible values are :

- CopyPut
- XORPut
- ORPut
- AndPut
- NotPut

Errors: None

See also: [ImageSize \(122\)](#), [GetImage \(118\)](#)

PutPixel

Declaration: Procedure `PutPixel (X,Y : Integer; Color : Word);`

Description: Puts a point at (X, Y) using color Color

Errors: None.

See also: [GetPixel \(120\)](#)

Rectangle

Declaration: Procedure `Rectangle (X1,Y1,X2,Y2 : Integer);`

Description: Draws a rectangle with corners at (X1, Y1) and (X2, Y2), using the current color and style.

Errors: None.

See also: [Bar \(114\)](#), [Bar3D \(114\)](#)

RegisterBGIDriver

Declaration: Function `RegisterBGIDriver (Driver : Pointer) : Integer;`

Description: Registers a user-defined BGI driver

Errors: None.

See also: [InstallUserDriver \(122\)](#), [RegisterBGIFont \(125\)](#)

RegisterBGIFont

Declaration: Function `RegisterBGIFont (Font : Pointer) : Integer;`

Description: Registers a user-defined BGI driver

Errors: None.

See also: [InstallUserFont \(123\)](#), [RegisterBGIDriver \(125\)](#)

RestoreCRTMode

Declaration: Procedure `RestoreCRTMode ;`

Description: Restores the screen modus which was active before the graphical modus was started.

To get back to the graph mode you were last in, you can use `SetGraphMode(GetGraphMode)`

Errors: None.

See also: [InitGraph \(122\)](#)

Sector

Declaration: Procedure Sector (X,Y : Integer;
Start,Stop,XRadius,YRadius : Word);

Description: Sector draws and fills a sector of an ellipse with center (X, Y) and radii XRadius and YRadius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: Arc ([114](#)), Circle ([115](#)), PieSlice ([124](#))

SetActivePage

Declaration: Procedure SetActivePage (Page : Word);

Description: Sets Page as the active page for all graphical output.

Errors: None.

See also:

SetAllPalette

Declaration: Procedure SetAllPalette (Var Palette);

Description: Sets the current palette to Palette. Palette is an untyped variable, usually pointing to a record of type PaletteType

Errors: None.

See also: GetPalette ([120](#))

SetAspectRatio

Declaration: Procedure SetAspectRatio (Xasp,Yasp : Word);

Description: Sets the aspect ratio of the current screen to Xasp/Yasp.

Errors: None

See also: InitGraph ([122](#)), GetAspectRatio ([117](#))

SetBkColor

Declaration: Procedure SetBkColor (Color : Word);

Description: Sets the background color to Color.

Errors: None.

See also: GetBkColor ([117](#)), SetColor ([127](#))

SetColor

Declaration: Procedure SetColor (Color : Word);

Description: Sets the foreground color to Color.

Errors: None.

See also: GetColor ([117](#)), SetBkColor ([126](#))

SetFillPattern

Declaration: Procedure SetFillPattern (FillPattern : FillPatternType,
Color : Word);

Description: SetFillPattern sets the current fill-pattern to FillPattern, and the filling color to Color
The pattern is an 8x8 raster, corresponding to the 64 bits in FillPattern.

Errors: None

See also: GetFillPattern ([118](#)), SetFillStyle ([127](#))

SetFillStyle

Declaration: Procedure SetFillStyle (Pattern, Color : word);

Description: SetFillStyle sets the filling pattern and color to one of the predefined filling patterns. Pattern can be one of the following predefined constants :

- EmptyFill Uses backgroundcolor.
- SolidFill Uses filling color
- LineFill Fills with horizontal lines.
- ltSlashFill Fills with lines from left-under to top-right.
- SlashFill Idem as previous, thick lines.
- BkSlashFill Fills with thick lines from left-Top to bottom-right.
- LtBkSlashFill Idem as previous, normal lines.
- HatchFill Fills with a hatch-like pattern.
- XHatchFill Fills with a hatch pattern, rotated 45 degrees.
- InterLeaveFill
- WideDotFill Fills with dots, wide spacing.
- CloseDotFill Fills with dots, narrow spacing.
- UserFill Fills with a user-defined pattern.

Errors: None.

See also: SetFillPattern ([127](#))

SetGraphBufSize

Declaration: Procedure SetGraphBufSize (BufSize : Word);

Description: SetGraphBufSize is a dummy function which does not do anything; it is no longer needed.

Errors: None.

See also:

SetGraphMode

Declaration: Procedure SetGraphMode (Mode : Integer);

Description: SetGraphMode sets the graphical mode and clears the screen.

Errors: None.

See also: InitGraph ([122](#))

SetLineStyle

Declaration: Procedure SetLineStyle (LineStyle, Pattern, Width : Word);

Description: SetLineStyle sets the drawing style for lines. You can specify a LineStyle which is one of the following pre-defined constants:

- SolidLn=0; draws a solid line.
- DottedLn=1; Draws a dotted line.
- CenterLn=2; draws a non-broken centered line.
- DashedLn=3; draws a dashed line.
- UserBitLn=4; Draws a User-defined bit pattern.

If UserBitLn is specified then Pattern contains the bit pattern. In all another cases, Pattern is ignored. The parameter Width indicates how thick the line should be. You can specify one of the following pre-defined constants:

- NormWidth=1
- ThickWidth=3

Errors: None.

See also: GetLineSettings ([118](#))

SetPalette

Declaration: Procedure SetPalette (ColorNr : Word; NewColor : ShortInt);

Description: SetPalette changes the ColorNr-th entry in the palette to NewColor

Errors: None.

See also: SetAllPalette ([126](#)), SetRGBPalette ([128](#))

SetRGBPalette

Declaration: Procedure SetRGBPalette (ColorNr, Red, Green, Blue : Integer);

Description: SetRGBPalette sets the ColorNr-th entry in the palette to the color with RGB-values Red, Green Blue.

Errors: None.

See also: SetAllPalette ([126](#)), SetPalette ([128](#))

SetTextJustify

Declaration: Procedure SetTextJustify (Horizontal,Vertical : Word);

Description: SetTextJustify controls the placement of new text, relative to the (graphical) cursor position. Horizontal controls horizontal placement, and can be one of the following pre-defined constants:

- LeftText=0; Text is set left of the pointer.
- CenterText=1; Text is set centered horizontally on the pointer.
- RightText=2; Text is set to the right of the pointer.

Vertical controls the vertical placement of the text, relative to the (graphical) cursor position. Its value can be one of the following pre-defined constants :

- BottomText=0; Text is placed under the pointer.
- CenterText=1; Text is placed centered vertically on the pointer.
- TopText=2; Text is placed above the pointer.

Errors: None.

See also: OutText ([124](#)), OutTextXY ([124](#))

SetTextStyle

Declaration: Procedure SetTextStyle (Font,Direction,Magnitude : Word);

Description: SetTextStyle controls the style of text to be put on the screen. pre-defined constants for Font are:

- DefaultFont=0;
- TriplexFont=2;
- SmallFont=2;
- SansSerifFont=3;
- GothicFont=4;

Pre-defined constants for Direction are :

- HorizDir=0;
- VertDir=1;

Errors: None.

See also: GetTextSettings ([120](#))

SetUserCharSize

Declaration: Procedure SetUserCharSize (Xasp1,Xasp2,Yasp1,Yasp2 : Word);

Description: Sets the width and height of vector-fonts. The horizontal size is given by Xasp1/Xasp2, and the vertical size by Yasp1/Yasp2.

Errors: None.

See also: SetTextStyle ([129](#))

SetViewPort

Declaration: Procedure SetViewPort (X1,Y1,X2,Y2 : Integer; Clip : Boolean);

Description: Sets the current graphical viewport (window) to the rectangle defined by the top-left corner (X1, Y1) and the bottom-right corner (X2, Y2). If Clip is true, anything drawn outside the viewport (window) will be clipped (i.e. not drawn). Coordinates specified after this call are relative to the top-left corner of the viewport.

Errors: None.

See also: GetViewSettings ([120](#))

SetVisualPage

Declaration: Procedure SetVisualPage (Page : Word);

Description: SetVisualPage sets the video page to page number Page.

Errors: None

See also: SetActivePage ([126](#))

SetWriteMode

Declaration: Procedure SetWriteMode (Mode : Integer);

Description: SetWriteMode controls the drawing of lines on the screen. It controls the binary operation used when drawing lines on the screen. Mode can be one of the following pre-defined constants:

- CopyPut=0;
- XORPut=1;

Errors: None.

See also:

TextHeight

Declaration: Function TextHeight (S : String) : Word;

Description: TextHeight returns the height (in pixels) of the string S in the current font and text-size.

Errors: None.

See also: TextWidth ([130](#))

TextWidth

Declaration: Function TextWidth (S : String) : Word;

Description: TextWidth returns the width (in pixels) of the string S in the current font and text-size.

Errors: None.

See also: TextHeight ([130](#))

8.5 Target specific issues

In what follows we describe some things that are different on the various platforms:

DOS

WINDOWS

LINUX

Chapter 9

The HEAPTRC unit.

This chapter describes the HEAPTRC unit for Free Pascal. It was written by Pierre Muller. It is system independent, and works on all supported systems.

9.1 Purpose

The HEAPTRC unit can be used to debug your memory allocation/deallocation. It keeps track of the calls to `getmem/freemem`, and, implicitly, of `New/Dispose` statements.

When the program exits, or when you request it explicitly. It displays the total memory used, and then dumps a list of blocks that were allocated but not freed. It also displays where the memory was allocated.

If there are any inconsistencies, such as memory blocks being allocated or freed twice, or a memory block that is released but with wrong size, this will be displayed also.

The information that is stored/displayed can be customized using some constants.

9.2 Usage

All that you need to do is to include `heaptrc` in the `uses` clause of your program. Make sure that it is the first unit in the clause, otherwise memory allocated in initialization code of units that precede the `heaptrc` unit will not be accounted for, causing an incorrect memory usage report.

If you use the `-gh` switch, the compiler will insert the unit by itself, so you don't have to include it in your `uses` clause.

The following example shows how to use the `heaptrc` unit.

```
Program heapex;  
  
{ Program used to demonstrate the usage of heaptrc unit }  
  
Uses heaptrc;  
  
Var P1 : ^ Longint;  
      P2 : Pointer;  
      I : longint;  
  
begin
```

```
New(P1);
// causes previous allocation not to be de-allocated
New(P1);
Dispose(P1);
For I:=1 to 10 do
  begin
    GetMem (P2,128);
    // When I is even, deallocate block. We loose 5 times 128
    // bytes this way.
    If (I mod 2) = 0 Then FreeMem(P2,128);
  end;
  GetMem(P2,128);
  // This will provoke an error and a memory dump
  Freemem (P2,64);
end.
```

This is the memory dump shown when running this program:

```
Marked memory at 0040FA50 invalid
Wrong size : 128 allocated 64 freed
0x00408708
0x0040CB49
0x0040C481
Call trace for block 0x0040FA50 size 128
0x0040CB3D
0x0040C481
```

If you use the `lineinfo` unit (or use the `-gl` switch) as well, then `heaptrc` will also give you the filenames and line-numbers of the procedures in the backtrace:

```
Marked memory at 00410DA0 invalid
Wrong size : 128 allocated 64 freed
0x004094B8
0x0040D8F9  main,  line 25 of heapex.pp
0x0040D231
Call trace for block 0x00410DA0 size 128
0x0040D8ED  main,  line 23 of heapex.pp
0x0040D231
```

If lines without filename/line-number occur, this means there is a unit which has no debug info included.

9.3 Constants, Types and variables

The `FillExtraInfoType` is a procedural type used in the `SetExtraInfo` (135) call.

```
type
  FillExtraInfoType = procedure(p : pointer);
```

The following typed constants allow to fine-tune the standard dump of the memory usage by `DumpHeap` (134):

```
const
  tracesize = 8;
```

```
quicktrace : boolean = true;  
HaltOnError : boolean = true;  
keepreleased : boolean = false;  
add_tail : boolean = true;  
usecrc : boolean = true
```

`TraceSize` specifies how many levels of calls are displayed of the call stack during the memory dump. If you specify `keepreleased:=True` then half the `TraceSize` is reserved for the `GetMem` call stack, and the other half is reserved for the `FreeMem` call stack. For example, the default value of 8 will cause eight levels of call frames to be dumped for the `getmem` call if `keepreleased` is `False`. If `KeepReleased` is true, then 4 levels of call frames will be dumped for the `GetMem` call and 4 frames will be dumped for the `FreeMem` call. If you want to change this value, you must recode the `heaptrc` unit.

`Quicktrace` determines whether the memory manager checks whether a block that is about to be released is allocated correctly. This is a rather time consuming search, and slows program execution significantly, so by default it is set to `False`.

If `HaltOnError` is set to `True` then an illegal call to `FreeMem` will cause the memory manager to execute a `halt(1)` instruction, causing a memory dump. By Default it is set to `True`.

If `keepreleased` is set to true, then a list of freed memory blocks is kept. This is useful if you suspect that the same memory block is released twice. However, this option is very memory intensive, so use it sparingly, and only when it's really necessary.

If `add_tail` is `True` (the default) then a check is also performed on the memory location just behind the allocated memory.

If `usecrc` is `True` (the default) then a crc check is performed on locations before and after the allocated memory. This is useful to detect memory overwrites.

9.4 Functions and procedures

DumpHeap

Declaration: procedure `DumpHeap`;

Description: `DumpHeap` dumps to standard output a summary of memory usage. It is called automatically by the `heaptrc` unit when your program exits (by instaling an exit procedure), but it can be called at any time

Errors: None.

See also: `MarkHeap` ([134](#))

MarkHeap

Declaration: procedure `MarkHeap`;

Description: `MarkHeap` marks all memory blocks with a special signature. You can use this if you think that you corrupted the memory.

Errors: None.

See also: `DumpHeap` ([134](#))

SetExtraInfo

Declaration: `procedure SetExtraInfo( size : longint; func : FillExtraInfoType);`

Description: You can use `SetExtraInfo` to store extra info in the blocks that the `heaptrc` unit reserves when tracing `getmem` calls. `Size` indicates the size (in bytes) that the trace mechanism should reserve for your extra information. For each call to `getmem`, `func` will be called, and passed a pointer to the memory reserved.

When dumping the memory summary, the extra info is shown as `Longint` values.

Errors: You can only call `SetExtraInfo` if no memory has been allocated yet. If memory was already allocated prior to the call to `SetExtraInfo`, then an error will be displayed on standard error output, and a `DumpHeap` ([134](#)) is executed.

See also: `DumpHeap` ([134](#)), `SetHeapTraceOutput` ([136](#))

Program `heapex;`

{ Program used to demonstrate the usage of heaptrc unit }

Uses `heaptrc;`

Var `P1 : ^ Longint;`
 `P2 : Pointer;`
 `I : longint;`
 `Marker : Longint;`

Procedure `SetMarker (P : pointer);`

Type `PLongint = ^ Longint;`

begin
 `PLongint(P)^:= Marker;`
end;

Procedure `Part1;`

begin
 // Blocks allocated here are marked with \$FFAAFFAA = -5570646
 `Marker := $FFAAFFAA;`
 `New(P1);`
 `New(P1);`
 `Dispose(P1);`
 For `I:=1 to 10 do`
 begin
 `GetMem ( P2,128);`
 If `( I mod 2) = 0 Then FreeMem(P2,128);`
 end;
 `GetMem(P2,128);`
 end;

Procedure `Part2;`

begin
 // Blocks allocated here are marked with \$FAFAFAFA = -84215046
 `Marker := $FAFAFAFA;`
 `New(P1);`
 `New(P1);`

```
Dispose(P1);
For I:=1 to 10 do
begin
  GetMem ( P2,128);
  If ( I mod 2) = 0 Then FreeMem(P2,128);
end;
GetMem(P2,128);
end;

begin
  SetExtraInfo ( SizeOf (Marker), @SetMarker);
  Writeln ( ' Part _1' );
  part1 ;
  Writeln ( ' Part _2' );
  part2 ;
end.
```

SetHeapTraceOutput

Declaration: Procedure SetHeapTraceOutput(const name : string);

Description: SetHeapTraceOutput sets the filename into which heap trace info will be written. By default information is written to standard output, this function allows you to redirect the information to a file with full filename name.

Errors: If the file cannot be written to, errors will occur when writing the trace.

See also: SetExtraInfo ([135](#))

Chapter 10

The IPC unit.

This chapter describes the IPC unit for Free Pascal. It was written for LINUX by Michaël Van Canneyt. It gives all the functionality of system V Inter-Process Communication: shared memory, semaphores and messages. It works only on the LINUX operating system.

The chapter is divided in 2 sections:

- The first section lists types, constants and variables from the interface part of the unit.
- The second section describes the functions defined in the unit.

10.1 Types, Constants and variables :

Variables

```
Var
  IPCError : longint;
```

The `IPCError` variable is used to report errors, by all calls.

Constants

Many constants here are provided for completeness only, and should under normal circumstances not be used by the programmer.

```
Const
  IPC_CREAT = 1 shl 9; { create if key is nonexistent }
  IPC_EXCL  = 2 shl 9; { fail if key exists }
  IPC_NOWAIT = 4 shl 9; { return error on wait }
```

These constants are used in the various `xxxget` calls.

```
IPC_RMID = 0;      { remove resource }
IPC_SET  = 1;      { set ipc_perm options }
IPC_STAT = 2;      { get ipc_perm options }
IPC_INFO = 3;      { see ipcs }
```

These constants can be passed to the various `xxxctl` calls.

```
const
MSG_NOERROR = 1 shl 12;
MSG_EXCEPT = 2 shl 12;
MSGMNI = 128;
MSGMAX = 4056;
MSGMNB = 16384;
```

These constants are used in the messaging system, they are not for use by the programmer.

```
const
SEM_UNDO = $1000;
GETPID = 11;
GETVAL = 12;
GETALL = 13;
GETNCNT = 14;
GETZCNT = 15;
SETVAL = 16;
SETALL = 17;
```

These constants can be specified in the `semop` ([146](#)) call.

```
SEMMNI = 128;
SEMMSL = 32;
SEMMNS = (SEMMNI * SEMMSL);
SEMOPM = 32;
SEVMX = 32767;
```

These constants are used internally by the semaphore system, they should not be used by the programmer.

```
const
SHM_R      = 4 shl 6;
SHM_W      = 2 shl 6;
SHM_RDONLY = 1 shl 12;
SHM_RND     = 2 shl 12;
SHM_REMAP  = 4 shl 12;
SHM_LOCK   = 11;
SHM_UNLOCK = 12;
```

These constants are used in the `shmctl` ([152](#)) call.

Types

The following two types are provided because they are needed. One they should be defined in the system unit, however.

```
Type
PULong = ^Cardinal;
PWord  = ^Word;
```

```
Type
TKey   = Longint;
```

`TKey` is the type returned by the `ftok` ([142](#)) key generating function.

```
type
  PIPC_Perm = ^TIPC_Perm;
  TIPC_Perm = record
    key : TKey;
    uid,
    gid,
    cuid,
    cgid,
    mode,
    seq : Word;
  end;
```

The TIPC_Perm structure is used in all IPC systems to specify the permissions.

```
Type
  PSHMid_DS = ^TSHMid_ds;
  TSHMid_ds = record
    shm_perm : TIPC_Perm;
    shm_segsz : longint;
    shm_atime : longint;
    shm_dtime : longint;
    shm_ctime : longint;
    shm_cpid : word;
    shm_lpid : word;
    shm_nattch : integer;
    shm_npages : word;
    shm_pages : Pointer;
    attaches : pointer;
  end;
```

The TSHMid_ds structure is used in the shmctl ([152](#)) call to set or retrieve settings concerning shared memory.

```
type
  PSHMinfo = ^TSHMinfo;
  TSHMinfo = record
    shmmax : longint;
    shmmmin : longint;
    shmmni : longint;
    shmseg : longint;
    shmall : longint;
  end;
```

The TSHMinfo record is used by the shared memory system, and should not be accessed by the programmer directly.

```
type
  PMSG = ^TMSG;
  TMSG = record
    msg_next : PMSG;
    msg_type : Longint;
    msg_spot : PChar;
    msg_stime : Longint;
    msg_ts : Integer;
  end;
```

The TMSG record is used in the handling of message queues. There should be few cases where the programmer needs to access this data.

```
type
  PMSQid_ds = ^TMSQid_ds;
  TMSQid_ds = record
    msg_perm    : TIPC_perm;
    msg_first   : PMsg;
    msg_last    : PMsg;
    msg_stime   : Longint;
    msg_rtime   : Longint;
    msg_ctime   : Longint;
    wwait       : Pointer;
    rwait       : pointer;
    msg_cbytes  : word;
    msg_qnum    : word;
    msg_qbytes  : word;
    msg_lspid   : word;
    msg_lrpid   : word;
  end;
```

The TMSQid_ds record is returned by the msgctl (143) call, and contains all data about a message queue.

```
PMSGbuf = ^TMSGbuf;
TMSGbuf = record
  mtype : longint;
  mtext : array[0..0] of char;
end;
```

The TMSGbuf record is a record containing the data of a record. you should never use this record directly, instead you should make your own record that follows the structure of the TMSGbuf record, but that has a size that is big enough to accomodate your messages. The mtype field should always be present, and should always be filled.

```
Type
  PMSGinfo = ^TMSGinfo;
  TMSGinfo = record
    msgpool : Longint;
    msgmap  : Longint;
    msgmax  : Longint;
    msgmnb  : Longint;
    msgmni  : Longint;
    msgssz  : Longint;
    msgtql  : Longint;
    msgseg  : Word;
  end;
```

The TMSGinfo record is used internally by the message queue system, and should not be used by the programmer directly.

```
Type
  PSEMid_ds = ^PSEMid_ds;
  TSEMid_ds = record
```

```
sem_perm : tipc_perm;
sem_otime : longint;
sem_ctime : longint;
sem_base      : pointer;
sem_pending    : pointer;
sem_pending_last : pointer;
undo          : pointer;
sem_nsems : word;
end;
```

The TSEmid_ds structure is returned by the `semctl` (147) call, and contains all data concerning a semaphore.

Type

```
PSEmbuf = ^TSEmbuf;
TSEmbuf = record
    sem_num : word;
    sem_op  : integer;
    sem_flg : integer;
end;
```

The TSEmbuf record is used in the `semop` (146) call, and is used to specify which operations you want to do.

Type

```
PSEMinfo = ^TSEMinfo;
TSEMinfo = record
    semmap : longint;
    semmni : longint;
    semmns : longint;
    semmnu : longint;
    semmsl : longint;
    semopm : longint;
    semume : longint;
    semusz : longint;
    semvmx : longint;
    semaem : longint;
end;
```

The TSEMinfo record is used internally by the semaphore system, and should not be used directly.

Type

```
PSEMun = ^TSEMun;
TSEMun = record
    case longint of
        0 : ( val : longint );
        1 : ( buf : PSEmid_ds );
        2 : ( arr : PWord );
        3 : ( padbuf : PSEminfo );
        4 : ( padpad : pointer );
    end;
```

The TSEMun variant record (actually a C union) is used in the `semctl` (147) call.

10.2 Functions and procedures

ftok

Declaration: Function `ftok` (`Path` : `String`; `ID` : `char`) : `TKey`;

Description: `ftok` returns a key that can be used in a `semget` (146), `shmget` (151) or `msgget` (142) call to access a new or existing IPC resource.

`Path` is the name of a file in the file system, `ID` is a character of your choice. The `ftok` call does the same as it's C counterpart, so a pascal program and a C program will access the same resource if they use the same `Path` and `ID`

Errors: `ftok` returns -1 if the file in `Path` doesn't exist.

See also: `semget` (146), `shmget` (151), `msgget` (142)

For an example, see `msgctl` (143), `semctl` (147), `shmctl` (152).

msgget

Declaration: Function `msgget`(`key`: `TKey`; `msgflg`:`longint`):`longint`;

Description: `msgget` returns the ID of the message queue described by `key`. Depending on the flags in `msgflg`, a new queue is created.

`msgflg` can have one or more of the following values (combined by ORs):

IPC_CREATThe queue is created if it doesn't already exist.

IPC_EXCLIf used in combination with **IPC_CREAT**, causes the call to fail if the queue already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

Errors: On error, -1 is returned, and `IPCError` is set.

See also: `ftok` (142), `msgsnd` (142), `msgrcv` (143), `msgctl` (143), `semget` (2)

For an example, see `msgctl` (143).

msgsnd

Declaration: Function `msgsnd`(`msqid`:`longint`; `msgp`: `PMSGBuf`; `msgsz`: `longint`; `msgflg`:`longint`):`Boolean`;

Description: `msgsnd` sends a message to a message queue with ID `msqid`. `msgp` is a pointer to a message buffer, that should be based on the `TMSGBuf` type. `msgsz` is the size of the message (NOT of the message buffer record !)

The `msgflg` can have a combination of the following values (ORed together):

0No special meaning. The message will be written to the queue. If the queue is full, then the process is blocked.

IPC_NOWAITIf the queue is full, then no message is written, and the call returns immediatly.

The function returns `True` if the message was sent successfully, `False` otherwise.

Errors: In case of error, the call returns `False`, and `IPCError` is set.

See also: `msgget` (142), `msgrcv` (143), `seefmsgctl`

For an example, see `msgctl` (143).

msgrcv

Declaration: Function `msgrcv(msqid:longint; msgp: PMSGBuf; msgsz: longint; msgtyp:longint; msgflg:longint): Boolean;`

Description: `msgrcv` retrieves a message of type `msgtyp` from the message queue with ID `msqid`. `msgtyp` corresponds to the `mtype` field of the `TMSGbuf` record. The message is stored in the `MSGbuf` structure pointed to by `msgp`.

The `msgflg` parameter can be used to control the behaviour of the `msgrcv` call. It consists of an ORed combination of the following flags:

0No special meaning.

IPC_NOWAITif no messages are available, then the call returns immediatly, with the `ENOMSG` error.

MSG_NOERRORIf the message size is wrong (too large), no error is generated, instead the message is truncated. Normally, in such cases, the call returns an error (`E2BIG`)

The function returns `True` if the message was received correctly, `False` otherwise.

Errors: In case of error, `False` is returned, and `IPCError` is set.

See also: `msgget` (142), `msgsnd` (142), `msgctl` (143)

For an example, see `msgctl` (143).

msgctl

Declaration: Function `msgctl(msqid:longint; cmd: longint; buf: PMSQid_ds): Boolean;`

Description: `msgctl` performs various operations on the message queue with id `ID`. Which operation is performed, depends on the `cmd` parameter, which can have one of the following values:

IPC_STATIn this case, the `msgctl` call fills the `TMSQid_ds` structure with information about the message queue.

IPC_SETIn this case, the `msgctl` call sets the permissions of the queue as specified in the `ipc_perm` record inside `buf`.

IPC_RMIDIf this is specified, the message queue will be removed from the system.

`buf` contains the data that are needed by the call. It can be `Nil` in case the message queue should be removed.

The function returns `True` if successfull, `False` otherwise.

Errors: On error, `False` is returned, and `IPCError` is set accordingly.

See also: `msgget` (142), `msgsnd` (142), `msgrcv` (143)

```
program msgtool;

Uses ipc;

Type
  PMyMsgBuf = ^ TMyMsgBuf;
  TMyMsgBuf = record
    mtype : Longint;
    mtext : string [255];
  end;

Procedure DoError ( Const Msg : string );

begin
  Writeln (msg, ' returned_an_error _:_', ipcerror);
  halt (1);
end;

Procedure SendMessage ( Id : Longint;
                        Var Buf : TMyMsgBuf;
                        MType : Longint;
                        Const MText : String );

begin
  Writeln ( ' Sending_message.' );
  Buf.mtype:=mtype;
  Buf.Mtext:=mtext;
  If not msgsnd( Id , PMsgBuf(@Buf),256,0) then
    DoError( ' msgsnd' );
end;

Procedure ReadMessage ( ID : Longint;
                        Var Buf : TMyMsgBuf;
                        MType : longint );

begin
  Writeln ( ' Reading_message.' );
  Buf.MType:=MType;
  If msgrcv( ID , PMSGBuf(@Buf),256, mtype, 0) then
    Writeln ( ' Type:_:', buf.mtype, '_Text _:', buf.mtext)
  else
    DoError ( ' msgrcv' );
end;

Procedure RemoveQueue ( ID : Longint);

begin
  If msgctl ( id,IPC_RMID, Nil ) then
    Writeln ( ' Removed_queue_with_id ', Id);
end;

Procedure ChangeQueueMode ( ID,mode : longint);

Var QueueDS : TMSQid_ds;

begin
  If Not msgctl ( Id,IPC_STAT,@QueueDS) then
```

```
    DoError ( ' msgctl _:_ stat ' );
    Writeln ( ' Old_permissions _:_ ', QueueDS.msg_perm.mode);
    QueueDS.msg_perm.mode:=Mode;
    if msgctl ( ID,IPC_SET,@QueueDS) then
        Writeln ( ' New_permissions _:_ ', QueueDS.msg_perm.mode)
    else
        DoError ( ' msgctl _:_ IPC_SET ' );
end;

procedure usage;

begin
    Writeln ( ' Usage _:_ msgtool _s(end) _<type> _<text> _(max_255_characters) ' );
    Writeln ( ' _:_ _r( eceive) _<type>' );
    Writeln ( ' _:_ _d( elete) ' );
    Writeln ( ' _:_ _m( ode) _<decimal_mode>' );
    halt (1);
end;

Function StrToInt ( S : String ): longint;

Var M : longint;
    C : Integer;

begin
    val ( S,M,C);
    If C<>0 Then DoError ( ' StrToInt _:_ '+S);
    StrToInt:=M;
end;

Var
    Key : Tkey;
    ID : longint;
    Buf : TMyMsgBuf;

begin
    If Paramcount<1 then Usage;
    key := Ftok ( ' . ', 'M' );
    ID:=msgget(key,IPC_CREAT or 438);
    If ID<0 then DoError ( ' MsgGet' );
    Case upCase(Paramstr(1)[1]) of
        'S' : If ParamCount<>3 then
                Usage
            else
                SendMessage ( id , Buf , StrToInt ( Paramstr (2)), paramstr (3));
        'R' : If ParamCount<>2 then
                Usage
            else
                ReadMessage ( id , buf , strtoint ( Paramstr (2)));
        'D' : If ParamCount<>1 then
                Usage
            else
                RemoveQueue ( ID);
        'M' : If ParamCount<>2 then
                Usage
            else
                ChangeQueueMode ( id , strtoint ( paramstr (2)));
    else

```

```

        Usage
    end;
end.

```

semget

Declaration: Function `semget(key:Tkey; nsems:longint; semflg:longint): longint;`

Description: `msgget` returns the ID of the semaphore set described by `key`. Depending on the flags in `semflg`, a new queue is created.

`semflg` can have one or more of the following values (combined by ORs):

IPC_CREATThe queue is created if it doesn't already exist.

IPC_EXCLIf used in combination with `IPC_CREAT`, causes the call to fail if the set already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

if a new set of semaphores is created, then there will be `nsems` semaphores in it.

Errors: On error, -1 is returned, and `IPCError` is set.

See also: `ftok` ([142](#)), `semop` ([146](#)), `semctl` ([147](#))

semop

Declaration: Function `semop(semid:longint; sops: pointer; nsops: cardinal): Boolean;`

Description: `semop` performs a set of operations on a message queue. `sops` points to an array of type `TSEMbuf`. The array should contain `nsops` elements.

The fields of the `TSEMbuf` structure

```

TSEMbuf = record
    sem_num : word;
    sem_op  : integer;
    sem_flg : integer;

```

should be filled as follows:

sem_numThe number of the semaphore in the set on which the operation must be performed.

sem_opThe operation to be performed. The operation depends on the sign of `sem_op`

- 1.A positive number is simply added to the current value of the semaphore.
- 2.If 0 (zero) is specified, then the process is suspended until the specified semaphore reaches zero.
- 3.If a negative number is specified, it is subtracted from the current value of the semaphore. If the value would become negative then the process is suspended until the value becomes big enough, unless `IPC_NOWAIT` is specified in the `sem_flg`.

sem_flgOptional flags: if `IPC_NOWAIT` is specified, then the calling process will never be suspended.

The function returns `True` if the operations were successful, `False` otherwise.

Errors: In case of error, `False` is returned, and `IPCError` is set.

See also: `semget` ([146](#)), `semctl` ([147](#))

semctl

Declaration: `Function semctl(semid:longint; semnum:longint; cmd:longint; var arg:tsemun): longint;`

Description: `semctl` performs various operations on the semaphore `semnum` with semaphore set id `ID`.

The `arg` parameter supplies the data needed for each call. This is a variant record that should be filled differently, according to the command:

Type

```
TSEMun = record
  case longint of
    0 : ( val : longint );
    1 : ( buf : PSEMid_ds );
    2 : ( arr : Pword );
    3 : ( padbuf : PSEminfo );
    4 : ( padpad : pointer );
  end;
```

Which operation is performed, depends on the `cmd` parameter, which can have one of the following values:

IPC_STATIn this case, the `arg` record should have its `buf` field set to the address of a `TSEMid_ds` record. The `semctl` call fills this `TSEMid_ds` structure with information about the semaphore set.

IPC_SETIn this case, the `arg` record should have its `buf` field set to the address of a `TSEMid_ds` record. The `semctl` call sets the permissions of the queue as specified in the `ipc_perm` record.

IPC_RMIDIf this is specified, the semaphore set is removed from the system.

GETALLIn this case, the `arr` field of `arg` should point to a memory area where the values of the semaphores will be stored. The size of this memory area is `SizeOf(Word)* Number of semaphores in the set`. This call will then fill the memory array with all the values of the semaphores.

GETNCNTThis will fill the `val` field of the `arg` union with the number of processes waiting for resources.

GETPID`semctl` returns the process ID of the process that performed the last `semop` (146) call.

GETVAL`semctl` returns the value of the semaphore with number `semnum`.

GETZCNT`semctl` returns the number of processes waiting for semaphores that reach value zero.

SETALLIn this case, the `arr` field of `arg` should point to a memory area where the values of the semaphores will be retrieved from. The size of this memory area is `SizeOf(Word)* Number of semaphores in the set`. This call will then set the values of the semaphores from the memory array.

SETVALThis will set the value of semaphore `semnum` to the value in the `val` field of the `arg` parameter.

The function returns -1 on error.

Errors: The function returns -1 on error, and `IPCError` is set accordingly.

See also: `semget` (146), `semop` (146)

```
Program semtool;

{ Program to demonstrat the use of semaphores }

Uses ipc;

Const MaxSemValue = 5;

Procedure DoError ( Const Msg : String );

begin
    Writeln ( ' Error _:_', msg, '_Code:_:_', IPCError );
    Halt (1);
end;

Function getsemval ( ID, Member : longint ) : longint;

Var S : TSEMun;

begin
    GetSemVal:= SemCtl( id , member, GETVAL, S);
end;

Procedure DispVal ( ID, member : longint );

begin
    writeln ( ' Value _for _member_', member, '_ is _', GetSemVal( ID , Member));
end;

Function GetMemberCount ( ID : Longint ) : longint;

Var opts : TSEMun;
    semds : TSEMids;

begin
    opts . buf := @semds;
    If semctl( Id , 0, IPC_STAT, opts) <> -1 then
        GetMemberCount:= semds . sem_nsems
    else
        GetMemberCount:= -1;
end;

Function OpenSem ( Key : TKey ) : Longint;

begin
    OpenSem:= semget( Key, 0, 438);
    If OpenSem=-1 then
        DoError ( ' OpenSem' );
end;

Function CreateSem ( Key : TKey; Members : Longint ) : Longint;

Var Count : Longint;
    Semopts : TSemun;

begin
    If members>semmsl then
```

```
    DoError ( ' Sorry ,_maximum_number_of_semaphores_in_set_exceeded' );
WriteIn ( ' Trying_to_create_a_new_semaphore_set_with_',members,'_members.' );
CreateSem:=semget(key,members,IPC_CREAT or IPC_Excl or 438);
If CreateSem=-1 then
    DoError ( ' Semaphore_set_already_exists.' );
Semopts.val:=MaxSemValue; { Initial value of semaphores }
For Count:=0 to Members-1 do
    semctl ( CreateSem, count, setval, semopts);
end;

Procedure lockSem ( ID,Member: Longint);

Var lock : TSEMbuf;

begin
    With lock do
        begin
            sem_num:=0;
            sem_op:=-1;
            sem_flg:=IPC_NOWAIT;
            end;
        if ( member<0) or ( member>GetMemberCount(ID)-1) then
            DoError ( ' semaphore_member_out_of_range' );
        if getsemval(ID,member)=0 then
            DoError ( ' Semaphore_resources_exhausted_(no_lock)' );
        lock.sem_num:=member;
        WriteIn ( ' Attempting_to_lock_member_',member,'_of_semaphore_',ID);
        if not semop( Id ,@lock,1) then
            DoError ( ' Lock_failed' )
        else
            WriteIn ( ' Semaphore_resources_decremented_by_one' );
            dispval (ID,Member);
        end;

Procedure UnlockSem ( ID,Member: Longint);

Var Unlock : TSEMbuf;

begin
    With Unlock do
        begin
            sem_num:=0;
            sem_op:=1;
            sem_flg:=IPC_NOWAIT;
            end;
        if ( member<0) or ( member>GetMemberCount(ID)-1) then
            DoError ( ' semaphore_member_out_of_range' );
        if getsemval(ID,member)=MaxSemValue then
            DoError ( ' Semaphore_not_locked' );
        Unlock.sem_num:=member;
        WriteIn ( ' Attempting_to_unlock_member_',member,'_of_semaphore_',ID);
        if not semop( Id ,@unlock,1) then
            DoError ( ' Unlock_failed' )
        else
            WriteIn ( ' Semaphore_resources_incremented_by_one' );
            dispval (ID,Member);
        end;
end;
```

```
Procedure RemoveSem (ID : longint);

var S : TSemun;

begin
  If semctl (Id ,0, IPC_RMID,s)<>-1 then
    Writeln ( ' Semaphore_removed' )
  else
    DoError ( ' Couldn't remove semaphore' );
end;

Procedure ChangeMode (ID,Mode : longint);

Var rc : longint;
    opts : TSEMun;
    semds : TSEMid_ds;

begin
  opts.buf:=@semds;
  If not semctl ( Id ,0, IPC_STAT, opts)<>-1 then
    DoError ( ' Couldn't stat semaphore' );
  Writeln ( ' Old_permissions_were_', semds.sem_perm.mode);
  semds.sem_perm.mode:=mode;
  If semctl (id ,0, IPC_SET, opts)<>-1 then
    Writeln ( ' Set_permissions_to_', mode)
  else
    DoError ( ' Couldn't set permissions' );
end;

Procedure PrintSem (ID : longint);

Var I,cnt : longint;

begin
  cnt:=getmembercount(ID);
  Writeln ( ' Semaphore_', ID, '_has_', cnt, '_Members' );
  For I:=0 to cnt-1 Do
    DispVal (id , i );
end;

Procedure USage;

begin
  Writeln ( ' Usage_: semtool_c(reate)_<count>' );
  Writeln ( ' _____l(ock)_<member>' );
  Writeln ( ' _____u(nlock)_<member>' );
  Writeln ( ' _____d(elete)' );
  Writeln ( ' _____m(ode)_<mode>' );
  halt (1);
end;

Function StrToInt (S : String): longint;

Var M : longint;
    C : Integer;

begin
```



```

    val (S,M,C);
    If C<>0 Then DoError ( ' StrToInt ̣:̣'+S);
    StrToInt:=M;
end;

Var Key : Tkey;
    ID : Longint;

begin
    If ParamCount<1 then Usage;
    key:=ftok ( '.' , 's' );
    Case UpCase(Paramstr(1)[1]) of
        'C' : begin
            if paramcount<>2 then usage;
            CreateSem ( key, strtoint (paramstr(2)));
            end;
        'L' : begin
            if paramcount<>2 then usage;
            ID:=OpenSem ( key);
            LockSem ( ID, strtoint (paramstr(2)));
            end;
        'U' : begin
            if paramcount<>2 then usage;
            ID:=OpenSem ( key);
            UnLockSem ( ID, strtoint (paramstr(2)));
            end;
        'M' : begin
            if paramcount<>2 then usage;
            ID:=OpenSem ( key);
            ChangeMode ( ID, strtoint (paramstr(2)));
            end;
        'D' : Begin
            ID:=OpenSem(Key);
            RemoveSem(Id );
            end;
        'P' : begin
            ID:=OpenSem(Key);
            PrintSem ( Id );
            end;
    else
        Usage
    end;
end.

```

shmget

Declaration: Function shmget(key: Tkey; Size:longint; flag:longint):longint;

Description: shmget returns the ID of a shared memory block, described by key. Depending on the flags in flag, a new memory block is created.

flag can have one or more of the following values (combined by ORs):

IPC_CREATThe queue is created if it doesn't already exist.

IPC_EXCLIf used in combination with IPC_CREAT, causes the call to fail if the queue already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

if a new memory block is created, then it will have size `Size` semaphores in it.

Errors: On error, -1 is returned, and `IPCError` is set.

See also:

shmat

Declaration: Function `shmat (shmid:longint; shmaddr:pchar; shmflg:longint):pchar;`

Description: `shmat` attaches a shared memory block with identified `shmid` to the current process. The function returns a pointer to the shared memory block.

If `shmaddr` is `Nil`, then the system chooses a free unmapped memory region, as high up in memory space as possible.

If `shmaddr` is non-nil, and `SHM_RND` is in `shmflg`, then the returned address is `shmaddr`, rounded down to `SHMLBA`. If `SHM_RND` is not specified, then `shmaddr` must be a page-aligned address.

The parameter `shmflg` can be used to control the behaviour of the `shmat` call. It consists of a ORed combination of the following constants:

SHM_RNDThe suggested address in `shmaddr` is rounded down to `SHMLBA`.

SHM_RDONLYthe shared memory is attached for read access only. Otherwise the memory is attached for read-write. The process then needs read-write permissions to access the shared memory.

Errors: If an error occurs, -1 is returned, and `IPCError` is set.

See also: `shmget` ([151](#)), `shmdt` ([152](#)), `shmctl` ([152](#))

For an example, see `shmctl` ([152](#)).

shmdt

Declaration: Function `shmdt (shmaddr:pchar):boolean;`

Description: `shmdt` detaches the shared memory at address `shmaddr`. This shared memory block is unavailable to the current process, until it is attached again by a call to `shmat` ([152](#)).

The function returns `True` if the memory block was detached successfully, `False` otherwise.

Errors: On error, `False` is returned, and `IPCError` is set.

See also: `shmget` ([151](#)), `shmat` ([152](#)), `shmctl` ([152](#))

shmctl

Declaration: Function `shmctl(shmid:longint; cmd:longint; buf: pshmid_ds): Boolean;`

Description: `shmctl` performs various operations on the shared memory block identified by identifier `shmid`.

The `buf` parameter points to a `TSHMid_ds` record. The `cmd` parameter is used to pass which operation is to be performed. It can have one of the following values :

IPC_STATshmctl fills the TSHMid_ds record that **buf** points to with the available information about the shared memory block.

IPC_SET applies the values in the **ipc_perm** record that **buf** points to, to the shared memory block.

IPC_RMID the shared memory block is destroyed (after all processes to which the block is attached, have detached from it).

If successful, the function returns **True**, **False** otherwise.

Errors: If an error occurs, the function returns **False**, and **IPCerror** is set.

See also: **shmget** ([151](#)), **shmat** ([152](#)), **shmdt** ([152](#))

```
Program shmtool ;

uses ipc , strings ;

Const SegSize = 100;

var key : Tkey;
    shmid, cntr : longint;
    segptr : pchar;

Procedure USage;

begin
  Writeln ( ' Usage_: _shmtool_w( rite )_text ' );
  writeln ( ' _____r( ead) ' );
  writeln ( ' _____d( elete) ' );
  writeln ( ' _____m( ode_change)_mode' );
  halt (1);
end;

Procedure Writeshm ( ID : Longint; ptr : pchar; S : string );

begin
  strcpy ( ptr, S );
end;

Procedure Readshm( ID : longint; ptr : pchar );

begin
  Writeln ( ' Read_: _', ptr );
end;

Procedure removeshm ( ID : Longint );

begin
  shmctl ( ID, IPC_RMID, Nil );
  writeln ( ' Shared_memory_marked_for_deletion ' );
end;

Procedure CHangeMode ( ID : longint; mode : String );

Var m : word;
    code : integer;
    data : TSHMid_ds;
```

```
begin
  val (mode,m,code);
  if code<>0 then
    usage;
  If Not shmctl (shmids,IPC_STAT,@data) then
    begin
      writeln ( ' Error _shmctl _', ipcerror );
      halt(1);
    end;
  writeln ( ' Old_permissions _', data.shm_perm.mode);
  data.shm_perm.mode:=m;
  If Not shmctl (shmids,IPC_SET,@data) then
    begin
      writeln ( ' Error _shmctl _', ipcerror );
      halt(1);
    end;
  writeln ( ' New_permissions _', data.shm_perm.mode);
end;

begin
  if paramcount<1 then usage;
  key := ftok ( '.' , 'S' );
  shmids := shmget(key, segsize, IPC_CREAT or IPC_EXCL or 438);
  If shmids=-1 then
    begin
      writeln ( ' Shared_memory_exists _Opening_as_client ');
      shmids := shmget(key, segsize, 0);
      If shmids = -1 then
        begin
          writeln ( ' shmget _Error _', ipcerror );
          halt(1);
        end
      end
    else
      writeln ( ' Creating _new_shared_memory_segment. ');
      segptr := shmat(shmids, nil, 0);
      if longint(segptr)=-1 then
        begin
          writeln ( ' Shmat _error _', ipcerror );
          halt(1);
        end;
      case upcase(paramstr(1)[1]) of
        'W' : writeshm (shmids, segptr, paramstr(2));
        'R' : readshm (shmids, segptr);
        'D' : removeshm(shmids);
        'M' : changemode (shmids, paramstr(2));
      else
        begin
          writeln ( paramstr(1));
          usage;
        end;
      end;
end;
end.
```

Chapter 11

The LINUX unit.

This chapter describes the LINUX unit for Free Pascal. The unit was written by Michaël van Canneyt. It works only on the Linux operating system. This chapter is divided in 3 sections:

- The first section lists all constants, types and variables, as listed in the interface section of the LINUX unit.
- The second section gives an overview of all available functions, grouped by category.
- The third section describes all procedures and functions in the LINUX unit.

11.1 Type, Variable and Constant declarations

Types

PGlob and TGlob are 2 types used in the Glob ([202](#)) function:

```
PGlob = ^TGlob;  
TGlob = record  
    Name : PChar;  
    Next : PGlob;  
end;
```

The following types are used in the signal-processing procedures.

```
tfpreg = record  
    significand: array[0..3] of word;  
    exponent: word;  
end;  
  
pfpstate = ^tfpstate;  
tfpstate = record  
    cw, sw, tag, ipoff, cssel, dataoff, datasel: cardinal;  
    st: array[0..7] of tfpreg;  
    status: cardinal;  
end;  
  
PSigContextRec = ^SigContextRec;  
SigContextRec = record
```

```
gs, __gsh: word;
fs, __fsh: word;
es, __esh: word;
ds, __dsh: word;
edi: cardinal;
esi: cardinal;
ebp: cardinal;
esp: cardinal;
ebx: cardinal;
edx: cardinal;
ecx: cardinal;
eax: cardinal;
trapno: cardinal;
err: cardinal;
eip: cardinal;
cs, __csh: word;
eflags: cardinal;
esp_at_signal: cardinal;
ss, __ssh: word;
fpstate: pfpstate;
oldmask: cardinal;
cr2: cardinal;
end;
```

The above records contain information about the processor state and process state at the moment a signal is sent to your program.

The records below are used in catching signals.

```
TSigAction = procedure(Sig: Longint; SigContext: SigContextRec);cdecl;
SignalHandler = Procedure ( Sig : Integer);cdecl;

PSignalHandler = SignalHandler;
SignalRestorer = Procedure;cdecl;
PSignalrestorer = SignalRestorer;
SigActionRec = packed record
  Handler : record
    case byte of
      0: (Sh: SignalHandler);
      1: (Sa: TSigAction);
    end;
  Sa_Mask : SigSet;
  Sa_Flags : Longint;
  Sa_restorer : SignalRestorer; { Obsolete - Don't use }
end;
PSigActionRec = ^SigActionRec;
```

Stat is used to store information about a file. It is defined in the syscalls unit.

```
stat = record
  dev : word;
  pad1 : word;
  ino : longint;
  mode : word;
  nlink : word;
```

```
uid      : word;
gid      : word;
rdev     : word;
pad2     : word;
size     : longint;
blksize  : Longint;
blocks   : Longint;
atime    : Longint;
unused1  : longint;
mtime    : Longint;
unused2  : longint;
ctime    : Longint;
unused3  : longint;
unused4  : longint;
unused5  : longint;
end;
```

Statfs is used to store information about a filesystem. It is defined in the syscalls unit.

```
statfs = record
  fstype   : longint;
  bsize    : longint;
  blocks   : longint;
  bfree    : longint;
  bavail   : longint;
  files    : longint;
  ffree    : longint;
  fsid     : longint;
  namelen  : longint;
  spare    : array [0..6] of longint;
end
```

Dir and PDir are used in the [OpenDir \(213\)](#) and [ReadDir \(215\)](#) functions.

```
TDir = record
  fd       : integer;
  loc      : longint;
  size     : integer;
  buf      : pdirent;
  nextoff  : longint;
  dd_max   : integer;
  lock     : pointer;
end;
PDir = ^TDir;
```

Dirent, PDirent are used in the [ReadDir \(215\)](#) function to return files in a directory.

```
PDirent = ^Dirent;
Dirent = Record
  ino,
  off   : longint;
  reclen : word;
  name   : string[255]
end;
```

Termio and Termios are used with `ioctl()` calls for terminal handling.

```
Const  NCCS = 19;
       NCC = 8;
```

```
Type termio = record
  c_iflag,{ input mode flags }
  c_oflag,{ output mode flags }
  c_cflag,{ control mode flags }
  c_lflag : Word; { local mode flags }
  c_line : Word; { line discipline - careful, only High byte in use}
  c_cc : array [0..NCC-1] of char; { control characters }
end;
termios = record
  c_iflag,           { input mode flags }
  c_oflag,           { output mode flags }
  c_cflag,           { control mode flags }
  c_lflag : Cardinal; { local mode flags }
  c_line : char;      { line discipline }
  c_cc : array [0..NCCS-1] of char; { control characters }
end;
```

Utimbuf is used in the `Utime` (231) call to set access and modification time of a file.

```
utimbuf = record
  actime,modtime : Longint;
end;
```

For the `Select` (218) call, the following 4 types are needed:

```
FDSet = Array [0..31] of longint;
PFDSset = ^FDSet;
TimeVal = Record
  sec,usec : Longint;
end;
PTimeVal = ^TimeVal;
```

The `Uname` (231) function uses the `utsname` to return information about the current kernel :

```
utsname =record
  sysname,nodename,release,
  version,machine,domainname : Array[0..64] of char;
end;
```

Its elements are null-terminated C style strings, you cannot access them directly !

Variables

`Linuxerror` is the variable in which the procedures in the linux unit report errors.

```
LinuxError : Longint;
```

`StdErr` Is a `Text` variable, corresponding to Standard Error or diagnostic output. It is connected to file descriptor 2. It can be freely used, and will be closed on exit.

```
StdErr : Text;
```


Constants

Constants for setting/getting process priorities :

```
Prio_Process = 0;
Prio_PGrp    = 1;
Prio_User    = 2;
```

For testing access rights:

```
R_OK = 4;
W_OK = 2;
X_OK = 1;
F_OK = 0;
```

For signal handling functions :

```
SA_NOCLDSTOP = 1;
SA_SHIRQ     = $04000000;
SA_STACK     = $08000000;
SA_RESTART   = $10000000;
SA_INTERRUPT = $20000000;
SA_NOMASK    = $40000000;
SA_ONESHOT   = $80000000;
```

```
SIG_BLOCK   = 0;
SIG_UNBLOCK = 1;
SIG_SETMASK = 2;
SIG_DFL     = 0 ;
SIG_IGN     = 1 ;
SIG_ERR     = -1;
```

```
SIGHUP = 1;
SIGINT  = 2;
SIGQUIT = 3;
SIGILL  = 4;
SIGTRAP = 5;
SIGABRT = 6;
SIGIOT  = 6;
SIGBUS  = 7;
SIGFPE  = 8;
SIGKILL = 9;
SIGUSR1 = 10;
SIGSEGV = 11;
SIGUSR2 = 12;
SIGPIPE = 13;
SIGALRM = 14;
SIGTERM = 15;
SIGSTKFLT = 16;
SIGCHLD = 17;
SIGCONT = 18;
SIGSTOP = 19;
SIGTSTP = 20;
SIGTTIN = 21;
SIGTTOU = 22;
```

```
SIGURG = 23;
SIGXCPU = 24;
SIGXFSZ = 25;
SIGVTALRM = 26;
SIGPROF = 27;
SIGWINCH = 28;
SIGIO = 29;
SIGPOLL = SIGIO;
SIGPWR = 30;
SIGUNUSED = 31;
```

For file control mechanism :

```
F_GetFd = 1;
F_SetFd = 2;
F_GetFl = 3;
F_SetFl = 4;
F_GetLk = 5;
F_SetLk = 6;
F_SetLkW = 7;
F_GetOwn = 8;
F_SetOwn = 9;
```

For Terminal handling :

```
TCGETS = $5401 ;
TCSETS = $5402 ;
TCSETSW = $5403 ;
TCSETSF = $5404 ;
TCGETA = $5405 ;
TCSETA = $5406 ;
TCSETAW = $5407 ;
TCSETAF = $5408 ;
TCSBRK = $5409 ;
TCXONC = $540A ;
TCFLSH = $540B ;
TIOCEXCL = $540C ;
TIOCNXCL = $540D ;
TIOCSCTTY = $540E ;
TIOCGPGRP = $540F ;
TIOCSPPGRP = $5410 ;
TIOCOUTQ = $5411 ;
TIOCSTI = $5412 ;
TIOCGWINSZ = $5413 ;
TIOCSWINSZ = $5414 ;
TIOCMGET = $5415 ;
TIOCMBIS = $5416 ;
TIOCMBIC = $5417 ;
TIOCMSET = $5418 ;
TIOCGSOFTCAR = $5419 ;
TIOCSSOFTCAR = $541A ;
FIONREAD = $541B ;
TIOCINQ = FIONREAD;
TIOCLINUX = $541C ;
```

```
TIOCCONS = $541D ;
TIOCGSERIAL = $541E ;
TIOCSSERIAL = $541F ;
TIOCPKT = $5420 ;
FIONBIO = $5421 ;
TIOCNOTTY = $5422 ;
TIOCSETD = $5423 ;
TIOCGETD = $5424 ;
TCSBRKP = $5425 ;
TIOCTTYGSTRUCT = $5426 ;
FIONCLEX = $5450 ;
FIOCLEX = $5451 ;
FIOASYNC = $5452 ;
TIOCSERCONFIG = $5453 ;
TIOCSERGWILD = $5454 ;
TIOCSERSWILD = $5455 ;
TIOCGLCCKTRMIO = $5456 ;
TIOCSLCKTRMIO = $5457 ;
TIOCSERGSTRUCT = $5458 ;
TIOCSERGETLSR = $5459 ;
TIOCSERGETMULTI = $545A ;
TIOCSERSETMULTI = $545B ;
TIOCMWAIT = $545C ;
TIOCGICOUNT = $545D ;
TIOCPKT_DATA = 0;
TIOCPKT_FLUSHREAD = 1;
TIOCPKT_FLUSHWRITE = 2;
TIOCPKT_STOP = 4;
TIOCPKT_START = 8;
TIOCPKT_NOSTOP = 16;
TIOCPKT_DOSTOP = 32;
```

Other than that, all constants for setting the speed and control flags of a terminal line, as described in the `termios(2)` man page, are defined in the `linux` unit. It would take too much place to list them here. To check the `mode` field of a `stat` record, you can use the following constants :

```
{ Constants to check stat.mode }
STAT_IFMT = $f000; {00170000}
STAT_IFSOCK = $c000; {0140000}
STAT_IFLNK = $a000; {0120000}
STAT_IFREG = $8000; {0100000}
STAT_IFBLK = $6000; {0060000}
STAT_IFDIR = $4000; {0040000}
STAT_IFCHR = $2000; {0020000}
STAT_IFIFO = $1000; {0010000}
STAT_ISUID = $0800; {0004000}
STAT_ISGID = $0400; {0002000}
STAT_ISVTX = $0200; {0001000}
{ Constants to check permissions }
STAT_IRWX0 = $7;
STAT_IROTH = $4;
STAT_IWOTH = $2;
STAT_IXOTH = $1;
STAT_IRWXG = STAT_IRWX0 shl 3;
```

```
STAT_IRGRP = STAT_IROTH shl 3;
STAT_IWGRP = STAT_IWOTH shl 3;
STAT_IXGRP = STAT_IXOTH shl 3;
STAT_IRWXU = STAT_IRWXO shl 6;
STAT_IRUSR = STAT_IROTH shl 6;
STAT_IWUSR = STAT_IWOTH shl 6;
STAT_IXUSR = STAT_IXOTH shl 6;
```

You can test the type of a filesystem returned by a `FStat` ([191](#)) call with the following constants:

```
fs_old_ext2 = $ef51;
fs_ext2     = $ef53;
fs_ext      = $137d;
fs_iso      = $9660;
fs_minix    = $137f;
fs_minix_30 = $138f;
fs_minix_V2 = $2468;
fs_msdos    = $4d44;
fs_nfs      = $6969;
fs_proc     = $9fa0;
fs_xia      = $012FD16D;
```

the `FLock` ([189](#)) call uses the following mode constants :

```
LOCK_SH = 1;
LOCK_EX = 2;
LOCK_UN = 8;
LOCK_NB = 4;
```

The `MMap` ([210](#)) function uses the following constants to specify access to mapped memory:

```
PROT_READ  = $1; { page can be read }
PROT_WRITE = $2; { page can be written }
PROT_EXEC  = $4; { page can be executed }
PROT_NONE  = $0; { page can not be accessed }
```

and the following constants to specify the type of mapping.

```
MAP_SHARED = $1; { Share changes }
MAP_PRIVATE = $2; { Changes are private }
MAP_TYPE    = $f; { Mask for type of mapping }
MAP_FIXED   = $10; { Interpret addr exactly }
MAP_ANONYMOUS = $20; { don't use a file }
```

11.2 Function list by category

What follows is a listing of the available functions, grouped by category. For each function there is a reference to the page where you can find the function.

File Input/Output routines

Functions for handling file input/output.

Name	Description	Page
Dup	Duplicate a file handle	177
Dup2	Copy one file handle to another	178
Fcntl	General file control	193
fdClose	Close file descriptor	185
fdFlush	Flush file descriptor	185
fdOpen	Open new file descriptor	186
fdRead	Read from file descriptor	187
fdSeek	Position in file	188
fdTruncate	Truncate file	188
fdWrite	Write to file descriptor	188
GetFS	Get file descriptor of pascal file	198
Select	Wait for input from file descriptor	218
SelectText	Wait for input from pascal file	219

General File handling routines

Functions for handling files on disk.

Name	Description	Page
Access	Check access rights on file	167
BaseName	Return name part of file	171
Chown	Change owner of file	172
Chmod	Change access rights on file	173
DirName	Return directory part of file	177
FSplit	Split filename in parts	190
FExpand	Return full-grown filename	189
FLock	Set lock on a file	189
FNMatch	Match filename to searchpattern	189
FSearch	Search for a file in a path	190
FSStat	Return filesystem information	191
FStat	Return file information	192
FRename	Rename file	194
LStat	Return information on a link	207
Link	Create a link	208
ReadLink	Read contents of a symbolic link	215
SymLink	Create a symbolic link	225
Umask	Set the file creation mask	230
UnLink	Remove a file	231
Utime	Change file timestamps	231

Pipes, FIFOs and streams

Functions for creating and managing pipes.

Name	Description	Page
AssignPipe	Create a pipe	168
AssignStream	Create pipes to program's input and output	169
MkFifo	Make a fifo	210
PClose	Close a pipe	214
POpen	Open a pipe for to program's input or output	214

Directory handling routines

Functions for reading and searching directories.

Name	Description	Page
CloseDir	Close directory handle	176
Glob	Return files matching a search expression	202
GlobFree	Free result of Glob	203
OpenDir	Open directory for reading	213
ReadDir	Read directory entry	215
SeekDir	Seek directory	218
TellDir	Seek directory	230

Process handling

Functions for managing processes and programs.

Name	Description	Page
Clone	Create a thread	174
Execl	Execute process with command-line list	179
Execle	Execute process with command-line list and environment	180
Execlp	Search in path and execute process with command list	181
Execv	Execute process	182
Execve	Execute process with environment	182
Execvp	Search in path and execute process	183
Fork	Spawn child process	194
GetEGid	Get effective group id	196
GetEnv	Get environment variable	197
GetEUid	Get effective user id	197
GetGid	Get group id	198
GetPid	Get process id	199
GetPPid	Get parent process id	200

GetPriority	Get process priority	200
GetUid	Get user id	202
Nice	Change priority of process	212
SetPriority	Change priority of process	220
Shell	Execute shell command	220
WaitPid	Wait for child process to terminate	232

Signals

Functions for managing and responding to signals.

Name	Description	Page
Alarm	Send alarm signal to self	168
Kill	Send arbitrary signal to process	206
pause	Wait for signal to arrive	214
SigAction	Set signal action	221
Signal	Set signal action	223
SigPending	See if signals are waiting	222
SigProcMask	Set signal processing mask	222
SigRaise	Send signal to self	222
SigSuspend	Sets signal mask and waits for signal	223

System information

Functions for retrieving system information such as date and time.

Name	Description	Page
GetDate	Return system date	195
GetDateTime	Return system date and time	195
GetDomainName	Return system domain name	196
GetEpochTime	Return epoch time	197
GetHostName	Return system host name	199
GetLocalTimezone	Return system timezone	199
GetTime	Return system time	201
GetTimeOfDay	Return system time	201
GetTimezoneFile	Return name of timezone file	202
ReadTimezoneFile	Read timezone file contents	218
SysInfo	Return general system information	226
Uname	Return system information	231

Terminal functions

Functions for controlling the terminal to which the process is connected.

Name	Description	Page
CFMakeRaw	Set terminal to raw mode	171
CFSetISpeed	Set terminal reading speed	172
CFSetOSpeed	Set terminal writing speed	172
IOCtl	General IO control call	203
IsATTY	See if filedescriptor is a terminal	204
TCDrain	Wait till all output was written	227
TCFlow	Suspend transmission or receipt of data	227
TCFlush	Discard data written to terminal	228
TCGetAttr	Get terminal attributes	228
TCGetPGrp	Return PID of foreground process	229
TCSendBreak	Send data for specific time	229
TCSetAttr	Set terminal attributes	229
TCSetPGrp	Set foreground process	230
TTYName	Name of tty file	230

Port input/output

Functions for reading and writing to the hardware ports.

Name	Description	Page
IOperm	Set permissions for port access	204
ReadPort	Read data from port	217
ReadPortB	Read 1 byte from port	217
ReadPortL	Read 4 bytes from port	217
ReadPortW	Read 2 bytes from port	218
WritePort	Write data to port	233
WritePortB	Write 1 byte to port	233
WritePortL	Write 4 bytes to port	233
WritePortW	Write 2 bytes to port	234

Utility routines

Auxiliary functions that are useful in connection with the other functions.

Name	Description	Page
CreateShellArgV	Create an array of pchars from string	176
EpochToLocal	Convert epoch time to local time	179
FD_Clr	Clear item of select filedescriptors	184

FD_IsSet	Check item of select filedescriptors	185
FD_Set	Set item of select filedescriptors	185
FD_ZERO	Clear all items in select filedescriptors	184
LocalToEpoch	Convert local time to epoch time	209
MMap	Map a file into memory	210
MUnMap	Unmap previously mapped memory file	211
Octal	Convert octal to digital	212
S_ISBLK	Check file mode for block device	204
S_ISCHR	Check file mode for character device	205
S_ISDIR	Check file mode for directory	205
S_ISFIFO	Check file mode for FIFO	205
S_ISLNK	Check file mode for symbolic link	205
S_ISREG	Check file mode for regular file	206
S_ISSOCK	Check file mode for socket	206
StringToPPchar	Create an array of pchars from string	224

11.3 Functions and procedures

Access

Declaration: Function Access (Path : Pathstr; Mode : integer) : Boolean;

Description: Tests user's access rights on the specified file. Mode is a mask existing of one or more of

R_OKUser has read rights.

W_OKUser has write rights.

X_OKUser has execute rights.

F_OKUser has search rights in the directory where the file is.

The test is done with the real user ID, instead of the effective user ID. If access is denied, or an error occurred, false is returned.

Errors: `LinuxError` is used to report errors:

sys_eaccessThe requested access is denied, either to the file or one of the directories in its path.

sys_einvalMode was incorrect.

sys_enoentA directory component in `Path` doesn't exist or is a dangling symbolic link.

sys_enotdirA directory component in `Path` is not a directory.

sys_enomemInsufficient kernel memory.

sys_eloop`Path` has a circular symbolic link.

See also: `Chown` (172), `Chmod` (173), `Access` (2)

Listing: `linuxex/ex26.pp`

```
Program Example26;

{ Program to demonstrate the Access function . }

Uses linux ;

begin
  if Access ( '/ etc / passwd' ,W_OK) then
    begin
      WriteLn ( ' Better _check_your_system .' );
      WriteLn ( ' I _can_write _to _the _/etc/passwd_file _!' );
    end;
end.
```

Alarm

Declaration: Function Alarm(Sec : longint) : Longint;

Description: Alarm schedules an alarm signal to be delivered to your process in Sec seconds. When Sec seconds have elapsed, Linux will send a SIGALRM signal to the current process. If Sec is zero, then no new alarm will be set. Whatever the value of Sec, any previous alarm is cancelled.

The function returns the number of seconds till the previously scheduled alarm was due to be delivered, or zero if there was none.

Errors: None

Listing: linuxex/ex59.pp

```
Program Example59;

{ Program to demonstrate the Alarm function . }

Uses linux ;

Procedure AlarmHandler(Sig : longint); cdecl;

begin
  WriteLn ( ' Got_to_alarm_handler ' );
end;

begin
  WriteLn ( ' Setting _alarm_handler ' );
  Signal(SIGALRM, @AlarmHandler);
  WriteLn ( ' Scheduling _Alarm_in _10_seconds ' );
  Alarm(10);
  WriteLn ( ' Pausing ' );
  Pause;
  WriteLn ( ' Pause_returned ' );
end.
```

AssignPipe

Declaration: Function AssignPipe(var pipe_in,pipe_out:longint):boolean; Function AssignPipe(var pipe_in,pipe_out:text):boolean; Function AssignPipe(var pipe_in,pipe_out:file):boolean;

Description: AssignPipe creates a pipe, i.e. two file objects, one for input, one for output. What is written to Pipe_out, can be read from Pipe_in.

This call is overloaded. The in and out pipe can take three forms: an typed or untyped file, a text file or a file descriptor.

If a text file is passed then reading and writing from/to the pipe can be done through the usual Readln(Pipe_in, ...) and Writeln (Pipe_out, ...) procedures.

The function returns True if everything went successfully, False otherwise.

Errors: In case the function fails and returns False, LinuxError is used to report errors:

sys_enfileToo many file descriptors for this process.

sys_enfileThe system file table is full.

See also: POpen (214), MkFifo (210), pipe (2)

Listing: linuxex/ex36.pp

Program Example36;

{ Program to demonstrate the AssignPipe function . }

Uses linux ;

Var pipi , pipo : Text;
s : **String**;

begin

```
Writeln ( ' Assigning _Pipes .' );
If Not assignpipe ( pipi , pipo ) then
  Writeln ( ' Error _assigning _pipes _!' , LinuxError );
Writeln ( ' Writing _to _pipe _and _flushing .' );
Writeln ( pipo , ' This _is _a _textstring ' ); close ( pipo );
Writeln ( ' Reading _from _pipe .' );
While not eof ( pipi ) do
  begin
    Readln ( pipi , s );
    Writeln ( ' Read _from _pipe _:_ ' , s );
  end;
close ( pipi );
writeln ( ' Closed _pipes .' );
writeln
```

end.

AssignStream

Declaration: Function AssignStream(Var StreamIn,Streamout:text; Const Prog:String)
: longint; Function AssignStream(var StreamIn, StreamOut, StreamErr:
Text; const prog: String): LongInt;

Description: AssignStream creates a 2 or 3 pipes, i.e. two (or three) file objects, one for input, one for output,(and one for standard error) the other ends of these pipes are connected to standard input and output (and standard error) of Prog. Prog is the name of a program (including path) with options, which will be executed.

What is written to `StreamOut`, will go to the standard input of `Prog`. Whatever is written by `Prog` to its standard output can be read from `StreamIn`. Whatever is written by `Prog` to its standard error read from `StreamErr`, if present.

Reading and writing happens through the usual `ReadLn(StreamIn, ...)` and `WriteLn (StreamOut, ...)` procedures.

Remark: You should *not* use `Reset` or `Rewrite` on a file opened with `POpen`. This will close the file before re-opening it again, thereby closing the connection with the program.

The function returns the process ID of the spawned process, or -1 in case of error.

Errors: In case of error (return value -1) `LinuxError` is used to report errors:

`sys_emfile` Too many file descriptors for this process.

`sys_enfile` The system file table is full.

Other errors include the ones by the `fork` and `exec` programs

See also: `AssignPipe` (168), `POpen` (214), `pipe` (2)

Listing: linuxex/ex38.pp

Program Example38;

{ Program to demonstrate the AssignStream function . }

Uses linux ;

Var Si, So : Text;
S : **String**;
i : longint;

begin

```
  if not ( paramstr(1)='-son' ) then
    begin
      WriteLn ( ' Calling _son' );
      Assignstream ( Si, So, './ ex38_-son' );
      if linuxerror <> 0 then
        begin
          writeln ( ' AssignStream _failed _!' );
          halt (1);
        end;
      WriteLn ( ' Speaking _to _son' );
      For i:=1 to 10 do
        begin
          writeln ( so, ' Hello _son _!' );
          if ioreult <> 0 then writeln ( ' Can' ' t _speak _to _son ... ' );
        end;
      For i:=1 to 3 do writeln ( so, ' Hello _chap _!' );
      close ( so );
      while not eof(si) do
        begin
          readln ( si, s );
          writeln ( ' Father : _Son _said _:_', S );
        end;
      WriteLn ( ' Stopped _conversation ' );
      Close ( Si );
      WriteLn ( ' Put _down _phone ' );
    end
```

```
Else
  begin
    Writeln ( ' This_is_the_son_ ');
    While not eof ( input ) do
      begin
        readln ( s);
        if pos ( ' Hello_son_!', S)<>0 then
          Writeln ( ' Hello_Dad_!')
        else
          writeln ( ' Who_are_you_? ');
        end;
      close ( output );
    end
  end.
```

BaseName

Declaration: Function BaseName (Const Path;Const Suf : Pathstr) : Pathstr;

Description: Returns the filename part of Path, stripping off Suf if it exists. The filename part is the whole name if Path contains no slash, or the part of Path after the last slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: DirName ([177](#)), FExpand ([189](#)), Basename ([1](#))

Listing: linuxex/ex48.pp

Program Example48;

{ Program to demonstrate the BaseName function . }

Uses linux ;

Var S : **String** ;

begin

S:=FExpand(**Paramstr**(0));

Writeln (' This_program_is_called _:_', Basename(S, ''));

end.

CFMakeRaw

Declaration: Procedure CFMakeRaw (var Tios:TermIOS);

Description: CFMakeRaw Sets the flags in the Termios structure Tios to a state so that the terminal will function in Raw Mode.

Errors: None.

See also: CFSetOSpeed ([172](#)), CFSetISpeed ([172](#)), termios ([2](#))

For an example, see TCGetAttr ([228](#)).

CFSetISpeed

Declaration: Procedure CFSetISpeed (var Tios:TermIOS;Speed:Longint);

Description: CFSetISpeed Sets the input baudrate in the TermIOS structure Tios to Speed.

Errors: None.

See also: CFSetOSpeed ([172](#)), CFMakeRaw ([171](#)), termios (2)

CFSetOSpeed

Declaration: Procedure CFSetOSpeed (var Tios:TermIOS;Speed:Longint);

Description: CFSetOSpeed Sets the output baudrate in the Termios structure Tios to Speed.

Errors: None.

See also: CFSetISpeed ([172](#)), CFMakeRaw ([171](#)), termios (2)

Chown

Declaration: Function Chown (Path : Pathstr;NewUid,NewGid : Longint) : Boolean;

Description: Chown sets the User ID and Group ID of the file in Path to NewUid, NewGid. The function returns True if the call was succesfull, False if the call failed.

Errors: Errors are returned in LinuxError.

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in Path has no search (=execute) permission.

sys_enoentA directory entry in Path does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdirA directory entry in OldPath or NewPath is nor a directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe file is on a read-only filesystem.

sys_eloopPath has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: Chmod ([173](#)), Access ([167](#)), Chown (1 2)

Listing: linuxex/ex24.pp

Program Example24;

{ Program to demonstrate the Chown function . }

Uses linux ;

Var UID,GID : Longint;
F : Text;

begin

Writeln (' This_will_only_work_if_you_are_root . ');

```
Write ( ' Enter_a_UID_:_' ); readln (UID);
Write ( ' Enter_a_GID_:_' ); readln (GID);
Assign ( f, ' test . txt ' );
Rewrite ( f );
Writeln ( f, ' The_owner_of_this_file_should_become_:_' );
Writeln ( f, ' UID_:_', UID );
Writeln ( f, ' GID_:_', GID );
Close ( F );
if not Chown ( ' test . txt ', UID, GID) then
  if LinuxError=Sys_EPERM then
    Writeln ( ' You_are_not_root_' )
  else
    Writeln ( ' Chmod_failed_with_exit_code_:_', LinuxError )
else
  Writeln ( ' Changed_owner_successfully_' );
end.
```

Chmod

Declaration: Function Chmod (Path : Pathstr;NewMode : Longint) : Boolean;

Description: Chmod Sets the Mode bits of the file in Path to NewMode. Newmode can be specified by 'or'-ing the following:

- S_ISUID**Set user ID on execution.
- S_ISGID**Set Group ID on execution.
- S_ISVTX**Set sticky bit.
- S_IRUSR**Read by owner.
- S_IWUSR**Write by owner.
- S_IXUSR**Execute by owner.
- S_IRGRP**Read by group.
- S_IWGRP**Write by group.
- S_IXGRP**Execute by group.
- S_IROTH**Read by others.
- S_IWOTH**Write by others.
- S_IXOTH**Execute by others.
- S_IRWXO**Read, write, execute by others.
- S_IRWXG**Read, write, execute by groups.
- S_IRWXU**Read, write, execute by user.

Errors: Errors are returned in LinuxError.

- sys_eperm**The effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.
- sys_eaccess**One of the directories in Path has no search (=execute) permission.
- sys_enoent**A directory entry in Path does not exist or is a symbolic link pointing to a non-existent directory.
- sys_enotdir**A directory entry in OldPath or NewPath is nor a directory.
- sys_enomem**Insufficient kernel memory.
- sys_erofs**The file is on a read-only filesystem.

`sys_loopPath` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `Chown` ([172](#)), `Access` ([167](#)), `Chmod` (`() 2`), `Octal` ([212](#))

Listing: linuxex/ex23.pp

Program Example23;

{ Program to demonstrate the Chmod function . }

Uses linux ;

Var F : Text;

begin

```
  { Create a file }
  Assign ( f, 'testex21' );
  Rewrite ( F );
  Writeln ( f, '#!/ bin / sh' );
  Writeln ( f, 'echo _Some_text_for _this _file ' );
  Close ( F );
  { Octal() makes the correct number from a
    number that LOOKS octal }
  Chmod ( 'testex21', octal (777));
  { File is now executable }
  execl ( './testex21' );
```

end.

Clone

Declaration: `TCloneFunc=function(args:pointer):longint;cdecl; Clone(func:TCloneFunc;sp:pointer;flags`

Description: `Clone` creates a child process which is a copy of the parent process, just like `Fork` ([194](#)) does. In difference with `Fork`, however, the child process shares some parts of it's execution context with its parent, so it is suitable for the implementation of threads: many instances of a program that share the same memory.

When the child process is created, it starts executing the function `Func`, and passes it `Args`. The return value of `Func` is either the explicit return value of the function, or the exit code of the child process.

The `sp` pointer points to the memory reserved as stack space for the child process. This address should be the top of the memory block to be used as stack.

The `Flags` determine the behaviour of the `Clone` call. The low byte of the `Flags` contains the number of the signal that will be sent to the parent when the child dies. This may be bitwise OR'ed with the following constants:

CLONE_VMParent and child share the same memory space, including memory (un)mapped with subsequent `mmap` calls.

CLONE_FSParent and child have the same view of the filesystem; the `chroot`, `chdir` and `umask` calls affect both processes.

CLONE_FILESthe file descriptor table of parent and child is shared.

CLONE_SIGHANDthe parent and child share the same table of signal handlers. The signal masks are different, though.

CLONE_PIDParent and child have the same process ID.

Clone returns the process ID in the parent process, and -1 if an error occurred.

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagainToo many processes are running.

sys_enomemNot enough memory to create child process.

See also: Fork ([194](#)), c l one (2)

Listing: linuxex/ex71.pp

```
program TestC{ lone };

uses
  Linux , Errors , crt ;

const
  Ready : Boolean = false ;
  aChar : Char    = 'a' ;

function CloneProc( Arg: Pointer ): LongInt; Cdecl;
begin
  WriteLn( ' Hello _from _the _clone _' , PChar( Arg ) );
  repeat
    Write( aChar );
    Select( 0,0,0,0,600 );
  until Ready;
  WriteLn( ' Clone _finished .' );
  CloneProc := 1;
end;

var
  PID : LongInt;

procedure MainProc;
begin
  WriteLn( ' cloned _process _PID:_' , PID );
  WriteLn( ' Press _<ESC> _to _kill _..._' );
  repeat
    Write( '.' );
    Select( 0,0,0,0,300 );
    if KeyPressed then
      case ReadKey of
        #27: Ready := true ;
        'a': aChar := 'A' ;
        'A': aChar := 'a' ;
        'b': aChar := 'b' ;
        'B': aChar := 'B' ;
      end;
    until Ready;
  WriteLn( ' Ready .' );
end;

const
  StackSize = 16384;
  theFlags = CLONE_VM+CLONE_FS+CLONE_FILES+CLONE_SIGHAND;
```

```

aMsg      : PChar = 'Oops_!';

var
  theStack : Pointer;
  ExitStat : LongInt;

begin
  GetMem(theStack, StackSize);
  PID := Clone(@CloneProc,
               Pointer(LongInt(theStack)+StackSize),
               theFlags,
               aMsg);
  if PID < 0 then
    WriteLn('Error _:_', LinuxError, '_when_cloning.')
  else
    begin
      MainProc;
      case WaitPID(0, @ExitStat, Wait_Untraced or wait_clone) of
        -1: WriteLn('error:', LinuxError, ':_', StrError(LinuxError));
        0: WriteLn('error:', LinuxError, ':_', StrError(LinuxError));
      else
        WriteLn('Clone_exited_with:_', ExitStat shr 8);
      end;
    end;
  FreeMem(theStack, StackSize);
end.

```

CloseDir

Declaration: Function CloseDir (p:pdirent) : integer;

Description: CloseDir closes the directory pointed to by p. It returns zero if the directory was closed successfully, -1 otherwise.

Errors: Errors are returned in LinuxError.

See also: OpenDir (213), ReadDir (215), SeekDir (218), TellDir (230), c_lodedir (3)

For an example, see OpenDir (213).

CreateShellArgV

Declaration: function CreateShellArgV(const prog:string):ppchar; function CreateShellArgV(const prog:Ansistring):ppchar;

Description: CreateShellArgV creates an array of 3 PChar pointers that can be used as arguments to ExecVE the first elements in the array will contain /bin/sh, the second will contain -c, and the third will contain prog.

The function returns a pointer to this array, of type PPChar.

Errors: None.

See also: Shell (220)

Listing: linuxex/ex61.pp

```
Program ex61;

{ Example program to demonstrate the CreateShellArgV function }

uses linux;

Var
  S: String;
  PP : PPchar;
  I : longint;

begin
  S:= 'script_a_b_c_d_e_fghijk';
  PP:= CreateShellArgV (S);
  I:=0;
  If PP<>Nil then
    While PP[I]<>Nil do
      begin
        Writeln ( 'Got_',PP[I], '' );
        Inc (I);
      end;
    end;
end.
```

DirName

Declaration: Function DirName (Const Path : Pathstr) : Pathstr;

Description: Returns the directory part of Path. The directory is the part of Path before the last slash, or empty if there is no slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: BaseName ([171](#)), FExpand ([189](#)), Dirname (1)

Listing: linuxex/ex47.pp

```
Program Example47;

{ Program to demonstrate the DirName function. }

Uses linux;

Var S : String;

begin
  S:= FExpand (Paramstr (0));
  Writeln ( ' This_program_is_in_directory_', Dirname(S));
end.
```

Dup

Declaration: Function Dup(oldfile:longint;var newfile:longint):Boolean; Function Dup(var oldfile,newfile:text):Boolean; Function Dup(var oldfile,newfile:file):Boolean;

Description: Makes `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in case it is a Text file or untyped file. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup (2)` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns `False` in case of an error, `True` if successful.

Errors: In case of errors, `Linuxerror` is used to report errors.

`sys_ebadfOldFile` hasn't been assigned.

`sys_emfile`Maximum number of open files for the process is reached.

See also: `Dup2` ([178](#)), `Dup` (2)

Listing: linuxex/ex31.pp

```
program Example31;

{ Program to demonstrate the Dup function . }

uses linux ;

var f : text ;

begin
  if not dup ( output , f ) then
    Writeln ( ' Dup_Failed _!' );
  writeln ( ' This_is_written_to_stdout . ' );
  writeln ( f , ' This_is_written_to_the_dup_file ,_and_flushed ' ); flush ( f );
  writeln
end.
```

Dup2

Declaration: `Function Dup2(oldfile,newfile:longint):Boolean;` `Function Dup2(var oldfile,newfile:text):Boolean;` `Function Dup2(var oldfile,newfile:file):Boolean;`

Description: Makes `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in the case of text or untyped files.

`NewFile` can be an assigned file. If `newfile` was open, it is closed first. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup2 (2)` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns `True` if succesful, false otherwise.

Errors: In case of error, `Linuxerror` is used to report errors.

`sys_ebadfOldFile` hasn't been assigned.

`sys_emfile`Maximum number of open files for the process is reached.

See also: `Dup` ([177](#)), `Dup2` (2)

Listing: linuxex/ex32.pp

```
program Example31;

{ Program to demonstrate the Dup function . }

uses linux ;

var f : text;
    i : longint;

begin
  Assign ( f, 'text.txt' );
  Rewrite ( F);
  For i:=1 to 10 do writeln ( F, ' Line _:', i );
  if not dup2 ( output, f ) then
    Writeln ( ' Dup2_Failed _!' );
  writeln ( ' This_is _written _to _stdout .' );
  writeln ( f, ' This_is _written _to _the _dup _file , _and _flushed ' );
  flush(f);
  writeln ;
  { Remove file . Comment this if you want to check flushing .}
  Unlink ( 'text.txt' );
end.
```

EpochToLocal

Declaration: Procedure EpochToLocal (Epoch : Longint; var Year, Month, Day, Hour, Minute, Second : Word);

Description: Converts the epoch time (=Number of seconds since 00:00:00 , January 1, 1970, corrected for your time zone) to local date and time.

This function takes into account the timzeone settings of your system.

Errors: None

See also: GetEpochTime ([197](#)), LocalToEpoch ([209](#)), GetTime ([201](#)), GetDate ([195](#))

Listing: linuxex/ex3.pp

```
Program Example3;

{ Program to demonstrate the EpochToLocal function . }

Uses linux ;

Var Year, month, day, hour, minute, seconds : Word;

begin
  EpochToLocal ( GetEpochTime, Year, month, day, hour, minute, seconds );
  Writeln ( ' Current _date _:', Day:2, '/' , Month:2, '/' , Year:4 );
  Writeln ( ' Current _time _:', Hour:2, ':' , minute:2, ':' , seconds:2 );
end.
```

Execl

Declaration: Procedure Execl (Path : pathstr);

Description: Replaces the currently running program with the program, specified in `path`. Path is split into a command and it's options. The executable in `path` is NOT searched in the path. The current environment is passed to the program. On success, `execl` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `Execve` ([182](#)), `Execv` ([182](#)), `Execvp` ([183](#)), `Execl` ([180](#)), `Execlp` ([181](#)), `Fork` ([194](#)), `execvp` ([3](#))

Listing: linuxex/ex10.pp

Program Example10;

{ Program to demonstrate the Execl function . }

Uses linux , strings ;

begin

{ Execute 'ls -l' , with current environment . }

{ 'ls' is NOT looked for in PATH environment variable . }

`Execl ( '/ bin / ls_-l ' );`

end.

Execl

Declaration: Procedure `Execl` (`Path` : `pathstr`, `Ep` : `ppchar`);

Description: Replaces the currently running program with the program, specified in `path`. Path is split into a command and it's options. The executable in `path` is searched in the path, if it isn't an absolute filename. The environment in `ep` is passed to the program. On success, `execl` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: [Execve \(182\)](#), [Execv \(182\)](#), [Execvp \(183\)](#), [Execl \(179\)](#), [Execlp \(181\)](#), [Fork \(194\)](#), [execvp \(3\)](#)

Listing: linuxex/ex11.pp

```
Program Example11;

{ Program to demonstrate the Execl function . }

Uses linux , strings ;

begin
  { Execute 'ls -l', with current environment . }
  { 'ls' is NOT looked for in PATH environment variable .}
  { envp is defined in the system unit .}
  Execl ( '/ bin / ls _l ' , envp);
end.
```

Execlp

Declaration: Procedure `Execlp (Path : pathstr);`

Description: Replaces the currently running program with the program, specified in `path`. `Path` is split into a command and it's options. The executable in `path` is searched in the path, if it isn't an absolute filename. The current environment is passed to the program. On success, `execlp` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: [Execve \(182\)](#), [Execv \(182\)](#), [Execvp \(183\)](#), [Execl \(180\)](#), [Execl \(179\)](#), [Fork \(194\)](#), [execvp \(3\)](#)

Listing: linuxex/ex12.pp

```
Program Example12;

{ Program to demonstrate the Execlp function . }

Uses linux , strings ;

begin
  { Execute 'ls -l', with current environment . }
  { 'ls' is looked for in PATH environment variable .}
  { envp is defined in the system unit .}
  Execlp ( ' ls _l ' , envp);
end.
```

Execv

Declaration: Procedure Execv (Path : pathstr; args : ppchar);

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execv` does not return.

Errors: Errors are reported in `LinuxError`:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `Execve` ([182](#)), `Execvp` ([183](#)), `Execl` ([180](#)), `Execl` ([179](#)), `Execlp` ([181](#)), `Fork` ([194](#)), `execv` (3)

Listing: linuxex/ex8.pp

Program Example8;

{ Program to demonstrate the Execv function . }

Uses linux , strings ;

Const Arg0 : PChar = '/ bin / ls ' ;
Arg1 : Pchar = ' - l ' ;

Var PP : PPchar ;

begin

GetMem (PP, 3 * SizeOf (Pchar)) ;

PP[0] := Arg0 ;

PP[1] := Arg1 ;

PP[3] := Nil ;

{ Execute '/ bin / ls - l ' , with current environment }

Execv ('/ bin / ls ' , pp) ;

end.

Execve

Declaration: Procedure Execve(Path:pchar;args:ppchar;ep:ppchar); Procedure Execve (Path : pathstr; args,ep : ppchar);

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `args`, and the environment in `ep`. They are pointers to an array of pointers to null-terminated strings. The last pointer in this array should be nil. On success, `execve` does not return.

Errors: Errors are reported in `LinuxError`:

eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.
sys_ epermThe file system is mounted *noexec*.
sys_ e2bigArgument list too big.
sys_ enoexecThe magic number in the file is incorrect.
sys_ enoentThe file does not exist.
sys_ enomemNot enough memory for kernel.
sys_ enotdirA component of the path is not a directory.
sys_ eloopThe path contains a circular reference (via symlinks).

See also: `Execve` ([182](#)), `Execv` ([182](#)), `Execvp` ([183](#)) `Execl` ([180](#)), `Execl` ([179](#)), `Execlp` ([181](#)), `Fork` ([194](#)), `execve` (2)

Listing: `linuxex/ex7.pp`

```
Program Example7;  
  
{ Program to demonstrate the Execve function . }  
  
Uses linux , strings ;  
  
Const Arg0 : PChar = '/ bin / ls ' ;  
        Arg1 : Pchar = '- l ' ;  
  
Var PP : PPchar ;  
  
begin  
  GetMem ( PP, 3* SizeOf( Pchar ));  
  PP[0]:= Arg0 ;  
  PP[1]:= Arg1 ;  
  PP[3]:= Nil ;  
  { Execute '/ bin / ls - l ' , with current environment }  
  { Env is defined in system.inc }  
  ExecVe ( '/ bin / ls ' , pp, envp);  
end.
```

Execvp

Declaration: Procedure `Execvp` (`Path` : `pathstr`; `args` : `ppchar`);

Description: Replaces the currently running program with the program, specified in `path`. The executable in `path` is searched in the path, if it isn't an absolute filename. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execvp` does not return.

Errors: Errors are reported in `LinuxError`:

sys_ eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.
sys_ epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: Execve ([182](#)), Execv ([182](#)), Execle ([180](#)), Execl ([179](#)), Execlp ([181](#)), Fork ([194](#)), execvp ([3](#))

Listing: linuxex/ex9.pp

Program Example9;

{ Program to demonstrate the Execvp function . }

Uses linux , strings ;

Const Arg0 : PChar = 'ls' ;
 Arg1 : Pchar = '-l' ;

Var PP : PPchar;

begin

GetMem (PP,3* **SizeOf** (Pchar));
 PP[0]:= Arg0;
 PP[1]:= Arg1;
 PP[3]:= Nil;
 { Execute 'ls -l', with current environment . }
 { 'ls' is looked for in PATH environment variable . }
 { Env is defined in the system unit . }
 Execvp ('ls' , pp, envp);

end.

FD_ZERO

Declaration: Procedure FD_ZERO (var fds:fdSet);

Description: FD_ZERO clears all the filedescriptors in the file descriptor set fds.

Errors: None.

See also: Select ([218](#)), SelectText ([219](#)), GetFS ([198](#)), FD_Clr ([184](#)), FD_Set ([185](#)), FD_IsSet ([185](#))

For an example, see Select ([218](#)).

FD_Clr

Declaration: Procedure FD_Clr (fd:longint;var fds:fdSet);

Description: FD_Clr clears file descriptor fd in filedescriptor set fds.

Errors: None.

See also: Select ([218](#)), SelectText ([219](#)), GetFS ([198](#)), FD_ZERO ([184](#)), FD_Set ([185](#)), FD_IsSet ([185](#))

For an example, see Select ([218](#)).

FD_IsSet

Declaration: `Function FD_IsSet (fd:longint;var fds:fdSet) : boolean;`

Description: `FD_Set` Checks whether file descriptor `fd` in filedescriptor set `fds` is set.

Errors: None.

See also: [Select \(218\)](#), [SelectText \(219\)](#), [GetFS \(198\)](#), [FD_ZERO \(184\)](#), [FD_Clr \(184\)](#), [FD_Set \(185\)](#)

For an example, see [Select \(218\)](#).

FD_Set

Declaration: `Procedure FD_Set (fd:longint;var fds:fdSet);`

Description: `FD_Set` sets file descriptor `fd` in filedescriptor set `fds`.

Errors: None.

See also: [Select \(218\)](#), [SelectText \(219\)](#), [GetFS \(198\)](#), [FD_ZERO \(184\)](#), [FD_Clr \(184\)](#), [FD_IsSet \(185\)](#)

For an example, see [Select \(218\)](#).

fdClose

Declaration: `Function fdClose (fd:longint) : boolean;`

Description: `fdClose` closes a file with file descriptor `Fd`. The function returns `True` if the file was closed successfully, `False` otherwise.

Errors: Errors are returned in `LinuxError`

See also: [fdOpen \(186\)](#), [fdRead \(187\)](#), [fdWrite \(188\)](#), [fdTruncate \(188\)](#), [fdFlush \(185\)](#), [seefdSeek](#)

For an example, see [fdOpen \(186\)](#).

fdFlush

Declaration: `Function fdFlush (fd:Longint) : boolean;`

Description: `fdflush` flushes the Linux kernel file buffer, so the file is actually written to disk. This is NOT the same as the internal buffer, maintained by Free Pascal. The function returns `True` if the call was successful, `false` if an error occurred.

Errors: Errors are returned in `LinuxError`.

See also: [fdOpen \(186\)](#), [fdClose \(185\)](#), [fdRead \(187\)](#), [fdWrite \(188\)](#), [fdTruncate \(188\)](#), [fdSeek \(188\)](#)

For an example, see [fdRead \(187\)](#).

fdOpen

Declaration: `Function fdOpen(PathName:String;flags:longint):longint; Function fdOpen(PathName:Pchar ;flags:longint):longint; Function fdOpen(PathName:String;flags,mode:longint):longint; Function fdOpen(PathName:Pchar ;flags,mode:longint):longint;`

Description: `fdOpen` opens a file in `PathName` with flags `flags` One of the following:

Open_RdOnlyFile is opened Read-only.

Open_WrOnlyFile is opened Write-only.

Open_RdWrFile is opened Read-Write.

The flags may be OR-ed with one of the following constants:

Open_AccmodeFile is opened

Open_CreatFile is created if it doesn't exist.

Open_ExclIf the file is opened with `Open_Creat` and it already exists, the call will fail.

Open_NoCttyIf the file is a terminal device, it will NOT become the process' controlling terminal.

Open_TruncIf the file exists, it will be truncated.

Open_Appendthe file is opened in append mode. *Before each write*, the file pointer is positioned at the end of the file.

Open_NonBlockThe file is opened in non-blocking mode. No operation on the file descriptor will cause the calling process to wait till.

Open_NDelayIdem as `Open_NonBlock`

Open_SyncThe file is opened for synchronous IO. Any write operation on the file will not return untill the data is physically written to disk.

Open_NoFollowif the file is a symbolic link, the open fails. (LINUX 2.1.126 and higher only)

Open_Directoryif the file is not a directory, the open fails. (LINUX 2.1.126 and higher only)

`PathName` can be of type `PChar` or `String`. The optional `mode` argument specifies the permissions to set when opening the file. This is modified by the `umask` setting. The real permissions are `Mode` and not `umask`. The return value of the function is the filedescriptor, or a negative value if there was an error.

Errors: Errors are returned in `LinuxError`

See also: `fdClose` (185), `fdRead` (187), `fdWrite` (188), `fdTruncate` (188), `fdFlush` (185), `fdSeek` (188)

Listing: `linuxex/ex19.pp`

Program `Example19`;

{ Program to demonstrate the fdOpen, fdwrite and fdClose functions. }

Uses `linux`;

Const `Line : String [80] = ' This_is_easy_writing _! ';`

Var `FD : Longint;`

begin

`FD:=fdOpen ( ' Test.dat ' , Open_WrOnly or Open_Creat);`

`if FD>0 then`

`begin`

```
    if length(Line)<>fdwrite (FD,Line[1],Length(Line)) then
      Writeln ( ' Error_when_writing_to_file _!');
      fdClose (FD);
    end;
end.
```

fdRead

Declaration: Function fdRead (fd:longint;var buf;size:longint) : longint;

Description: fdRead reads at most size bytes from the file descriptor fd, and stores them in buf. The function returns the number of bytes actually read, or -1 if an error occurred. No checking on the length of buf is done.

Errors: Errors are returned in LinuxError.

See also: fdOpen ([186](#)), fdClose ([185](#)), fdWrite ([188](#)),fdTruncate ([188](#)), fdFlush ([185](#)), fdSeek ([188](#))

Listing: linuxex/ex20.pp

Program Example20;

{ Program to demonstrate the fdRead and fdTruncate functions . }

Uses linux;

Const Data : **string** [10] = '12345687890';

Var FD : Longint;
I : longint;

begin

FD:=fdOpen(' test . dat' , open_wronly or open_creat , octal (666));

if fd>0 **then**

begin

{ Fill file with data }

for I:=1 **to** 10 **do**

if fdWrite (FD,Data[1],10)<>10 **then**

begin

writeln (' Error_when_writing _!');

halt (1);

end;

 fdClose (FD);

 FD:=fdOpen(' test . dat' , open_rdonly);

{ Read data again }

if FD>0 **then**

begin

For I:=1 **to** 5 **do**

if fdRead (FD,Data[1],10)<>10 **then**

begin

Writeln (' Error_when_Reading _!');

Halt (2);

end;

 fdClose (FD);

{ Truncating file at 60 bytes }

{ For truncating , file must be open or write }

 FD:=fdOpen(' test . dat' , open_wronly , octal (666));

```
    if FD>0 then
    begin
    if not fdTruncate (FD,60) then
        Writeln ( ' Error_when_truncating _!' );
        fdClose ( FD);
    end;
    end;
end;
end.
```

fdSeek

Declaration: Function `fdSeek (fd,Pos,SeekType:longint) : longint;`

Description: `fdSeek` sets the current fileposition of file `fd` to `Pos`, starting from `SeekType`, which can be one of the following:

Seek_Set `Pos` is the absolute position in the file.

Seek_Cur `Pos` is relative to the current position.

Seek_end `Pos` is relative to the end of the file.

The function returns the new fileposition, or -1 of an error occurred.

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` ([186](#)), `fdWrite` ([188](#)), `fdClose` ([185](#)), `fdRead` ([187](#)), `fdTruncate` ([188](#)), `fdFlush` ([185](#))

For an example, see `fdOpen` ([186](#)).

fdTruncate

Declaration: Function `fdTruncate (fd,size:longint) : boolean;`

Description: `fdTruncate` sets the length of a file in `fd` on `size` bytes, where `size` must be less than or equal to the current length of the file in `fd`. The function returns `True` if the call was successful, `false` if an error occurred.

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` ([186](#)), `fdClose` ([185](#)), `fdRead` ([187](#)), `fdWrite` ([188](#)), `fdFlush` ([185](#)), `fdSeek` ([188](#))

fdWrite

Declaration: Function `fdWrite (fd:longint;var buf;size:longint) : longint;`

Description: `fdWrite` writes at most `size` bytes from `buf` to file descriptor `fd`. The function returns the number of bytes actually written, or -1 if an error occurred.

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` ([186](#)), `fdClose` ([185](#)), `fdRead` ([187](#)), `fdTruncate` ([188](#)), `fdSeek` ([188](#)), `fdFlush` ([185](#))

FExpand

Declaration: `Function FExpand (Const Path: Pathstr) : pathstr;`

Description: Expands Path to a full path, starting from root, eliminating directory references such as . and .. from the result.

Errors: None

See also: [BaseName \(171\)](#), [DirName \(177\)](#)

Listing: linuxex/ex45.pp

```
Program Example45;

{ Program to demonstrate the FExpand function . }

Uses linux ;

begin
  Writeln ( ' This_program_is_in _:_', FExpand(Paramstr(0)));
end.
```

FLock

Declaration: `Function Flock (fd,mode : longint) : boolean;` `Function Flock (var T : text;mode : longint) : boolean;` `Function Flock (var F : File;mode : longint) : boolean;`

Description: FLock implements file locking. it sets or removes a lock on the file F. F can be of type Text or File, or it can be a LINUX filedescriptor (a longint) Mode can be one of the following constants :

LOCK_SH sets a shared lock.

LOCK_EX sets an exclusive lock.

LOCK_UN unlocks the file.

LOCK_NB This can be OR-ed together with the other. If this is done the application doesn't block when locking.

The function returns **True** if successful, **False** otherwise.

Errors: If an error occurs, it is reported in **LinuxError**.

See also: [Fcntl \(193\)](#), `flock (2)`

FNMatch

Declaration: `Function FNMatch(const Pattern,Name:string):Boolean;`

Description: FNMatch returns **True** if the filename in Name matches the wildcard pattern in Pattern, **False** otherwise.

Pattern can contain the wildcards * (match zero or more arbitrary characters) or ? (match a single character).

Errors: None.

See also: [FSearch \(190\)](#), [FExpand \(189\)](#)

Listing: linuxex/ex69.pp

Program Example69;

{ Program to demonstrate the FNMatch function . }

Uses linux ;

Procedure TestMatch (Pattern , Name : String);

begin

Write ('' , Name , ' ');

If FNMatch (Pattern , Name) **then**

Write (' matches ')

else

Write (' does_not_match ');

WriteLn (' ' , Pattern , ' ');

end;

begin

 TestMatch ('*' , ' FileName ');

 TestMatch ('. * ' , ' FileName ');

 TestMatch (' * a * ' , ' FileName ');

 TestMatch ('? ile * ' , ' FileName ');

 TestMatch ('? ' , ' FileName ');

 TestMatch ('. ? ' , ' FileName ');

 TestMatch ('? a * ' , ' FileName ');

 TestMatch (' ?? * me ? ' , ' FileName ');

end.

FSearch

Declaration: Function FSearch (Path : pathstr; DirList : string) : Pathstr;

Description: Searches in DirList, a colon separated list of directories, for a file named Path. It then returns a path to the found file.

Errors: An empty string if no such file was found.

See also: BaseName ([171](#)), DirName ([177](#)), FExpand ([189](#)), FNMatch ([189](#))

Listing: linuxex/ex46.pp

Program Example46;

{ Program to demonstrate the FSearch function . }

Uses linux , strings ;

begin

WriteLn (' Is it in ' , FSearch (' Is ' , strpas (Getenv (' PATH '))));

end.

FSplit

Declaration: Procedure FSplit (const Path : PathStr;
 Var Dir : DirStr; Var Name : NameStr; Var Ext : ExtStr);

Description: `FSplit` splits a full file name into 3 parts : A `Path`, a `Name` and an extension (in `ext`). The extension is taken to be all letters after the last dot (.).

Errors: None.

See also: `FSearch` ([190](#))

Listing: linuxex/ex67.pp

```
Program Example67;

uses Linux;

{ Program to demonstrate the FSplit function. }

var
  Path, Name, Ext : string;

begin
  FSplit (ParamStr(1), Path, Name, Ext);
  WriteLn(' Split _', ParamStr(1), '_ in :');
  WriteLn(' Path _', Path);
  WriteLn(' Name _', Name);
  WriteLn(' Extension : _', Ext);
end.
```

FSStat

Declaration: `Function FSStat (Path : Pathstr; Var Info : statfs) : Boolean; Function FSStat (Fd:longint;Var Info:stat) : Boolean;`

Description: Return in `Info` information about the filesystem on which the file `Path` resides, or on which the file with file descriptor `fd` resides. `Info` is of type `statfs`. The function returns `True` if the call was succesfull, `False` if the call failed.

Errors: `LinuxError` is used to report errors.

`sys_enotdir` A component of `Path` is not a directory.
`sys_einval` Invalid character in `Path`.
`sys_enoent` `Path` does not exist.
`sys_eaccess` Search permission is denied for component in `Path`.
`sys_eloop` A circular symbolic link was encountered in `Path`.
`sys_eio` An error occurred while reading from the filesystem.

See also: `FStat` ([192](#)), `LStat` ([207](#)), `statfs` (2)

Listing: linuxex/ex30.pp

```
program Example30;

{ Program to demonstrate the FSStat function. }

uses linux;

var s : string;
```

```

    info : statfs ;

begin
  writeln ( ' Info_about_current_partition _:_ ');
  s:= '.' ;
  while s<>'q' do
    begin
      if not fsstat (s,info) then
        begin
          writeln ( ' Fstat_failed _:_Errno _:_ ', linuxerror );
          halt (1);
        end;
      writeln ;
      writeln ( ' Result_of_fsstat_on_file _'' ',s, '' '. ');
      writeln ( ' fstype _:_ ', info . fstype );
      writeln ( ' bsize _:_ ', info . bsize );
      writeln ( ' bfree _:_ ', info . bfree );
      writeln ( ' bavail _:_ ', info . bavail );
      writeln ( ' files _:_ ', info . files );
      writeln ( ' ffree _:_ ', info . ffree );
      writeln ( ' fsid _:_ ', info . fsid );
      writeln ( ' Namelen _:_ ', info . namelen );
      write ( ' Type_name_of_file _to_do_fsstat _:(q_quits) _:' );
      readln ( s )
    end;
  end.

```

FStat

Declaration: Function FStat(Path:Pathstr;Var Info:stat):Boolean; Function FStat(Fd:longint;Var Info:stat):Boolean; Function FStat(var F:Text;Var Info:stat):Boolean; Function FStat(var F:File;Var Info:stat):Boolean;

Description: FStat gets information about the file specified in one of the following:

Patha file on the filesystem.

Fda valid file descriptor.

Fan opened text file or untyped file.

and stores it in **Info**, which is of type **stat**. The function returns **True** if the call was succesfull, **False** if the call failed.

Errors: **LinuxError** is used to report errors.

sys_enoentPath does not exist.

See also: **FSStat** ([191](#)), **LStat** ([207](#)), **stat** ([2](#))

Listing: linuxex/ex28.pp

```

program example28;

{ Program to demonstrate the FStat function. }

uses linux ;

var f : text;

```

```

    i : byte;
    info : stat;

begin
    { Make a file }
    assign ( f, ' test . fil ' );
    rewrite ( f );
    for i:=1 to 10 do writeln ( f, ' Testline _#_', i );
    close ( f );
    { Do the call on made file . }
    if not fstat ( ' test . fil ', info ) then
        begin
            writeln ( ' Fstat _failed _Errno _:_', linuxerror );
            halt ( 1 );
        end;
    writeln ;
    writeln ( ' Result _of _fstat _on _file _' ' test . fil ' ' . ' );
    writeln ( ' Inode _:_:_', info . ino );
    writeln ( ' Mode _:_:_:_', info . mode );
    writeln ( ' nlink _:_:_:_', info . nlink );
    writeln ( ' uid _:_:_:_:_', info . uid );
    writeln ( ' gid _:_:_:_:_', info . gid );
    writeln ( ' rdev _:_:_:_:_', info . rdev );
    writeln ( ' Size _:_:_:_:_', info . size );
    writeln ( ' Blksize _:_:_', info . blksize );
    writeln ( ' Blocks _:_:_', info . blocks );
    writeln ( ' atime _:_:_:_', info . atime );
    writeln ( ' mtime _:_:_:_', info . mtime );
    writeln ( ' ctime _:_:_:_', info . ctime );
    { Remove file }
    erase ( f );
end.

```

Fcntl

Declaration: Function Fcntl(Fd:longint;Cmd:Integer):integer; Function Fcntl(var Fd:Text;Cmd:Integer)

Description: Read a file's attributes. Fd is an assigned file, or a valid file descriptor. Cmd specifies what to do, and is one of the following:

F_GetFdRead the close_on_exec flag. If the low-order bit is 0, then the file will remain open across execve calls.

F_GetFlRead the descriptor's flags.

F_GetOwnGet the Process ID of the owner of a socket.

Errors: LinuxError is used to report errors.

sys_ebadfFd has a bad file descriptor.

See also: Fcntl ([193](#)), Fcnt l (2)

Fcntl

Declaration: Procedure Fcntl (Fd : text, Cmd : Integer; Arg : longint); Procedure Fcntl (Fd:longint;Cmd:longint;Arg:Longint);

Description: Read or Set a file's attributes. `Fd` is an assigned file or a valid file descriptor. `Cmd` specifies what to do, and is one of the following:

F_SetFd Set the `close_on_exec` flag of `Fd`. (only the least significant bit is used).

F_GetLk Return the `flock` record that prevents this process from obtaining the lock, or set the `l_type` field of the lock if there is no obstruction. `Arg` is a pointer to a `flock` record.

F_SetLk Set the lock or clear it (depending on `l_type` in the `flock` structure). if the lock is held by another process, an error occurs.

F_GetLkw Same as for **F_Setlk**, but wait until the lock is released.

F_SetOwn Set the Process or process group that owns a socket.

Errors: `LinuxError` is used to report errors.

sys_ebadf `Fd` has a bad file descriptor.

sys_eagain or **sys_eaccess** For **F_SetLk**, if the lock is held by another process.

See also: `Fcntl` ([193](#)), `Fcntl` (2), `seefLock`

Fork

Declaration: `Function Fork : Longint;`

Description: `Fork` creates a child process which is a copy of the parent process. `Fork` returns the process ID in the parent process, and zero in the child's process. (you can get the parent's PID with `GetPPid` ([200](#))).

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagain Not enough memory to create child process.

See also: `Execve` ([182](#)), `Clone` ([174](#)), `fork` (2)

FRename

Declaration: `Function FRename (OldName, NewName : Pchar) : Boolean;` `Function FRename (OldName, NewName : String) : Boolean;`

Description: `FRename` renames the file `OldName` to `NewName`. `NewName` can be in a different directory than `OldName`, but it cannot be on another partition (device). Any existing file on the new location will be replaced.

If the operation fails, then the `OldName` file will be preserved.

The function returns `True` on success, `False` on failure.

Errors: On error, errors are reported in `LinuxError`. Possible errors include:

sys_eisdir `NewName` exists and is a directory, but `OldName` is not a directory.

sys_exdev `NewName` and `OldName` are on different devices.

sys_enotempty or **sys_eexist** `NewName` is an existing, non-empty directory.

sys_ebusy `OldName` or `NewName` is a directory and is in use by another process.

sys_einval `NewName` is part of `OldName`.

sys_mlink `OldPath` or `NewPath` already have the maximum amount of links pointing to them.

sys_enotdir part of `OldName` or `NewName` is not directory.

sys_efault For the `pchar` case: One of the pointers points to an invalid address.

sys_eaccessaccess is denied when attempting to move the file.

sys_enametoolongEither OldName or NewName is too long.

sys_enoenta directory component in OldName or NewName didn't exist.

sys_enomemnot enough kernel memory.

sys_erofsNewName or OldName is on a read-only file system.

sys_elooptoo many symbolic links were encountered trying to expand OldName or NewName

sys_enospthe filesystem has no room for the new directory entry.

See also: UnLink ([231](#))

GetDate

Declaration: Procedure GetDate (Var Year, Month, Day : Word) ;

Description: Returns the current date.

Errors: None

See also: GetEpochTime ([197](#)), GetTime ([201](#)), GetDateTime ([195](#)), EpochToLocal ([179](#))

Listing: linuxex/ex6.pp

```
Program Example6;

{ Program to demonstrate the GetDate function . }

Uses linux ;

Var Year , Month , Day : Word;

begin
  GetDate ( Year , Month , Day);
  WriteLn ( ' Date : ', Day:2, ' / ' , Month:2, ' / ' , Year:4);
end.
```

GetDateTime

Declaration: Procedure GetDateTime(Var Year, Month, Day, hour, minute, second:Word);

Description: Returns the current date and time. The time is corrected for the local time zone. This procedure is equivalent to the GetDate ([195](#)) and GetTime calls.

Errors: None

See also: GetEpochTime ([197](#)), GetTime ([201](#)), EpochToLocal ([179](#)), GetDate ([195](#))

Listing: linuxex/ex60.pp

```
Program Example6;

{ Program to demonstrate the GetDateTime function . }

Uses linux ;
```

```
Var Year, Month, Day, Hour, min, sec : Word;

begin
  GetDateTime ( Year, Month, Day, Hour, min, sec);
  Writeln ( ' Date _:', Day:2, '/' , Month:2, '/' , Year:4);
  Writeln ( ' Time _:', Hour:2, ':' , Min:2, ':' , Sec:2);
end.
```

GetDomainName

Declaration: Function GetDomainName : String;

Description: Get the domain name of the machine on which the process is running. An empty string is returned if the domain is not set.

Errors: None.

See also: GetHostName ([199](#)), seemGetdomainname2

Listing: linuxex/ex39.pp

```
Program Example39;

{ Program to demonstrate the GetDomainName function . }

Uses linux ;

begin
  Writeln ( ' Domain_name_of _this _machine _is _:', GetDomainName);
end.
```

GetEGid

Declaration: Function GetEGid : Longint;

Description: Get the effective group ID of the currently running process.

Errors: None.

See also: GetGid ([198](#)), getegid (2)

Listing: linuxex/ex18.pp

```
Program Example18;

{ Program to demonstrate the GetGid and GetEGid functions . }

Uses linux ;

begin
  writeln ( ' Group_Id _=_', getgid , ' _ Effective _group_Id _=_', getegid );
end.
```

GetEuid

Declaration: Function GetEuid : Longint;

Description: Get the effective user ID of the currently running process.

Errors: None.

See also: GetEuid ([197](#)), geteuid (2)

Listing: linuxex/ex17.pp

Program Example17;

{ Program to demonstrate the GetUid and GetEuid functions . }

Uses linux ;

begin

writeln (' User_Id = ', getuid , ' Effective User_Id = ', geteuid);

end.

GetEnv

Declaration: Function GetEnv (P : String) : PChar;

Description: Returns the value of the environment variable in P. If the variable is not defined, nil is returned. The value of the environment variable may be the empty string. A PChar is returned to accomodate for strings longer than 255 bytes, TERMCAP and LS_COLORS, for instance.

Errors: None.

See also: sh (1) , csh (1)

Listing: linuxex/ex41.pp

Program Example41;

{ Program to demonstrate the GetEnv function . }

Uses linux ;

begin

writeln (' Path_is ', Getenv (' PATH'));

end.

GetEpochTime

Declaration: Function GetEpochTime : longint;

Description: returns the number of seconds since 00:00:00 gmt, january 1, 1970. it is adjusted to the local time zone, but not to DST.

Errors: no errors

See also: EpochToLocal ([179](#)), GetTime ([201](#)), time (2)

Listing: linuxex/ex1.pp

```
Program Example1;

{ Program to demonstrate the GetEpochTime function . }

Uses linux ;

begin
  Write ( ' Secs_past_the_start_of_the_Epoch_(00:00_1/1/1980)_:_ ' );
  WriteLn ( GetEpochTime );
end.
```

GetFS

Declaration: Function GetFS (Var F : Any File Type) : Longint;

Description: GetFS returns the file selector that the kernel provided for your file. In principle you don' need this file selector. Only for some calls it is needed, such as the [Select \(218\)](#) call or so.

Errors: In case the file was not opened, then -1 is returned.

See also: [Select \(218\)](#)

Listing: linuxex/ex34.pp

```
Program Example33;

{ Program to demonstrate the SelectText function . }

Uses linux ;

Var tv : TimeVal;

begin
  WriteLn ( ' Press_the_<ENTER>_to_continue_the_program.' );
  { Wait until File descriptor 0 (= Input) changes }
  SelectText ( Input, nil );
  { Get rid of <ENTER> in buffer }
  readln ;
  WriteLn ( ' Press_<ENTER>_key_in_less_than_2_seconds...' );
  tv . sec := 2;
  tv . usec := 0;
  if SelectText ( Input, @tv) > 0 then
    WriteLn ( ' Thank_you_' );
  else
    WriteLn ( ' Too_late_' );
end.
```

GetGid

Declaration: Function GetGid : Longint;

Description: Get the real group ID of the currently running process.

Errors: None.

See also: [GetEGid \(196\)](#), [getgid \(2\)](#)

Listing: linuxex/ex18.pp

```
Program Example18;  
  
{ Program to demonstrate the GetGid and GetEGid functions . }  
  
Uses linux ;  
  
begin  
  writeln ( ' Group_Id =_', getgid , '_ Effective_group_Id =_', getegid );  
end.
```

GetHostName

Declaration: `Function GetHostName : String;`

Description: Get the hostname of the machine on which the process is running. An empty string is returned if hostname is not set.

Errors: None.

See also: [GetDomainName \(196\)](#), [seemGethostname2](#)

Listing: linuxex/ex40.pp

```
Program Example40;  
  
{ Program to demonstrate the GetHostName function . }  
  
Uses linux ;  
  
begin  
  writeln ( ' Name_of_this_machine_is _:', GetHostName );  
end.
```

GetLocalTimezone

Declaration: `procedure GetLocalTimezone(timer:longint;var leap_correct, leap_hit:longint);`
`procedure GetLocalTimezone(timer:longint);`

Description: `GetLocalTimezone` returns the local timezone information. It also initializes the `TZSeconds` variable, which is used to correct the epoch time to local time.

There should never be any need to call this function directly. It is called by the initialization routines of the Linux unit.

See also: [GetTimezoneFile \(202\)](#), [ReadTimezoneFile \(218\)](#)

GetPid

Declaration: `Function GetPid : Longint;`

Description: Get the Process ID of the currently running process.

Errors: None.

See also: [GetPPid \(200\)](#), [getpid \(2\)](#)

Listing: linuxex/ex16.pp

```
Program Example16;  
  
{ Program to demonstrate the GetPid, GetPPid function . }  
  
Uses linux ;  
  
begin  
  WriteLn ( ' Process_Id = ', getpid , ' Parent_process_Id = ', getppid );  
end.
```

GetPPid

Declaration: Function GetPPid : Longint;

Description: Get the Process ID of the parent process.

Errors: None.

See also: [GetPid \(199\)](#), [getppid \(2\)](#)

Listing: linuxex/ex16.pp

```
Program Example16;  
  
{ Program to demonstrate the GetPid, GetPPid function . }  
  
Uses linux ;  
  
begin  
  WriteLn ( ' Process_Id = ', getpid , ' Parent_process_Id = ', getppid );  
end.
```

GetPriority

Declaration: Function GetPriority (Which,Who : Integer) : Integer;

Description: GetPriority returns the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the pre-defined Prio_Process, Prio_PGrp, Prio_User, in which case Who is the process ID, Process group ID or User ID, respectively.

Errors: Error checking must be done on LinuxError, since a priority can be negative.

sys_esrchNo process found using which and who.

sys_einvalWhich was not one of Prio_Process, Prio_Grp or Prio_User.

See also: [SetPriority \(220\)](#), [Nice \(212\)](#), [Getpriority \(2\)](#)

For an example, see [Nice \(212\)](#).

GetTime

Declaration: `procedure GetTime(var hour,min,sec,msec,usec:word); procedure GetTime(var hour,min,sec,sec100:word); procedure GetTime(var hour,min,sec:word);`

Description: Returns the current time of the day, adjusted to local time. Upon return, the parameters are filled with

hourHours since 00:00 today.

minminutes in current hour.

secseconds in current minute.

sec100hundreds of seconds in current second.

msecmilliseconds in current second.

usecmicroseconds in current second.

Errors: None

See also: [GetEpochTime \(197\)](#), [GetDate \(195\)](#), [GetDateTime \(195\)](#), [EpochToLocal \(179\)](#)

Listing: linuxex/ex5.pp

Program Example5;

{ Program to demonstrate the GetTime function . }

Uses linux ;

Var Hour , Minute , Second : Word;

begin

 GetTime (Hour , Minute , Second);

Writeln (' Time_':_ , Hour :2 , ':' , Minute :2 , ':' , Second :2);

end.

GetTimeOfDay

Declaration: `Procedure GetTimeOfDay(var tv:timeval);`

Description: `GetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT in a `timeval` record. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call. To get the local time, [GetTime \(201\)](#).

Errors: None.

See also: [GetTime \(201\)](#), [GetTimeOfDay \(201\)](#)

GetTimeOfDay

Declaration: `Function GetTimeOfDay:longint;`

Description: `GetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call. To get the local time, [GetTime \(201\)](#).

Errors: None.

See also: [GetTimeOfDay \(201\)](#), [GetTime \(201\)](#)

GetTimezoneFile

Declaration: `function GetTimezoneFile:string;`

Description: `GetTimezoneFile` returns the location of the current timezone file. The location of file is determined as follows:

- 1.If `/etc/timezone` exists, it is read, and the contents of this file is returned. This should work on Debian systems.
- 2.If `/usr/lib/zoneinfo/localtime` exists, then it is returned. (this file is a symlink to the timezone file on SuSE systems)
- 3.If `/etc/localtime` exists, then it is returned. (this file is a symlink to the timezone file on RedHat systems)

Errors: If no file was found, an empty string is returned.

See also: `ReadTimezoneFile` ([218](#))

GetUid

Declaration: `Function GetUid : Longint;`

Description: Get the real user ID of the currently running process.

Errors: None.

See also: `GetEUid` ([197](#)), `getuid` (2)

Listing: `linuxex/ex17.pp`

```
Program Example17;

{ Program to demonstrate the GetUid and GetEUid functions . }

Uses linux ;

begin
  writeln ( ' User_Id =_', getuid , '_ Effective_user_Id =_', geteuid );
end.
```

Glob

Declaration: `Function Glob (Const Path : Pathstr) : PGlob;`

Description: `Glob` returns a pointer to a glob structure which contains all filenames which exist and match the pattern in `Path`. The pattern can contain wildcard characters, which have their usual meaning.

Errors: Returns nil on error, and `LinuxError` is set.

sys_enomemNo memory on heap for glob structure.
othersAs returned by the `opendir` call, and `sys_readdir`.

See also: `GlobFree` ([203](#)), `Glob` (3)

Listing: `linuxex/ex49.pp`

```
Program Example49;

{ Program to demonstrate the Glob and GlobFree functions . }

Uses linux ;

Var G1,G2 : PGlob;

begin
  G1:=Glob ( '*' );
  if LinuxError=0 then
    begin
      G2:=G1;
      WriteLn ( ' Files _in _this _directory _:_ ' );
      While g2<>Nil do
        begin
          WriteLn ( g2^.name);
          g2:=g2^. next;
        end;
      GlobFree ( g1);
    end;
end.
```

GlobFree

Declaration: Procedure GlobFree (Var P : Pglob);

Description: Releases the memory, occupied by a pglob structure. P is set to nil.

Errors: None

See also: Glob ([202](#))

For an example, see Glob ([202](#)).

IOctl

Declaration: Procedure IOctl (Handle, Ndx: Longint; Data: Pointer);

Description: This is a general interface to the Unix/ LINUX ioctl call. It performs various operations on the filedescriptor `Handle`. `Ndx` describes the operation to perform. `Data` points to data needed for the `Ndx` function. The structure of this data is function-dependent, so we don't elaborate on this here. For more information on this, see various manual pages under linux.

Errors: Errors are reported in LinuxError. They are very dependent on the used function, that's why we don't list them here

See also: `ioctl` (2)

Listing: linuxex/ex54.pp

```
Program Example54;
```

```
uses Linux;
```

```
{ Program to demonstrate the IOCTL function . }  
  
var  
  tios : Termios;  
begin  
  IOCTL (1, TCGETS, @tios);  
  WriteLn( ' Input_Flags :_$_' , hexstr( tios . c_iflag , 8));  
  WriteLn( ' Output_Flags :_$_' , hexstr( tios . c_oflag , 8));  
  WriteLn( ' Line_Flags :_$_' , hexstr( tios . c_lflag , 8));  
  WriteLn( ' Control_Flags :_$_' , hexstr( tios . c_cflag , 8));  
end.
```

IOperm

Declaration: Function IOperm (From, Num : Cardinal; Value : Longint) : boolean;

Description: IOperm sets permissions on Num ports starting with port From to Value. The function returns True if the call was successful, False otherwise. *Remark:*

- This works ONLY as root.
- Only the first 0x03ff ports can be set.
- When doing a Fork ([194](#)), the permissions are reset. When doing a Execve ([182](#)) they are kept.

Errors: Errors are returned in LinuxError

See also: ioperm ([2](#))

IsATTY

Declaration: Function IsATTY (var f) : Boolean;

Description: Check if the filehandle described by f is a terminal. f can be of type

1. longint for file handles;
2. Text for text variables such as input etc.

Returns True if f is a terminal, False otherwise.

Errors: No errors are reported

See also: IOCTL ([203](#)), TTYName ([230](#))

S_ISBLK

Declaration: Function S_ISBLK (m:integer) : boolean;

Description: S_ISBLK checks the file mode m to see whether the file is a block device file. If so it returns True.

Errors: FStat ([192](#)), S_ISLNK ([205](#)), S_ISREG ([206](#)), S_ISDIR ([205](#)), S_ISCHR ([205](#)), S_ISFIFO ([205](#)), S_ISSOCK ([206](#))

See also: ISLNK.

S_ISCHR

Declaration: Function S_ISCHR (m:integer) : boolean;

Description: S_ISCHR checks the file mode m to see whether the file is a character device file. If so it returns True.

Errors: FStat (192), S_ISLNK (205), S_ISREG (206), S_ISDIR (205), S_ISBLK (204), S_ISFIFO (205), S_ISSOCK (206)

See also: ISLNK.

S_ISDIR

Declaration: Function S_ISDIR (m:integer) : boolean;

Description: S_ISDIR checks the file mode m to see whether the file is a directory. If so it returns True

Errors: FStat (192), S_ISLNK (205), S_ISREG (206), S_ISCHR (205), S_ISBLK (204), S_ISFIFO (205), S_ISSOCK (206)

See also: ISLNK.

S_ISFIFO

Declaration: Function S_ISFIFO (m:integer) : boolean;

Description: S_ISFIFO checks the file mode m to see whether the file is a fifo (a named pipe). If so it returns True.

Errors: FStat (192), S_ISLNK (205), S_ISREG (206), S_ISDIR (205), S_ISCHR (205), S_ISBLK (204), S_ISSOCK (206)

See also: ISLNK.

S_ISLNK

Declaration: Function S_ISLNK (m:integer) : boolean;

Description: S_ISLNK checks the file mode m to see whether the file is a symbolic link. If so it returns True

Errors: FStat (192), S_ISREG (206), S_ISDIR (205), S_ISCHR (205), S_ISBLK (204), S_ISFIFO (205), S_ISSOCK (206)

See also:

Listing: linuxex/ex53.pp

Program Example53;

{ Program to demonstrate the S_ISLNK function . }

Uses linux ;

Var Info : Stat;

begin

```
if LStat ( paramstr(1), info ) then
begin
  if S_ISLNK( info .mode) then
    Writeln ( ' File _is _a _link ' );
  if S_ISREG( info .mode) then
    Writeln ( ' File _is _a _regular _file ' );
  if S_ISDIR( info .mode) then
    Writeln ( ' File _is _a _directory ' );
  if S_ISCHR( info .mode) then
    Writeln ( ' File _is _a _character _device _file ' );
  if S_ISBLK( info .mode) then
    Writeln ( ' File _is _a _block _device _file ' );
  if S_ISFIFO( info .mode) then
    Writeln ( ' File _is _a _named _pipe _(FIFO)' );
  if S_ISSOCK( info .mode) then
    Writeln ( ' File _is _a _socket ' );
end;
end.
```

S_ISREG

Declaration: Function S_ISREG (m:integer) : boolean;

Description: S_ISREG checks the file mode m to see whether the file is a regular file. If so it returns True

Errors: FStat ([192](#)), S_ISLNK ([205](#)), S_ISDIR ([205](#)), S_ISCHR ([205](#)), S_ISBLK ([204](#)), S_ISFIFO ([205](#)), S_ISSOCK ([206](#))

See also: ISLNK.

S_ISSOCK

Declaration: Function S_ISSOCK (m:integer) : boolean;

Description: S_ISSOCK checks the file mode m to see whether the file is a socket. If so it returns True.

Errors: FStat ([192](#)), S_ISLNK ([205](#)), S_ISREG ([206](#)), S_ISDIR ([205](#)), S_ISCHR ([205](#)), S_ISBLK ([204](#)), S_ISFIFO ([205](#))

See also: ISLNK.

Kill

Declaration: Function Kill (Pid : Longint; Sig : Integer) : Integer;

Description: Send a signal Sig to a process or process group. If Pid>0 then the signal is sent to Pid, if it equals -1, then the signal is sent to all processes except process 1. If Pid<-1 then the signal is sent to process group -Pid. The return value is zero, except in case three, where the return value is the number of processes to which the signal was sent.

Errors: LinuxError is used to report errors:

sys_einvalAn invalid signal is sent.

sys_esrchThe Pid or process group don't exist.

sys_epermThe effective userid of the current process doesn't math the one of process Pid.

See also: SigAction ([221](#)), Signal ([223](#)), Kill (2)

LStat

Declaration: Function LStat (Path : Pathstr; Var Info : stat) : Boolean;

Description: LStat gets information about the link specified in Path, and stores it in Info, which is of type stat. Contrary to FStat, it stores information about the link, not about the file the link points to. The function returns True if the call was succesfull, False if the call failed.

Errors: LinuxError is used to report errors.

sys_enoentPath does not exist.

See also: FStat ([192](#)), FSStat ([191](#)), stat ([2](#))

Listing: linuxex/ex29.pp

```
program example29;

{ Program to demonstrate the LStat function. }

uses linux;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign ( f, ' test . fil ' );
  rewrite ( f );
  for i := 1 to 10 do writeln ( f, ' Testline _#_', i );
  close ( f );
  { Do the call on made file . }
  if not fstat ( ' test . fil ', info ) then
    begin
      writeln ( ' Fstat _failed _Errno _:', linuxerror );
      halt ( 1 );
    end;
  writeln;
  writeln ( ' Result_of_fstat_on_file _' test . fil ' ' );
  writeln ( ' Inode _:', info . ino );
  writeln ( ' Mode _:', info . mode );
  writeln ( ' nlink _:', info . nlink );
  writeln ( ' uid _:', info . uid );
  writeln ( ' gid _:', info . gid );
  writeln ( ' rdev _:', info . rdev );
  writeln ( ' Size _:', info . size );
  writeln ( ' Blksize _:', info . blksize );
  writeln ( ' Blocks _:', info . blocks );
  writeln ( ' atime _:', info . atime );
  writeln ( ' mtime _:', info . mtime );
  writeln ( ' ctime _:', info . ctime );

  If not SymLink ( ' test . fil ', ' test . lnk ' ) then
    writeln ( ' Link _failed _!_Errno _:', linuxerror );

  if not lstat ( ' test . lnk ', info ) then
    begin
      writeln ( ' LStat _failed _Errno _:', linuxerror );
```

```
    halt (1);
end;
writeln;
writeln ( ' Result_of_fstat_on_file ' ' test . lnk ' ' . ' );
writeln ( ' Inode_:::', info . ino );
writeln ( ' Mode_:::', info . mode );
writeln ( ' nlink_:::', info . nlink );
writeln ( ' uid_:::', info . uid );
writeln ( ' gid_:::', info . gid );
writeln ( ' rdev_:::', info . rdev );
writeln ( ' Size_:::', info . size );
writeln ( ' Blksize_:::', info . blksize );
writeln ( ' Blocks_:::', info . blocks );
writeln ( ' atime_:::', info . atime );
writeln ( ' mtime_:::', info . mtime );
writeln ( ' ctime_:::', info . ctime );
{ Remove file and link }
erase ( f );
unlink ( ' test . lnk ' );
end.
```

Link

Declaration: Function Link (OldPath,NewPath : pathstr) : Boolean;

Description: Link makes NewPath point to the same file als OldPath. The two files then have the same inode number. This is known as a 'hard' link. The function returns True if the call was succesfull, False if the call failed.

Errors: Errors are returned in LinuxError.

sys_exdevOldPath and NewPath are not on the same filesystem.

sys_epermThe filesystem containing oldpath and newpath doesn't support linking files.

sys_eaccessWrite access for the directory containing Newpath is disallowed, or one of the directories in OldPath or NewPath has no search (=execute) permission.

sys_enoentA directory entry in OldPath or NewPath does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdirA directory entry in OldPath or NewPath is nor a directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe files are on a read-only filesystem.

sys_eexistNewPath already exists.

sys_mlinkOldPath has reached maximal link count.

sys_eloopOldPath or NewPath has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospcThe device containing NewPath has no room for anothe entry.

sys_epermOldPath points to . or .. of a directory.

See also: SymLink (225), UnLink (231), Link (2)

Listing: linuxex/ex21.pp

```
Program Example21;

{ Program to demonstrate the Link and UnLink functions . }

Uses linux ;

Var F : Text;
    S : String ;
begin
    Assign ( F, ' test . txt ' );
    Rewrite ( F );
    Writeln ( F, ' This_is_written_to_test . txt ' );
    Close ( f );
    { new.txt and test.txt are now the same file }
    if not Link ( ' test . txt ', ' new . txt ' ) then
        writeln ( ' Error_when_linking _!' );
    { Removing test.txt still leaves new.txt }
    If not Unlink ( ' test . txt ' ) then
        Writeln ( ' Error_when_unlinking _!' );
    Assign ( f, ' new . txt ' );
    Reset ( F );
    While not EOF(f) do
        begin
            Readln(F,S);
            Writeln ( '>_', s );
        end;
    Close ( f );
    { Remove new.txt also }
    If not Unlink ( ' new . txt ' ) then
        Writeln ( ' Error_when_unlinking _!' );
end.
```

LocalToEpoch

Declaration: Function LocalToEpoch (Year,Month,Day,Hour,Minute,Second : Word) : longint;

Description: Converts the Local time to epoch time (=Number of seconds since 00:00:00 , January 1, 1970).

Errors: None

See also: GetEpochTime ([197](#)), EpochToLocal ([179](#)), GetTime ([201](#)),GetDate ([195](#))

Listing: linuxex/ex4.pp

```
Program Example4;

{ Program to demonstrate the LocalToEpoch function . }

Uses linux ;

Var year , month , day , hour , minute , second : Word;

begin
    Write ( ' Year_:_:' ); readln ( Year );
    Write ( ' Month_:_:' ); readln ( Month );
```

```

Write ( ' Day_____:' ); readln ( Day );
Write ( ' Hour_____:' ); readln ( Hour );
Write ( ' Minute____:' ); readln ( Minute );
Write ( ' Seonds____:' ); readln ( Second );
Write ( ' This_is____:' );
Write ( LocalToEpoch ( year , month , day , hour , minute , second ) );
Writeln ( ' _seconds_past_00:00_1/1/1980' );
end.

```

MkFifo

Declaration: Function MkFifo (PathName: String; Mode : Longint) : Boolean;

Description: MkFifo creates a named pipe in the filesystem, with name PathName and mode Mode.

Errors: LinuxError is used to report errors:

sys_emfileToo many file descriptors for this process.

sys_enfileThe system file table is full.

See also: POpen ([214](#)), MkFifo ([210](#)), mkfifo ([4](#))

MMap

Declaration: Function MMap(const m:tmmapargs):longint;

Description: MMap maps or unmaps files or devices into memory. The different fields of the argument m determine what and how the mmap maps this:

addressAddress where to mmap the device. This address is a hint, and may not be followed.

sizeSize (in bytes) of area to be mapped.

protProtection of mapped memory. This is a OR-ed combination of the following constants:

PROT_EXECThe memory can be executed.

PROT_READThe memory can be read.

PROT_WRITEThe memory can be written.

PROT_NONEThe memory can not be accessed.

flagsContains some options for the mmap call. It is an OR-ed combination of the following constants:

MAP_FIXEDDo not map at another address than the given address. If the address cannot be used, MMap will fail.

MAP_SHAREDShare this map with other processes that map this object.

MAP_PRIVATECreate a private map with copy-on-write semantics.

MAP_ANONYMOUSfd does not have to be a file descriptor.

One of the options MAP_SHARED and MAP_PRIVATE must be present, but not both at the same time.

fdFile descriptor from which to map.

offsetOffset to be used in file descriptor fd.

The function returns a pointer to the mapped memory, or a -1 in case of an error.

Errors: On error, -1 is returned and LinuxError is set to the error code:

Sys_EBADFfd is not a valid file descriptor and MAP_ANONYMOUS was not specified.

Sys_EACCESSMAP_PRIVATE was specified, but fd is not open for reading. Or **MAP_SHARED** was asked and **PROT_WRITE** is set, fd is not open for writing

Sys_EINVALOne of the record fields **Start**, **length** or **offset** is invalid.

Sys_ETXTBUSY**MAP_DENYWRITE** was set but the object specified by fd is open for writing.

Sys_EAGAINfd is locked, or too much memory is locked.

Sys_ENOMEMNot enough memory for this operation.

See also: **MUnMap** ([211](#)), **mmap** ([2](#))

Listing: linuxex/ex66.pp

Program Example66;

{ Program to demonstrate the MMap function . }

Uses linux ;

Var S : **String** ;

fd, Len : Longint ;

args : tmapargs ;

P : PChar ;

begin

S:= ' This_is_a_string ' #0;

Len:= **Length**(S);

fd:=fdOpen(' testfile .txt ', Open_wrOnly or open_creat);

If fd=-1 **then**

Halt(1);

If fdWrite (fd ,S[1], Len)=-1 **then**

Halt(2);

fdClose (fd);

fdOpen(' testfile .txt ', Open_rdOnly);

if fd=-1 **then**

Halt(3);

args . address :=0;

args . offset :=0;

args . size := Len+1;

args . fd :=Fd;

args . flags :=MAP_PRIVATE;

args . prot :=PROT_READ or PROT_WRITE;

P:= Pchar (mmap(args));

If longint (P)=-1 **then**

Halt(4);

Writeln (' Read_in_memory_':', P);

fdclose (fd);

if Not MUnMap(P, Len) **Then**

Halt (LinuxError);

end.

MUnMap

Declaration: function MUnMap (P : Pointer; Size : Longint) : Boolean;

Description: MUnMap unmaps the memory block of size Size, pointed to by P, which was previously allocated with MMap ([210](#)).

The function returns **True** if successful, **False** otherwise.

Errors: In case of error the function returns `False` and `LinuxError` is set to an error value. See `MMap` (210) for possible error values.

See also: `MMap` (210), `munmap` (2)

For an example, see `MMap` (210).

Nice

Declaration: `Procedure Nice ( N : Integer);`

Description: `Nice` adds `-N` to the priority of the running process. The lower the priority numerically, the less the process is favored. Only the superuser can specify a negative `N`, i.e. increase the rate at which the process is run.

Errors: Errors are returned in `LinuxError`

`sys_epermA` non-superuser tried to specify a negative `N`, i.e. do a priority increase.

See also: `GetPriority` (200), `SetPriority` (220), `Nice` (2)

Listing: `linuxex/ex15.pp`

Program `Example15;`

{ Program to demonstrate the Nice and Get/SetPriority functions . }

Uses `linux ;`

begin

`writeln ( ' Setting _priority _to _5' );`

`setpriority ( prio_process , getpid , 5);`

`writeln ( ' New _priority _= _', getpriority ( prio_process , getpid ));`

`writeln ( ' Doing _nice _10' );`

`nice (10);`

`writeln ( ' New _Priority _= _', getpriority ( prio_process , getpid ));`

end.

Octal

Declaration: `Function Octal(l:longint):longint;`

Description: `Octal` will convert a number specified as an octal number to its decimal value.

This is useful for the `Chmod` (173) call, where permissions are specified as octal numbers.

Errors: No checking is performed whether the given number is a correct Octal number. e.g. specifying 998 is possible; the result will be wrong in that case.

See also: `Chmod` (173).

Listing: `linuxex/ex68.pp`

Program `Example68;`

{ Program to demonstrate the Octal function . }

Uses linux ;

begin

Writeln ('Mode_777_', Octal (777));

Writeln ('Mode_644_', Octal (644));

Writeln ('Mode_755_', Octal (755));

end.

OpenDir

Declaration: Function OpenDir (f:pchar) : pdir; Function OpenDir (f:string) : pdir;

Description: OpenDir opens the directory f, and returns a pdir pointer to a Dir record, which can be used to read the directory structure. If the directory cannot be opened, nil is returned.

Errors: Errors are returned in LinuxError.

See also: CloseDir ([176](#)), ReadDir ([215](#)), SeekDir ([218](#)), TellDir ([230](#)), opendir (3)

Listing: linuxex/ex35.pp

Program Example35;

*{ Program to demonstrate the
 OpenDir, ReadDir, SeekDir and TellDir functions. }*

Uses linux ;

Var TheDir : PDir;
 ADirent : PDirent;
 Entry : Longint;

begin

 TheDir := OpenDir ('./.');

Repeat

 Entry := TellDir (TheDir);

 ADirent := ReadDir (TheDir);

If ADirent <> Nil **then**

With ADirent **^ do**

begin

Writeln (' Entry_No_', Entry);

Writeln (' Inode_', ino);

Writeln (' Offset_', off);

Writeln (' Reclen_', reclen);

Writeln (' Name_', pchar (@name[0]));

end;

Until ADirent = Nil ;

Repeat

Write (' Entry_No_ you_would_like_to_see_again_(-1_to_stop):_');

ReadLn (Entry);

If Entry <> -1 **then**

begin

 SeekDir (TheDir, Entry);

 ADirent := ReadDir (TheDir);

If ADirent <> Nil **then**

With ADirent **^ do**

begin

```
        Writeln ( ' Entry_No: ', Entry );
        Writeln ( ' Inode: ', ino );
        Writeln ( ' Offset: ', off );
        Writeln ( ' Reclen: ', reclen );
        Writeln ( ' Name: ', pchar (@name[0]));
    end;
    until Entry=-1;
    CloseDir ( TheDir );
end.
```

pause

Declaration: Procedure Pause;

Description: Pause puts the process to sleep and waits until the application receives a signal. If a signal handler is installed for the received signal, the handler will be called and after that pause will return control to the process.

Errors: None.

For an example, see Alarm ([168](#)).

PClose

Declaration: Function PClose (Var F : FileType) : longint;

Description: PClose closes a file opened with POpen. It waits for the command to complete, and then returns the exit status of the command.

Errors: LinuxError is used to report errors. If it is different from zero, the exit status is not valid.

See also: POpen ([214](#))

For an example, see POpen ([214](#))

POpen

Declaration: Procedure POpen (Var F : FileType; Cmd : pathstr; rw : char);

Description: Popen runs the command specified in Cmd, and redirects the standard in or output of the command to the other end of the pipe F. The parameter rw indicates the direction of the pipe. If it is set to 'W', then F can be used to write data, which will then be read by the command from stdin. If it is set to 'R', then the standard output of the command can be read from F. F should be reset or rewritten prior to using it. F can be of type Text or File. A file opened with POpen can be closed with Close, but also with PClose ([214](#)). The result is the same, but PClose returns the exit status of the command Cmd.

Errors: Errors are reported in LinuxError and are essentially those of the Execve, Dup and AssignPipe commands.

See also: AssignPipe ([168](#)), popen (3), PClose ([214](#))

Listing: linuxex/ex37.pp

Program Example37;

```
{ Program to demonstrate the Popen function . }

uses linux ;

var f : text;
    i : longint;

begin
  writeln ( ' Creating_a_shell_script_to_which_echoes_its_arguments' );
  writeln ( ' and_input_back_to_stdout' );
  assign ( f, ' test21a' );
  rewrite ( f );
  writeln ( f, '#!/ bin / sh' );
  writeln ( f, ' echo_this_is_the_child_speaking ....' );
  writeln ( f, ' echo_got_arguments_*"$*"');
  writeln ( f, ' cat' );
  writeln ( f, ' exit _2' );
  writeln ( f );
  close ( f );
  chmod ( ' test21a', octal (755));
  popen ( f, './ test21a_arg1_arg2', 'W' );
  if linuxerror <> 0 then
    writeln ( ' error_from_POpen:_Linuxerror _:', Linuxerror );
  for i:=1 to 10 do
    writeln ( f, ' This_is_written_to_the_pipe,_and_should_appear_on_stdout.' );
  Flush(f);
  Writeln ( ' The_script_exited_with_status _:', PClose ( f ));
  writeln ;
  writeln ( ' Press_return_to_remove_shell_script.' );
  readln ;
  assign ( f, ' test21a' );
  erase ( f )
end.
```

ReadDir

Declaration: Function ReadDir (p:pdirent) : pdirent;

Description: ReadDir reads the next entry in the directory pointed to by p. It returns a pdirent pointer to a structure describing the entry. If the next entry can't be read, Nil is returned.

Errors: Errors are returned in LinuxError.

See also: CloseDir ([176](#)), OpenDir ([213](#)), SeekDir ([218](#)), TellDir ([230](#)), readdir ([3](#))

For an example, see OpenDir ([213](#)).

ReadLink

Declaration: Function ReadLink(name, linkname:pchar;maxlen:longint):longint; Function ReadLink(name:pathstr):pathstr;

Description: ReadLink returns the file the symbolic link `name` is pointing to. The first form of this function accepts a buffer `linkname` of length `maxlen` where the filename will be stored. It returns the actual number of characters stored in the buffer.

The second form of the function returns simply the name of the file.

Errors: On error, the first form of the function returns -1; the second one returns an empty string. `LinuxError` is set to report errors:

SYS_ENOTDIRA part of the path in `Name` is not a directory.

SYS_EINVAL`maxlen` is not positive, or the file is not a symbolic link.

SYS_ENAMETOOLONGA pathname, or a component of a pathname, was too long.

SYS_ENOENTthe link `name` does not exist.

SYS_EACCESNo permission to search a directory in the path

SYS_ELOOPToo many symbolic links were encountered in translating the pathname.

SYS_EIOAn I/O error occurred while reading from the file system.

SYS_EFAULTThe buffer is not part of the process's memory space.

SYS_ENOMEMNot enough kernel memory was available.

See also: [SymLink \(225\)](#)

Listing: linuxex/ex62.pp

Program Example62;

{ Program to demonstrate the ReadLink function . }

Uses linux ;

Var F : Text;
 S : String;

begin

```
Assign (F, 'test.txt ');
Rewrite (F);
Writeln (F, ' This_is_written_to_test.txt ');
Close(f);
{ new.txt and test.txt are now the same file }
if not SymLink ( 'test.txt', 'new.txt' ) then
  writeln ( ' Error_when_symlinking _!' );
S:=ReadLink('new.txt ');
If S='' then
  Writeln ( ' Error_reading_link _!' )
Else
  Writeln ( ' Link_points_to _:',S);
{ Now remove links }
If not Unlink ( 'new.txt' ) then
  Writeln ( ' Error_when_unlinking _!' );
If not Unlink ( 'test.txt' ) then
  Writeln ( ' Error_when_unlinking _!' );
```

end.

ReadPort

Declaration: `Procedure ReadPort (Port : Longint; Var Value : Byte); Procedure ReadPort (Port : Longint; Var Value : Word); Procedure ReadPort (Port : Longint; Var Value : Longint);`

Description: `ReadPort` reads one Byte, Word or Longint from port `Port` into `Value`.

Note that you need permission to read a port. This permission can be set by the root user with the `IOperm` (204) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `IOperm` (204), `ReadPortB` (217), `ReadPortW` (218), `ReadPortL` (217), `WritePort` (233), `WritePortB` (233), `WritePortL` (233), `WritePortW` (234)

ReadPortB

Declaration: `Procedure ReadPortB (Port : Longint; Var Buf; Count: longint); Function ReadPortB (Port : Longint): Byte;`

Description: The procedural form of `ReadPortB` reads `Count` bytes from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` bytes.

The functional form of `ReadPortB` reads 1 byte from port `B` and returns the byte that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `IOperm` (204) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `IOperm` (204), `ReadPort` (217), `ReadPortW` (218), `ReadPortL` (217), `WritePort` (233), `WritePortB` (233), `WritePortL` (233), `WritePortW` (234)

ReadPortL

Declaration: `function ReadPortL (Port : Longint): LongInt; Procedure ReadPortL (Port : Longint; Var Buf; Count: longint);`

Description: The procedural form of `ReadPortL` reads `Count` longints from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` Longints.

The functional form of `ReadPortB` reads 1 longint from port `B` and returns the longint that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `IOperm` (204) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `IOperm` (204), `ReadPort` (217), `ReadPortW` (218), `ReadPortB` (217), `WritePort` (233), `WritePortB` (233), `WritePortL` (233), `WritePortW` (234)

ReadPortW

Declaration: Procedure ReadPortW (Port : Longint; Var Buf; Count: longint); function ReadPortW (Port : Longint): Word;

Description: The procedural form of ReadPortB reads Count words from port Port and stores them in Buf. There must be enough memory allocated at Buf to store Count words.

The functional form of ReadPortB reads 1 word from port B and returns the word that was read.

Note that you need permission to read a port. This permission can be set by the root user with the IOperm (204) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: IOperm (204), ReadPort (217), ReadPortB (217), ReadPortL (217), WritePort (233), WritePortB (233), WritePortL (233), WritePortW (234)

ReadTimezoneFile

Declaration: procedure ReadTimezoneFile(fn:string);

Description: ReadTimezoneFile reads the timezone file fn and initializes the local time routines based on the information found there.

There should be no need to call this function. The initialization routines of the linux unit call this routine at unit startup.

Errors: None.

See also: GetTimezoneFile (202), GetLocalTimezone (199)

SeekDir

Declaration: Procedure SeekDir (p:pdir;off:longint);

Description: SeekDir sets the directory pointer to the off-th entry in the directory structure pointed to by p.

Errors: Errors are returned in LinuxError.

See also: CloseDir (176), ReadDir (215), OpenDir (213), TellDir (230), seekdir (3)

For an example, see OpenDir (213).

Select

Declaration: Function Select (N : Longint;
var readfds,writefds,exceptfds : PFDset; Var Timeout) : Longint;

Description: Select checks one of the file descriptors in the FDsets to see if its status changed. readfds, writefds and exceptfds are pointers to arrays of 256 bits. If you want a file descriptor to be checked, you set the corresponding element in the array to 1. The other elements in the array must be set to zero. Three arrays are passed : The entries in readfds are checked to see if characters become available for reading. The entries in writefds are checked to see if it is OK to write to them, while entries in exceptfds are checked to see if an exception occurred on them. You can use the functions FD_ZERO (184), FD_Clr (184), FD_Set (185), FD_IsSet (185) to manipulate the individual elements of a set. The pointers can be nil. N is the largest index of a nonzero entry plus 1. (= the largest file-descriptor + 1). Timeout can be used to set a time limit. If Timeout can be two types :

1. `TimeOut` is of type `PTime` and contains a zero time, the call returns immediately. If `TimeOut` is `Nil`, the kernel will wait forever, or until a status changed.
2. `TimeOut` is of type `Longint`. If it is -1, this has the same effect as a `Timeout` of type `PTime` which is `Nil`. Otherwise, `TimeOut` contains a time in milliseconds.

When the `TimeOut` is reached, or one of the file descriptors has changed, the `Select` call returns. On return, it will have modified the entries in the array which have actually changed, and it returns the number of entries that have been changed. If the timeout was reached, and no descriptor changed, zero is returned; The arrays of indexes are undefined after that. On error, -1 is returned.

Errors: On error, the function returns -1, and Errors are reported in `LinuxError` :

SYS_EBADF An invalid descriptor was specified in one of the sets.

SYS_EINTR A non blocked signal was caught.

SYS_EINVAL `N` is negative or too big.

SYS_ENOMEM `Select` was unable to allocate memory for its internal tables.

See also: `SelectText` ([219](#)), `GetFS` ([198](#)), `FD_ZERO` ([184](#)), `FD_Clr` ([184](#)), `FD_Set` ([185](#)), `FD_IsSet` ([185](#))

Listing: `linuxex/ex33.pp`

Program `Example33;`

{ Program to demonstrate the Select function . }

Uses `linux;`

Var `FDS : FDSet;`

begin

`FD_Zero (FDS);`

`FD_Set (0, FDS);`

`Writeln ( ' Press_the_<ENTER>_to_continue_the_program.' );`

{ Wait until File descriptor 0 (= Input) changes }

`Select (1, @FDS, nil, nil, nil);`

{ Get rid of <ENTER> in buffer }

`readln;`

`Writeln ( ' Press_<ENTER>_key_in_less_than_2_seconds...' );`

`FD_Zero (FDS);`

`FD_Set (0, FDS);`

`if Select (1, @FDS, nil, nil, 2000) > 0 then`

`Writeln ( ' Thank_you_!')`

{ FD_ISSET(0, FDS) would be true here. }

`else`

`Writeln ( ' Too_late_!');`

end.

SelectText

Declaration: `Function SelectText ( var T : Text; TimeOut : PTime) : Longint;`

Description: `SelectText` executes the `Select` ([218](#)) call on a file of type `Text`. You can specify a timeout in `TimeOut`. The `SelectText` call determines itself whether it should check for read or write, depending on how the file was opened : With `Reset` it is checked for reading, with `Rewrite` and `Append` it is checked for writing.

Errors: See [Select \(218\)](#). `SYS_EBADF` can also mean that the file wasn't opened.

See also: [Select \(218\)](#), [GetFS \(198\)](#)

SetPriority

Declaration: `Function SetPriority (Which,Who,Prio : Integer) : Integer;`

Description: `SetPriority` sets the priority with which a process is running. Which process(es) is determined by the `Which` and `Who` variables. `Which` can be one of the pre-defined `Prio_Process`, `Prio_PGrp`, `Prio_User`, in which case `Who` is the process ID, Process group ID or User ID, respectively. `Prio` is a value in the range -20 to 20.

Errors: Error checking must be done on `LinuxError`, since a priority can be negative.

sys_esrchNo process found using `which` and `who`.

sys_einval`Which` was not one of `Prio_Process`, `Prio_Grp` or `Prio_User`.

sys_epermA process was found, but neither its effective or real user ID match the effective user ID of the caller.

sys_eaccessA non-superuser tried to a priority increase.

See also: [GetPriority \(200\)](#), [Nice \(212\)](#), [Setpriority \(2\)](#)

For an example, see [Nice \(212\)](#).

Shell

Declaration: `Function Shell (Command : String) : Longint;`

Description: `Shell` invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command, or 127 if it could not complete the [Fork \(194\)](#) or [Execve \(182\)](#) calls.

Errors: Errors are reported in `LinuxError`.

See also: [POpen \(214\)](#), [Fork \(194\)](#), [Execve \(182\)](#), [system \(3\)](#)

Listing: `linuxex/ex56.pp`

```
program example56;

uses linux;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  Writeln ( ' Output_of_ls_-l_*.pp' );
  S:= Shell ( ' ls_-l_*.pp' );
  Writeln ( ' Command_exited_wwith_status_:',S);
end.
```

SigAction

Declaration: Procedure SigAction (Signum : Integer; Var Act,OldAct : PSigActionRec);

Description: Changes the action to take upon receipt of a signal. Act and OldAct are pointers to a SigActionRec record. SigNum specifies the signal, and can be any signal except **SIGKILL** or **SIGSTOP**. If Act is non-nil, then the new action for signal SigNum is taken from it. If OldAct is non-nil, the old action is stored there. Sa_Handler may be SIG_DFL for the default action or SIG_IGN to ignore the signal. Sa_Mask Specifies which signals should be ignored during the execution of the signal handler. Sa_Flags Specifies a series of flags which modify the behaviour of the signal handler. You can 'or' none or more of the following :

SA_NOCLDSTOPIf signum is **SIGCHLD** do not receive notification when child processes stop.

SA_ONESHOT or **SA_RESETHAND**Restore the signal action to the default state once the signal handler has been called.

SA_RESTARTFor compatibility with BSD signals.

SA_NOMASK or **SA_NODEFER**Do not prevent the signal from being received from within its own signal handler.

Errors: LinuxError is used to report errors.

sys_einvalan invalid signal was specified, or it was **SIGKILL** or **SIGSTOP**.

sys_efaultAct, OldAct point outside this process address space

sys_eintrSystem call was interrupted.

See also: SigProcMask (222), SigPending (222), SigSuspend (223), Kill (206), Sigaction (2)

Listing: linuxex/ex57.pp

Program example57;

{ Program to demonstrate the SigAction function .}

```
{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}
```

uses Linux;

Var

oa, na : PSigActionRec;

Procedure DoSig(sig : Longint); **cdecl**;

begin

writeln('Receiving_signal :_', sig);

end;

begin

new(na);

new(oa);

na^.Handler := @DoSig;

na^.Sa_Mask := 0;

na^.Sa_Flags := 0;

```
na^. Sa_Restorer := Nil ;
SigAction ( SigUshr1 , na , oa );
if LinuxError <> 0 then
  begin
    writeln ( ' Error :_', linuxerror , '.' );
    halt (1);
  end;
WriteLn ( ' Send_USR1_signal_or_press_<ENTER>_to_exit ' );
readln ;
end.
```

SigPending

Declaration: Function SigPending : SigSet;

Description: Sigpending allows the examination of pending signals (which have been raised while blocked.) The signal mask of pending signals is returned.

Errors: None

See also: SigAction (221), SigProcMask (222), SigSuspend (223), Signal (223), Kill (206), Sigpending (2)

SigProcMask

Declaration: Procedure SigProcMask (How : Integer; SSet, OldSSet : PSigSet);

Description: Changes the list of currently blocked signals. The behaviour of the call depends on How :

SIG_BLOCKThe set of blocked signals is the union of the current set and the SSet argument.

SIG_UNBLOCKThe signals in SSet are removed from the set of currently blocked signals.

SIG_SETMASKThe list of blocked signals is set so SSet.

If OldSSet is non-nil, then the old set is stored in it.

Errors: LinuxError is used to report errors.

sys_efaultSSet or OldSSet point to an adress outside the range of the process.

sys_eintrSystem call was interrupted.

See also: SigAction (221), SigPending (222), SigSuspend (223), Kill (206), Sigprocmask (2)

SigRaise

Declaration: Procedure SigRaise(Sig:integer);

Description: SigRaise sends a Sig signal to the current process.

Errors: None.

See also: Kill (206), GetPid (199)

Listing: linuxex/ex65.pp

```
Program example64;

{ Program to demonstrate the SigRaise function.}

uses Linux;

Var
    oa, na : PSigActionRec;

Procedure DoSig( sig : Longint ); cdecl;

begin
    writeln ( ' Receiving_signal :_', sig );
end;

begin
    new(na);
    new(oa);
    na^. handler . sh := @DoSig;
    na^. Sa_Mask := 0;
    na^. Sa_Flags := 0;
    na^. Sa_Restorer := Nil ;
    SigAction ( SigUsrc1 , na, oa );
    if LinuxError <> 0 then
        begin
            writeln ( ' Error :_', linuxerror , ' .' );
            halt (1);
        end;
    Writeln ( ' Sending_USR1_' , sigusr1 , ' )_ signal_to_self .' );
    SigRaise ( sigusr1 );
end.
```

SigSuspend

Declaration: Procedure SigSuspend (Mask : SigSet);

Description: SigSuspend temporarily replaces the signal mask for the process with the one given in Mask, and then suspends the process until a signal is received.

Errors: None

See also: SigAction (221), SigProcMask (222), SigPending (222), Signal (223), Kill (206), SigSuspend (2)

Signal

Declaration: Function Signal (SigNum : Integer; Handler : SignalHandler) : SignalHandler;

Description: Signal installs a new signal handler for signal SigNum. This call has the same functionality as the **SigAction** call. The return value for Signal is the old signal handler, or nil on error.

Errors: LinuxError is used to report errors :

SIG_ERRAn error occurred.

See also: SigAction (221), Kill (206), Signal (2)

Listing: linuxex/ex58.pp

```
Program example58;

{ Program to demonstrate the Signal function .}

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}

uses Linux;

Procedure DoSig(sig : Longint); cdecl;

begin
  writeln ( ' Receiving_signal :_', sig );
end;

begin
  SigNal ( SigUsr1 , @DoSig );
  if LinuxError <> 0 then
    begin
      writeln ( ' Error :_', linuxerror , '.' );
      halt (1);
    end;
  Writeln ( ' Send_USR1_signal _or _press _<ENTER>_to _exit ' );
  readln ;
end.
```

StringToPPchar

Declaration: Function StringToPPChar(Var S:String):ppchar;

Description: StringToPPChar splits the string S in words, replacing any whitespace with zero characters. It returns a pointer to an array of pchars that point to the first letters of the words in S. This array is terminated by a Nil pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of PChar; The caller is responsible for freeing this memory.

This function can be called to create arguments for the various Exec calls.

Errors: None.

See also: CreateShellArgV ([176](#)), Execve ([182](#)), Execv ([182](#))

Listing: linuxex/ex70.pp

```
Program Example70;

{ Program to demonstrate the StringToPPchar function . }

Uses linux;
```

```

Var S : String;
      P : PPChar;
      I : longint;

begin
  // remark whitespace at end.
  S:= ' This_is_a_string_with_words.';
  P:= StringToPPChar (S);
  I:=0;
  While P[I]<> Nil do
    begin
      WriteLn ( ' Word_', i, ' : ', P[I]);
      Inc (I);
    end;
  FreeMem(P, i * SizeOf (Pchar));
end.

```

SymLink

Declaration: `Function SymLink (OldPath, NewPath : pathstr) : Boolean;`

Description: SymLink makes Newpath point to the file in OldPath, which doesn't necessarily exist. The two files DO NOT have the same inode number. This is known as a 'soft' link. The permissions of the link are irrelevant, as they are not used when following the link. Ownership of the file is only checked in case of removal or renaming of the link. The function returns `True` if the call was successful, `False` if the call failed.

Errors: Errors are returned in `LinuxError`.

sys_epermThe filesystem containing oldpath and newpath doesn't support linking files.

sys_eaccessWrite access for the directory containing Newpath is disallowed, or one of the directories in OldPath or NewPath has no search (=execute) permission.

sys_enoentA directory entry in OldPath or NewPath does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdirA directory entry in OldPath or NewPath is not a directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe files are on a read-only filesystem.

sys_eexistNewPath already exists.

sys_eloopOldPath or NewPath has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospcThe device containing NewPath has no room for another entry.

See also: [Link \(208\)](#), [UnLink \(231\)](#), [ReadLink \(215\)](#), [SymLink \(2\)](#)

Listing: linuxex/ex22.pp

Program Example22;

{ Program to demonstrate the SymLink and UnLink functions. }

Uses linux;

Var F : Text;

```

    S : String;

begin
    Assign (F, 'test.txt');
    Rewrite (F);
    Writeln (F, ' This_is_written_to_test.txt ');
    Close(f);
    { new.txt and test.txt are now the same file }
    if not SymLink ('test.txt', 'new.txt') then
        writeln (' Error_when_symlinking_! ');
    { Removing test.txt still leaves new.txt
      Pointing now to a non-existent file ! }
    If not Unlink ('test.txt') then
        Writeln (' Error_when_unlinking_! ');
    Assign (f, 'new.txt');
    { This should fail, since the symbolic link
      points to a non-existent file ! }
    {$i-}
    Reset (F);
    {$i+}
    If IOResult=0 then
        Writeln (' This_shouldn''t_happen ');
    { Now remove new.txt also }
    If not Unlink ('new.txt') then
        Writeln (' Error_when_unlinking_! ');
end.

```

SysInfo

Declaration: Function SysInfo(var Info:TSysinfo):Boolean;

Description: SysInfo returns system information in Info. Returned information in Info includes:

- uptime**Number of seconds since boot.
- loads**1, 5 and 15 minute load averages.
- totalram**total amount of main memory.
- freeram**amount of free memory.
- sharedram**amount of shared memory
- bufferram**amount of memory used by buffers.
- totalswap**total amount of swapspace.
- freeswap**amount of free swapspace.
- procs**number of current processes.

Errors: None.

See also: Uname ([231](#))

Listing: linuxex/ex64.pp

```

program Example64;

{ Example to demonstrate the SysInfo function }

Uses Linux;

```

```

Function Mb(L : Longint) : longint;

begin
  Mb:=L div (1024*1024);
end;

Var Info : TSysInfo;
      D,M,Secs,H : longint;

begin
  If Not SysInfo(Info) then
    Halt(1);
  With Info do
    begin
      D:=Uptime div (3600*24);
      UpTime:=UpTime mod (3600*24);
      h:=uptime div 3600;
      uptime:=uptime mod 3600;
      m:=uptime div 60;
      secs:=uptime mod 60;
      Writeln(' Uptime_',d,' days_',h,' hours_',m,' min_',secs,' s. ');
      Writeln(' Loads_',Loads[1], '/', Loads[2], '/', Loads[3]);
      Writeln(' Total_Ram_',Mb(totalram), ' Mb. ');
      Writeln(' Free_Ram_',Mb(freeram), ' Mb. ');
      Writeln(' Shared_Ram_',Mb(sharedram), ' Mb. ');
      Writeln(' Buffer_Ram_',Mb(bufferram), ' Mb. ');
      Writeln(' Total_Swap_',Mb(totalswap), ' Mb. ');
      Writeln(' Free_Swap_',Mb(freeswap), ' Mb. ');
    end;
end.

```

TCDrain

Declaration: **Function** TCDrain (Fd:longint) : Boolean;

Description: TCDrain waits until all data to file descriptor Fd is transmitted.

The function returns **True** if the call was succesfull, **False** otherwise.

Errors: Errors are reported in LinuxError

See also: **termios** (2)

TCFlow

Declaration: **Function** TCFlow (Fd,Act:longint) : Boolean;

Description: TCFlow suspends/resumes transmission or reception of data to or from the file descriptor Fd, depending on the action Act. This can be one of the following pre-defined values:

TCOOFF suspend reception/transmission,

TCOON resume reception/transmission,

TCIOFF transmit a stop character to stop input from the terminal,

TCION transmit start to resume input from the terminal.

The function returns **True** if the call was succesfull, **False** otherwise.

Errors: Errors are reported in `LinuxError`.

See also: `termios` (2)

TCFlush

Declaration: Function `TCFlush (Fd,QSel:longint) : Boolean;`

Description: `TCFlush` discards all data sent or received to/from file descriptor `fd`. `QSel` indicates which queue should be discard. It can be one of the following pre-defined values :

TCIFLUSH input,

TCOFLUSH output,

TCIOFLUSH both input and output.

The function returns `True` if the call was succesfull, `False` otherwise.

Errors: Errors are reported in `LinuxError`.

See also: `termios` (2)

TCGetAttr

Declaration: Function `TCGetAttr (fd:longint;var tios:TermIOS) : Boolean;`

Description: `TCGetAttr` gets the terminal parameters from the terminal referred to by the file descriptor `fd` and returns them in a `TermIOS` structure `tios`. The function returns `True` if the call was succesfull, `False` otherwise.

Errors: Errors are reported in `LinuxError`

See also: `TCSetAttr` ([229](#)), `termios` (2)

Listing: `linuxex/ex55.pp`

```
Program Example55;

uses Linux;

{ Program to demonstrate the TCGetAttr/TCSetAttr/CFMakeRaw functions. }

procedure ShowTermios(var tios:Termios);
begin
  WriteLn(' Input_Flags:_$', hexstr(tios.c_iflag,8)+#13);
  WriteLn(' Output_Flags:_$', hexstr(tios.c_oflag,8));
  WriteLn(' Line_Flags:_$', hexstr(tios.c_lflag,8));
  WriteLn(' Control_Flags:_$', hexstr(tios.c_cflag,8));
end;

var
  oldios,
  tios : Termios;
begin
  WriteLn(' Old_attributes: ');
  TCGetAttr(1, tios);
  ShowTermios(tios);
  oldios := tios;
```

```
    WriteLn ( ' Setting _raw_terminal _mode' );
    CFMakeRaw( tios );
    TCSetAttr (1, TCSANOW, tios );
    WriteLn ( ' Current _attributes :' );
    TCGetAttr (1, tios );
    ShowTermios( tios );
    TCSetAttr (1, TCSANOW, oldios );
end.
```

TCGetPGrp

Declaration: Function TCGetPGrp (Fd:longint;var Id:longint) : boolean;

Description: TCGetPGrp returns the process group ID of a foreground process group in Id The function returns True if the call was succesfull, False otherwise

Errors: Errors are reported in LinuxError

See also: termios (2)

TCSendBreak

Declaration: Function TCSendBreak (Fd,Duration:longint) : Boolean;

Description: TCSendBreak Sends zero-valued bits on an asynchrone serial connection decsribed by file-descriptor Fd, for duration Duration. The function returns True if the action was performed successfully, False otherwise.

Errors: Errors are reported in LinuxError.

See also: termios (2)

TCSetAttr

Declaration: Function TCSetAttr (Fd:longint;OptAct:longint;var Tios:TermIOS) : Boolean;

Description: TCSetAttr Sets the terminal parameters you specify in a TermIOS structure Tios for the terminal referred to by the file descriptor Fd. OptAct specifies an optional action when the set need to be done, this could be one of the following pre-defined values:

TCSANOW set immediately.

TCSADRAIN wait for output.

TCSAFLUSH wait for output and discard all input not yet read.

The function Returns True if the call was succesfull, False otherwise.

Errors: Errors are reported in LinuxError.

See also: TCGetAttr ([228](#)), termios (2)

For an example, see TCGetAttr ([228](#)).

TCSetsGrp

Declaration: Function TCSetsGrp (Fd,Id:longint) : boolean;

Description: TCSetsGrp Sets the Process Group Id to Id. The function returns True if the call was successful, False otherwise.

Errors: Errors are returned in LinuxError.

See also: TCGetPGrp (229), termios (2)

For an example, see TCGetPGrp (229).

TTYName

Declaration: Function TTYName (var f) : String;

Description: Returns the name of the terminal pointed to by f. f must be a terminal. f can be of type:

- 1.longint for file handles;
- 2.Text for text variables such as input etc.

Errors: Returns an empty string in case of an error. Linuxerror may be set to indicate what error occurred, but this is uncertain.

See also: IsATTY (204),IOctl (203)

TellDir

Declaration: Function TellDir (p:pdir) : longint;

Description: TellDir returns the current location in the directory structure pointed to by p. It returns -1 on failure.

Errors: Errors are returned in LinuxError.

See also: CloseDir (176), ReadDir (215), SeekDir (218), OpenDir (213), telldir (3)

For an example, see OpenDir (213).

Umask

Declaration: Function Umask (Mask : Integer) : Integer;

Description: Change the file creation mask for the current user to Mask. The current mask is returned.

Errors: None

See also: Chmod (173), Umask (2)

Listing: linuxex/ex27.pp

Program Example27;

{ Program to demonstrate the Umask function . }

Uses linux ;


```
begin
  Writeln ( ' Old_Umask_was_:', Umask( Octal (111)));
  Writeln ( ' New_Umask_is_:', Octal (111));
end.
```

Uname

Declaration: Procedure Uname (var unamerec:utsname);

Description: Uname gets the name and configuration of the current LINUX kernel, and returns it in unamerec.

Errors: LinuxError is used to report errors.

See also: GetHostName ([199](#)), GetDomainName ([196](#)), uname (2)

UnLink

Declaration: Function UnLink (Var Path) : Boolean;

Description: UnLink decreases the link count on file Path. Path can be of type PathStr or PChar. If the link count is zero, the file is removed from the disk. The function returns True if the call was succesfull, False if the call failed.

Errors: Errors are returned in LinuxError.

sys_eaccessYou have no write access right in the directory containing Path, or you have no search permission in one of the directory components of Path.

sys_epermThe directory containing pathname has the sticky-bit set and the process's effective uid is neither the uid of the file to be deleted nor that of the directory containing it.

sys_enoentA component of the path doesn't exist.

sys_enotdirA directory component of the path is not a directory.

sys_eisdirPath refers to a directory.

sys_enomemInsufficient kernel memory.

sys_erofsPath is on a read-only filesystem.

See also: Link ([208](#)), SymLink ([225](#)), UnLink (2)

For an example, see Link ([208](#)).

Utime

Declaration: Function Utime (path : pathstr; utim : utimbuf) : Boolean;

Description: Utime sets the access and modification times of a file. the utimbuf record contains 2 fields, actime, and modtime, both of type Longint. They should be filled with an epoch-like time, specifying, respectively, the last access time, and the last modification time. For some filesystem (most notably, FAT), these times are the same.

Errors: Errors are returned in LinuxError.

sys_eaccessOne of the directories in Path has no search (=execute) permission.

sys_enoentA directory entry in Path does not exist or is a symbolic link pointing to a non-existent directory.

Other errors may occur, but aren't documented.

See also: [GetEpochTime \(197\)](#), [Chown \(172\)](#), [Access \(167\)](#), [utime \(\) 2](#)

Listing: linuxex/ex25.pp

Program Example25;

{ Program to demonstrate the UTime function . }

Uses linux ;

Var utim : utimbuf ;
year , month , day , hour , minute , second : Word ;

begin

{ Set access and modification time of executable source }
GetTime (hour , minute , second) ;
GetDate (year , month , day) ;
utim . actime := LocalToEpoch (year , month , day , hour , minute , second) ;
utim . modtime := utim . actime ;
if not Utime (' ex25 . pp ' , utim) **then**
 writeln (' Call _to_ UTime _failed _ ! ')
else
 begin
 Write (' Set _access_ and _modification _times_ to _ : _ ') ;
 Write (Hour : 2 , ' : ' , minute : 2 , ' : ' , second , ' , _ ') ;
 Writeln (Day : 2 , ' / ' , month : 2 , ' / ' , year : 4) ;
 end ;

end.

WaitPid

Declaration: Function WaitPid (Pid : longint; Status : pointer; Options : Longint)
: Longint;

Description: WaitPid waits for a child process with process ID Pid to exit. The value of Pid can be one of the following:

Pid < -1 Causes WaitPid to wait for any child process whose process group ID equals the absolute value of pid.

Pid = -1 Causes WaitPid to wait for any child process.

Pid = 0 Causes WaitPid to wait for any child process whose process group ID equals the one of the calling process.

Pid > 0 Causes WaitPid to wait for the child whose process ID equals the value of Pid.

The Options parameter can be used to specify further how WaitPid behaves:

WNOHANG Causes Waitpid to return immediately if no child has exited.

WUNTRACED Causes WaitPid to return also for children which are stopped, but whose status has not yet been reported.

__WCLONE Causes WaitPid also to wait for threads created by the [Clone \(174\)](#) call.

Upon return, it returns the exit status of the process, or -1 in case of failure.

Errors: Errors are returned in LinuxError.

See also: Fork ([194](#)), Execve ([182](#)), waitpid ([2](#))

For an example, see Fork ([194](#)).

WritePort

Declaration: Procedure WritePort (Port : Longint; Value : Byte); Procedure WritePort (Port : Longint; Value : Word); Procedure WritePort (Port : Longint; Value : Longint);

Description: WritePort writes Value – 1 byte, Word or longint – to port Port.

Note: You need permission to write to a port. This permission can be set with root permission with the IOperm call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: IOperm ([204](#)), WritePortB ([233](#)), WritePortL ([233](#)), WritePortW ([234](#)), ReadPortB ([217](#)), ReadPortL ([217](#)), ReadPortW ([218](#))

WritePortB

Declaration: Procedure WritePortB (Port : Longint; Value : Byte); Procedure WritePortB (Port : Longint; Var Buf; Count: longint);

Description: The first form of WritePortB writes 1 byte to port Port. The second form writes Count bytes from Buf to port Port.

Note: You need permission to write to a port. This permission can be set with root permission with the IOperm call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: IOperm ([204](#)), WritePort ([233](#)), WritePortL ([233](#)), WritePortW ([234](#)), ReadPortB ([217](#)), ReadPortL ([217](#)), ReadPortW ([218](#))

WritePortL

Declaration: Procedure WritePortL (Port : Longint; Value : Longint); Procedure WritePortL (Port : Longint; Var Buf; Count: longint);

Description: The first form of WritePortB writes 1 byte to port Port. The second form writes Count bytes from Buf to port Port.

Note: You need permission to write to a port. This permission can be set with root permission with the IOperm call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: IOperm ([204](#)), WritePort ([233](#)), WritePortB ([233](#)), WritePortW ([234](#)), ReadPortB ([217](#)), ReadPortL ([217](#)), ReadPortW ([218](#))

WritePortW

Declaration: Procedure WritePortW (Port : Longint; Var Buf; Count: longint); Procedure WritePortW (Port : Longint; Value : Word);

Description: The first form of WritePortB writes 1 byte to port Port. The second form writes Count bytes from Buf to port Port.

Note: You need permission to write to a port. This permission can be set with root permission with the IOperm call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: IOperm ([204](#)), WritePort ([233](#)), WritePortL ([233](#)), WritePortB ([233](#)), ReadPortB ([217](#)), ReadPortL ([217](#)), ReadPortW ([218](#))

Chapter 12

The MATH unit

This chapter describes the `math` unit. The `math` unit was initially written by Florian Klaempfl. It provides mathematical functions which aren't covered by the `system` unit.

This chapter starts out with a definition of all types and constants that are defined, after which an overview is presented of the available functions, grouped by category, and the last part contains a complete explanation of each function.

The following things must be taken into account when using this unit:

1. This unit is compiled in Object Pascal mode so all `integers` are 32 bit.
2. Some overloaded functions exist for data arrays of integers and floats. When using the address operator (`@`) to pass an array of data to such a function, make sure the address is typecasted to the right type, or turn on the 'typed address operator' feature. failing to do so, will cause the compiler not be able to decide which function you want to call.

12.1 Constants and types

The following types are defined in the `math` unit:

Type

```
Float = Extended;  
PFloat = ^Float
```

All calculations are done with the `Float` type. This allows to recompile the unit with a different float type to obtain a desired precision. The pointer type is used in functions that accept an array of values of arbitrary length.

Type

```
TPaymentTime = (PTEndOfPeriod, PTStartOfPeriod);
```

`TPaymentTime` is used in the financial calculations.

Type

```
EInvalidArgument = Class(EMathError);
```

The `EInvalidArgument` exception is used to report invalid arguments.

12.2 Function list by category

What follows is a listing of the available functions, grouped by category. For each function there is a reference to the page where you can find the function.

Min/max determination

Functions to determine the minimum or maximum of numbers:

Name	Description	Page
max	Maximum of 2 values	249
maxIntValue	Maximum of an array of integer values	250
maxvalue	Maximum of an array of values	250
min	Minimum of 2 values	253
minIntValue	Minimum of an array of integer values	253
minvalue	Minimum of an array of values	254

Angle conversion

Name	Description	Page
cycleto rad	convert cycles to radians	242
degtograd	convert degrees to grads	243
degtorad	convert degrees to radians	243
gradtodeg	convert grads to degrees	245
gradtorad	convert grads to radians	245
radto cycle	convert radians to cycles	258
radtodeg	convert radians to degrees	258
radtograd	convert radians to grads	259

Trigonometric functions

Name	Description	Page
arccos	calculate reverse cosine	238
arcsin	calculate reverse sine	239
arctan2	calculate reverse tangent	240
cotan	calculate cotangent	242
sincos	calculate sine and cosine	260
tan	calculate tangent	264

Hyperbolic functions

Name	Description	Page
arcosh	calculate reverse hyperbolic cosine	238
arsinh	calculate reverse hyperbolic sine	240
artanh	calculate reverse hyperbolic tangent	241
cosh	calculate hyperbolic cosine	242
sinh	calculate hyperbolic sine	261
tanh	calculate hyperbolic tangent	264

Exponential and logarithmic functions

Name	Description	Page
intpower	Raise float to integer power	246
ldexp	Calculate $2^p x$	247
lnxp1	calculate $\log(x+1)$	247
log10	calculate 10-base log	248
log2	calculate 2-base log	248
logn	calculate N-base log	249
power	raise float to arbitrary power	257

Number converting

Name	Description	Page
ceil	Round to infinity	241
floor	Round to minus infinity	244
frexp	Return mantissa and exponent	244

Statistical functions

Name	Description	Page
mean	Mean of values	251
meanandstddev	Mean and standard deviation of values	252
momentskewkurtosis	Moments, skew and kurtosis	255
popnstddev	Population standarddeviation	256
popnvariance	Population variance	257
randg	Gaussian distributed random value	259
stddev	Standard deviation	261
sum	Sum of values	262
sumofsquares	Sum of squared values	262

sumsandsquares	Sum of values and squared values	263
totalvariance	Total variance of values	265
variance	variance of values	265

Geometrical functions

Name	Description	Page
hypot	Hypotenuse of triangle	246
norm	Euclidian norm	255

12.3 Functions and Procedures

arccos

Declaration: Function `arccos(x : float) : float;`

Description: `Arccos` returns the inverse cosine of its argument `x`. The argument `x` should lie between -1 and 1 (borders included).

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arcsin` ([239](#)), `arcosh` ([238](#)), `arsinh` ([240](#)), `artanh` ([241](#))

Listing: `mathex/ex1.pp`

```
Program Example1;

{ Program to demonstrate the arccos function . }

Uses math;

Procedure WriteRadDeg(X : float );

begin
  WriteLn (X:8:5, ' rad = ', radtodeg (x):8:5, ' degrees . ' )
end;

begin
  WriteRadDeg ( arccos (1));
  WriteRadDeg ( arccos ( sqrt (3)/2));
  WriteRadDeg ( arccos ( sqrt (2)/2));
  WriteRadDeg ( arccos (1/2));
  WriteRadDeg ( arccos (0));
  WriteRadDeg ( arccos (-1));
end.
```

arcosh

Declaration: Function `arcosh(x : float) : float;` Function `arccosh(x : float) : float;`

Description: `Arcosh` returns the inverse hyperbolic cosine of its argument `x`. The argument `x` should be larger than 1.

The `arccosh` variant of this function is supplied for Delphi compatibility.

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `cosh` (242), `sinh` (261), `arcsin` (239), `arsinh` (240), `artanh` (241), `tanh` (264)

Listing: `mathex/ex3.pp`

```
Program Example3;

{ Program to demonstrate the arcosh function . }

Uses math;

begin
    Writeln ( arcosh (1));
    Writeln ( arcosh (2));
end.
```

arcsin

Declaration: `Function arcsin(x : float) : float;`

Description: `Arcsin` returns the inverse sine of its argument `x`. The argument `x` should lie between -1 and 1.

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arccos` (238), `arcosh` (238), `arsinh` (240), `artanh` (241)

Listing: `mathex/ex2.pp`

```
Program Example1;

{ Program to demonstrate the arcsin function . }

Uses math;

Procedure WriteRadDeg(X : float );

begin
    Writeln (X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees . ' )
end;

begin
    WriteRadDeg ( arcsin (1));
    WriteRadDeg ( arcsin ( sqrt (3)/2));
    WriteRadDeg ( arcsin ( sqrt (2)/2));
    WriteRadDeg ( arcsin (1/2));
    WriteRadDeg ( arcsin (0));
    WriteRadDeg ( arcsin (-1));
end.
```

arctan2

Declaration: `Function arctan2(x,y : float) : float;`

Description: `arctan2` calculates `arctan(y/x)`, and returns an angle in the correct quadrant. The returned angle will be in the range $-\pi$ to π radians. The values of `x` and `y` must be between -2^{64} and 2^{64} , moreover `x` should be different from zero.

On Intel systems this function is implemented with the native intel `fpatan` instruction.

Errors: If `x` is zero, an overflow error will occur.

See also: `arccos` ([238](#)), `arcosh` ([238](#)), `arsinh` ([240](#)), `artanh` ([241](#))

Listing: `mathex/ex6.pp`

```
Program Example6;

{ Program to demonstrate the arctan2 function . }

Uses math;

Procedure WriteRadDeg (X : float );

begin
  WriteLn (X:8:5, ' rad = ', radtodeg (x):8:5, ' degrees . ' )
end;

begin
  WriteRadDeg ( arctan2 (1,1));
end.
```

arsinh

Declaration: `Function arsinh(x : float) : float; Function arcsinh(x : float) : float;`

Description: `arsinh` returns the inverse hyperbolic sine of its argument `x`.

The `arcsinh` variant of this function is supplied for Delphicompatibility.

Errors: None.

See also: `arcosh` ([238](#)), `arccos` ([238](#)), `arcsin` ([239](#)), `artanh` ([241](#))

Listing: `mathex/ex4.pp`

```
Program Example4;

{ Program to demonstrate the arsinh function . }

Uses math;

begin
  WriteLn ( arsinh (0));
  WriteLn ( arsinh (1));
end.
```

artanh

Declaration: `Function artanh(x : float) : float; Function arctanh(x : float) : float;`

Description: `artanh` returns the inverse hyperbolic tangent of its argument `x`, where `x` should lie in the interval `[-1,1]`, borders included.

The `arctanh` variant of this function is supplied for Delphi compatibility.

Errors: In case `x` is not in the interval `[-1,1]`, an `EInvalidArgument` exception is raised.

See also: `arcosh` ([238](#)), `arccos` ([238](#)), `arcsin` ([239](#)), `artanh` ([241](#))

Errors:

See also:

Listing: `mathex/ex5.pp`

```
Program Example5;

{ Program to demonstrate the artanh function . }

Uses math;

begin
    Writeln( artanh (0));
    Writeln( artanh (0.5));
end.
```

ceil

Declaration: `Function ceil(x : float) : longint;`

Description: `Ceil` returns the lowest integer number greater than or equal to `x`. The absolute value of `x` should be less than `maxint`.

Errors: If the absolute value of `x` is larger than `maxint`, an overflow error will occur.

See also: `floor` ([244](#))

Listing: `mathex/ex7.pp`

```
Program Example7;

{ Program to demonstrate the Ceil function . }

Uses math;

begin
    Writeln( Ceil (-3.7)); // should be -3
    Writeln( Ceil (3.7));  // should be 4
    Writeln( Ceil (-4.0)); // should be -4
end.
```

cosh

Declaration: Function cosh(x : float) : float;

Description: Cosh returns the hyperbolic cosine of its argument x.

Errors: None.

See also: arcosh ([238](#)), sinh ([261](#)), arsinh ([240](#))

Listing: mathex/ex8.pp

```
Program Example8;

{ Program to demonstrate the cosh function . }

Uses math;

begin
  Writeln ( Cosh (0));
  Writeln ( Cosh (1));
end.
```

cotan

Declaration: Function cotan(x : float) : float;

Description: Cotan returns the cotangent of its argument x. x should be different from zero.

Errors: If x is zero then a overflow error will occur.

See also: tanh ([264](#))

Listing: mathex/ex9.pp

```
Program Example9;

{ Program to demonstrate the cotan function . }

Uses math;

begin
  writeln ( cotan ( pi / 2 ));
  Writeln ( cotan ( pi / 3 ));
  Writeln ( cotan ( pi / 4 ));
end.
```

cycletorad

Declaration: Function cycletorad(cycle : float) : float;

Description: Cycletorad transforms its argument cycle (an angle expressed in cycles) to radians. (1 cycle is 2π radians).

Errors: None.

See also: degtograd ([243](#)), degtorad ([243](#)), radtodeg ([258](#)), radtograd ([259](#)), radtcycle ([258](#))

Listing: mathex/ex10.pp

```
Program Example10;  
  
{ Program to demonstrate the cycletorad function . }  
  
Uses math;  
  
begin  
  writeln(cos(cycletorad (1/6))); // Should print 1/2  
  writeln(cos(cycletorad (1/8))); // should be sqrt(2)/2  
end.
```

degtograd

Declaration: Function degtograd(deg : float) : float;

Description: Degtograd transforms it's argument deg (an angle in degrees) to grads.
(90 degrees is 100 grad.)

Errors: None.

See also: cycletorad ([242](#)), degtorad ([243](#)), radtodeg ([258](#)), radtograd ([259](#)), radtcycle ([258](#))

Listing: mathex/ex11.pp

```
Program Example11;  
  
{ Program to demonstrate the degtograd function . }  
  
Uses math;  
  
begin  
  writeln(degtograd (90));  
  writeln(degtograd (180));  
  writeln(degtograd (270))  
end.
```

degtorad

Declaration: Function degtorad(deg : float) : float;

Description: Degtorad converts it's argument deg (an angle in degrees) to radians.
(pi radians is 180 degrees)

Errors: None.

See also: cycletorad ([242](#)), degtograd ([243](#)), radtodeg ([258](#)), radtograd ([259](#)), radtcycle ([258](#))

Listing: mathex/ex12.pp

```
Program Example12;  
  
{ Program to demonstrate the degtorad function . }
```

Uses math;

```
begin
  writeln (degtorad (45));
  writeln (degtorad (90));
  writeln (degtorad (180));
  writeln (degtorad (270));
  writeln (degtorad (360));
end.
```

floor

Declaration: Function floor(x : float) : longint;

Description: Floor returns the largest integer smaller than or equal to x. The absolute value of x should be less than maxint.

Errors: If x is larger than maxint, an overflow will occur.

See also: ceil ([241](#))

Listing: mathex/ex13.pp

```
Program Example13;

{ Program to demonstrate the floor function . }

Uses math;

begin
  Writeln (Ceil (-3.7)); // should be -4
  Writeln (Ceil (3.7));  // should be 3
  Writeln (Ceil (-4.0)); // should be -4
end.
```

frexp

Declaration: Procedure frexp(x : float; var mantissa, exponent : float);

Description: Frexp returns the mantissa and exponent of it's argument x in mantissa and exponent.

Errors: None

See also:

Listing: mathex/ex14.pp

```
Program Example14;

{ Program to demonstrate the frexp function . }

Uses math;

Procedure dofrep (Const X : extended);

var man : extended;
```

```

    exp: integer;

begin
    man:=0;
    exp:=0;
    frexp(x, man, exp);
    write(x, ' has ');
    Writeln(' mantissa ', man, ' and exponent ', exp);
end;

begin
//    dofrep(1.00);
    dofrep(1.02e-1);
    dofrep(1.03e-2);
    dofrep(1.02e1);
    dofrep(1.03e2);
end.

```

gradtodeg

Declaration: Function gradtodeg(grad : float) : float;

Description: Gradtodeg converts its argument grad (an angle in grads) to degrees.

(100 grad is 90 degrees)

Errors: None.

See also: cycletorad ([242](#)), degtograd ([243](#)), radtodeg ([258](#)), radtograd ([259](#)), radtcycle ([258](#)), gradtorad ([245](#))

Listing: mathex/ex15.pp

```

Program Example15;

{ Program to demonstrate the gradtodeg function . }

Uses math;

begin
    writeln (gradtodeg (100));
    writeln (gradtodeg (200));
    writeln (gradtodeg (300));
end.

```

gradtorad

Declaration: Function gradtorad(grad : float) : float;

Description: Gradtorad converts its argument grad (an angle in grads) to radians.

(200 grad is pi degrees).

Errors: None.

See also: cycletorad ([242](#)), degtograd ([243](#)), radtodeg ([258](#)), radtograd ([259](#)), radtcycle ([258](#)), gradtodeg ([245](#))

Listing: mathex/ex16.pp

```
Program Example16;  
  
{ Program to demonstrate the gradtorad function . }  
  
Uses math;  
  
begin  
  writeln ( gradtorad (100));  
  writeln ( gradtorad (200));  
  writeln ( gradtorad (300));  
end.
```

hypot

Declaration: Function hypot(x,y : float) : float;

Description: Hypot returns the hypotenuse of the triangle where the sides adjacent to the square angle have lengths x and y.

The function uses Pythagoras' rule for this.

Errors: None.

See also:

Listing: mathex/ex17.pp

```
Program Example17;  
  
{ Program to demonstrate the hypot function . }  
  
Uses math;  
  
begin  
  Writeln (hypot (3,4)); // should be 5  
end.
```

intpower

Declaration: Function intpower(base : float;exponent : longint) : float;

Description: Intpower returns base to the power exponent, where exponent is an integer value.

Errors: If base is zero and the exponent is negative, then an overflow error will occur.

See also: [power \(257\)](#)

Listing: mathex/ex18.pp

```
Program Example18;  
  
{ Program to demonstrate the intpower function . }  
  
Uses math;
```



```
Procedure DoIntpower (X : extended; Pow : Integer);  
  
begin  
  writeln (X:8:4, '^', Pow:2, ' = ', intpower (X, pow):8:4);  
end;  
  
begin  
  dointpower (0.0,0);  
  dointpower (1.0,0);  
  dointpower (2.0,5);  
  dointpower (4.0,3);  
  dointpower (2.0,-1);  
  dointpower (2.0,-2);  
  dointpower (-2.0,4);  
  dointpower (-4.0,3);  
end.
```

Idexp

Declaration: Function Idexp(x : float;p : longint) : float;

Description: Idexp returns $2^p x$.

Errors: None.

See also: Inxp1 ([247](#)), log10 ([248](#)), log2 ([248](#)), logn ([249](#))

Listing: mathex/ex19.pp

```
Program Example19;  
  
{ Program to demonstrate the Idexp function. }  
  
Uses math;  
  
begin  
  writeln (Idexp (2,4):8:4);  
  writeln (Idexp (0.5,3):8:4);  
end.
```

Inxp1

Declaration: Function Inxp1(x : float) : float;

Description: Inxp1 returns the natural logarithm of 1+X. The result is more precise for small values of X. x should be larger than -1.

Errors: If $x \leq -1$ then an `EInvalidArgument` exception will be raised.

See also: Idexp ([247](#)), log10 ([248](#)), log2 ([248](#)), logn ([249](#))

Listing: mathex/ex20.pp

```
Program Example20;
```

```
{ Program to demonstrate the lnxp1 function . }
```

```
Uses math;
```

```
begin
```

```
  writeln (lnxp1 (0));  
  writeln (lnxp1 (0.5));  
  writeln (lnxp1 (1));
```

```
end.
```

log10

Declaration: Function log10(x : float) : float;

Description: Log10 returns the 10-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: Idexp ([247](#)), lnxp1 ([247](#)), log2 ([248](#)), logn ([249](#))

Listing: mathex/ex21.pp

Program Example21;

```
{ Program to demonstrate the log10 function . }
```

```
Uses math;
```

```
begin
```

```
  Writeln (Log10 (10):8:4);  
  Writeln (Log10 (100):8:4);  
  Writeln (Log10 (1000):8:4);  
  Writeln (Log10 (1):8:4);  
  Writeln (Log10 (0.1):8:4);  
  Writeln (Log10 (0.01):8:4);  
  Writeln (Log10 (0.001):8:4);
```

```
end.
```

log2

Declaration: Function log2(x : float) : float;

Description: Log2 returns the 2-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: Idexp ([247](#)), lnxp1 ([247](#)), log10 ([248](#)), logn ([249](#))

Listing: mathex/ex22.pp

Program Example22;

```
{ Program to demonstrate the log2 function . }
```

```
Uses math;
```

```
begin
  Writeln (Log2 (2):8:4);
  Writeln (Log2 (4):8:4);
  Writeln (Log2 (8):8:4);
  Writeln (Log2 (1):8:4);
  Writeln (Log2 (0.5):8:4);
  Writeln (Log2 (0.25):8:4);
  Writeln (Log2 (0.125):8:4);
end.
```

logn

Declaration: Function logn(n,x : float) : float;

Description: Logn returns the n-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: ldexp ([247](#)), lnxp1 ([247](#)), log10 ([248](#)), log2 ([248](#))

Listing: mathex/ex23.pp

```
Program Example23;

{ Program to demonstrate the logn function . }

Uses math;

begin
  Writeln (Logn (3,4):8:4);
  Writeln (Logn (2,4):8:4);
  Writeln (Logn (6,9):8:4);
  Writeln (Logn (exp(1), exp(1)):8:4);
  Writeln (Logn (0.5,1):8:4);
  Writeln (Logn (0.25,3):8:4);
  Writeln (Logn (0.125,5):8:4);
end.
```

max

Declaration: Function max(Int1,Int2:Cardinal):Cardinal; Function max(Int1,Int2:Integer):Integer;

Description: Max returns the maximum of Int1 and Int2.

Errors: None.

See also: min ([253](#)), maxIntValue ([250](#)), maxvalue ([250](#))

Listing: mathex/ex24.pp

```
Program Example24;

{ Program to demonstrate the max function . }

Uses math;
```

```
Var
  A,B : Cardinal;

begin
  A:=1; b:=2;
  writeln (max(a,b));
end.
```

maxIntValue

Declaration: function MaxIntValue(const Data: array of Integer): Integer;

Description: MaxIntValue returns the largest integer out of the Data array.

This function is provided for Delphicompatibility, use the maxvalue (250) function instead.

Errors: None.

See also: maxvalue (250), minvalue (254), minIntValue (253)

Listing: mathex/ex25.pp

```
Program Example25;

{ Program to demonstrate the MaxIntValue function . }

{ Make sure integer is 32 bit }
{$mode objfpc}

Uses math;

Type
  TExArray = Array[1..100] of Integer;

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=1 to 100 do
    ExArray[I]:=Random(I)-Random(100);
  Writeln (MaxIntValue ( ExArray ));
end.
```

maxvalue

Declaration: Function maxvalue(const data : array of float) : float; Function maxvalue(const data : array of Integer) : Integer; Function maxvalue(const data : PFloat; Const N : Integer) : float; Function maxvalue(const data : PInteger; Const N : Integer) : Integer;

Description: Maxvalue returns the largest value in the data array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of N integer or float values.

Errors: None.

See also: [maxIntValue \(250\)](#), [minvalue \(254\)](#), [minIntValue \(253\)](#)

Listing: mathex/ex26.pp

Program Example26;

{ Program to demonstrate the MaxValue function . }

{ Make sure integer is 32 bit }
{ \$mode objfpc }

Uses math;

Type

TExFloatArray = **Array**[1..100] **of** Float;
 TExIntArray = **Array**[1..100] **of** Integer;

Var

I : Integer;
 ExFloatArray : TExFloatArray;
 ExIntArray : TExIntArray;
 AFloatArray : PFloat;
 AIntArray : PInteger;

begin

Randomize;
 AFloatArray := @ExFloatArray[1];
 AIntArray := @ExIntArray[1];
for I:=1 **to** 100 **do**
 ExFloatArray[I] := (Random-~~Random~~)*100;
for I:=1 **to** 100 **do**
 ExIntArray[I] := Random(I)-Random(100);
Writeln ('Max_Float _____', MaxValue(ExFloatArray):8:4);
Writeln ('Max_Float ____ (b) _____', MaxValue(AFloatArray ,100):8:4);
Writeln ('Max_Integer _____', MaxValue(ExIntArray):8);
Writeln ('Max_Integer ____ (b) _____', MaxValue(AIntArray ,100):8);

end.

mean

Declaration: Function mean(const data : array of float) : float; Function mean(const data : PFloat; Const N : longint) : float;

Description: Mean returns the average value of data.

The second form accepts a pointer to an array of N values.

Errors: None.

See also: [meanandstddev \(252\)](#), [momentskewkurtosis \(255\)](#), [sum \(262\)](#)

Listing: mathex/ex27.pp

Program Example27;

{ Program to demonstrate the Mean function . }

Uses math;

Type

TExArray = **Array**[1..100] **of** Float;

Var

I : Integer;
ExArray : TExArray;

begin

Randomize;
for I:=1 **to** 100 **do**
 ExArray[I]:=(~~Random~~-Random)*100;
 Writeln (' Max_____:', MaxValue (ExArray):8:4);
 Writeln (' Min_____:', MinValue (ExArray):8:4);
 Writeln (' Mean_____:', Mean (ExArray):8:4);
 Writeln (' Mean_(b)____:', Mean (@ExArray[1],100):8:4);

end.

meanandstddev

Declaration: Procedure meanandstddev(const data : array of float; var mean,stddev : float); procedure meanandstddev(const data : PFloat; Const N : Longint;var mean,stddev : float);

Description: meanandstddev calculates the mean and standard deviation of data and returns the result in mean and stddev, respectively. Stddev is zero if there is only one value.

The second form accepts a pointer to an array of N values.

Errors: None.

See also: mean ([251](#)),sum ([262](#)), sumofsquares ([262](#)), momentskewkurtosis ([255](#))

Listing: mathex/ex28.pp

Program Example28;

{ Program to demonstrate the Meanandstddev function . }

Uses math;

Type

TExArray = **Array**[1..100] **of** Extended;

Var

I : Integer;
ExArray : TExArray;
Mean, stddev : Extended;

begin

Randomize;
for I:=1 **to** 100 **do**
 ExArray[I]:=(~~Random~~-Random)*100;
 MeanAndStdDev (ExArray , Mean, StdDev);
 Writeln (' Mean_____:', Mean:8:4);
 Writeln (' StdDev_____:', StdDev:8:4);

```
MeanAndStdDev( @ExArray[1],100, Mean, StdDev );  
Writeln ( ' Mean_ (b)_ ', Mean:8:4);  
Writeln ( ' StdDev_ (b)_ ', StdDev:8:4);  
end.
```

min

Declaration: `Function min(Int1,Int2:Cardinal):Cardinal; Function min(Int1,Int2:Integer):Integer;`

Description: `min` returns the smallest value of `Int1` and `Int2`;

Errors: None.

See also: `max` ([249](#))

Listing: mathex/ex29.pp

```
Program Example29;  
  
{ Program to demonstrate the min function . }  
  
Uses math;  
  
Var  
  A,B : Cardinal;  
  
begin  
  A:=1; b:=2;  
  writeln ( min(a, b));  
end.
```

minIntValue

Declaration: `Function minIntValue(const Data: array of Integer): Integer;`

Description: `MinIntValue` returns the smallest value in the `Data` array.

This function is provided for Delphicompatibility, use `minvalue` instead.

Errors: None

See also: `minvalue` ([254](#)), `maxIntValue` ([250](#)), `maxvalue` ([250](#))

Listing: mathex/ex30.pp

```
Program Example30;  
  
{ Program to demonstrate the MinIntValue function . }  
  
{ Make sore integer is 32 bit }  
{ $mode objfpc }  
  
Uses math;  
  
Type  
  TExArray = Array [1..100] of Integer;
```

```

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=1 to 100 do
    ExArray[I]:=Random(I)-Random(100);
  Writeln ( MinIntValue ( ExArray ));
end.

```

minvalue

Declaration: Function minvalue(const data : array of float) : float; Function minvalue(const data : array of Integer) : Integer; Function minvalue(const data : PFloat; Const N : Integer) : float; Function minvalue(const data : PInteger; Const N : Integer) : Integer;

Description: Minvalue returns the smallest value in the data array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of N integer or float values.

Errors: None.

See also: maxIntValue ([250](#)), maxvalue ([250](#)), minIntValue ([253](#))

Listing: mathex/ex31.pp

Program Example26;

```

{ Program to demonstrate the MinValue function . }

{ Make sure integer is 32 bit }
{$mode objfpc}

```

Uses math;

Type

```

TExFloatArray = Array [1..100] of Float;
TExIntArray = Array [1..100] of Integer;

```

Var

```

I : Integer;
ExFloatArray : TExFloatArray;
AFloatArray : PFloat;
ExIntArray : TExIntArray;
AIntArray : PInteger;

```

begin

```

Randomize;
AFloatArray := @ExFloatArray [0];
AIntArray := @ExIntArray [0];
for I:=1 to 100 do
  ExFloatArray[I]:=(Random-Random)*100;
for I:=1 to 100 do
  ExIntArray[I]:=Random(I)-Random(100);
Writeln ( ' Min_Float ', MinValue ( ExFloatArray ):8:4);

```



```
Writeln ( ' Min_Float _ _ _ (b) _ _ _ ', MinValue ( AFloatArray , 100):8:4);  
Writeln ( ' Min_Integer _ _ _ _ _ _ _ _ ', MinValue ( ExIntArray ):8);  
Writeln ( ' Min_Integer _ _ (b) _ _ _ ', MinValue ( AintArray , 100):8);  
end.
```

momentskewkurtosis

Declaration: procedure momentskewkurtosis(const data : array of float; var m1,m2,m3,m4,skew,kurtosis : float); procedure momentskewkurtosis(const data : PFloat; Const N : Integer; var m1,m2,m3,m4,skew,kurtosis : float);

Description: momentskewkurtosis calculates the 4 first moments of the distribution of values in data and returns them in m1,m2,m3 and m4, as well as the skew and kurtosis.

Errors: None.

See also: mean ([251](#)), meanandstddev ([252](#))

Listing: mathex/ex32.pp

Program Example32;

{ Program to demonstrate the momentskewkurtosis function . }

Uses math;

Var

```
DistArray : Array[1..1000] of float;  
I : longint;  
m1,m2,m3,m4,skew,kurtosis : float;
```

begin

```
randomize;  
for I:=1 to 1000 do  
  distarray [ i ]:= random;  
momentskewkurtosis ( DistArray , m1, m2, m3, m4, skew, kurtosis );
```

```
Writeln ( ' 1 st_moment _ _ _ ', m1:8:6);  
Writeln ( ' 2 nd_moment _ _ _ ', m2:8:6);  
Writeln ( ' 3 rd_moment _ _ _ ', m3:8:6);  
Writeln ( ' 4 th_moment _ _ _ ', m4:8:6);  
Writeln ( ' Skew _ _ _ _ _ _ _ _ ', skew:8:6);  
Writeln ( ' kurtosis _ _ _ _ _ ', kurtosis :8:6);  
end.
```

norm

Declaration: Function norm(const data : array of float) : float; Function norm(const data : PFloat; Const N : Integer) : float;

Description: Norm calculates the Euclidian norm of the array of data. This equals sqrt (sumofsquares (data)).

The second form accepts a pointer to an array of N values.

Errors: None.

See also: sumofsquares ([262](#))

Listing: mathex/ex33.pp

```
Program Example33;

{ Program to demonstrate the norm function . }

Uses math;

Type
  TVector = Array[1..10] of Float;

Var
  AVector : TVector;
  I : longint;

begin
  for I:=1 to 10 do
    AVector[I]:=Random;
  Writeln (Norm(AVector));
end.
```

popnstddev

Declaration: Function popnstddev(const data : array of float) : float; Function popnstddev(const data : PFloat; Const N : Integer) : float;

Description: Popnstddev returns the square root of the population variance of the values in the Data array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of N values.

Errors: None.

See also: popnvariance ([257](#)), mean ([251](#)), meanandstddev ([252](#)), stddev ([261](#)), momentskewkurtosis ([255](#))

Listing: mathex/ex35.pp

```
Program Example35;

{ Program to demonstrate the PopnStdDev function . }

Uses Math;

Type
  TExArray = Array[1..100] of Float;

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=1 to 100 do
    ExArray[I]:=(Random-Random)*100;
  Writeln ( ' Max', MaxValue ( ExArray ):8:4);
  Writeln ( ' Min', MinValue ( ExArray ):8:4);
```

```
    Writeln ( ' Pop. _ stddev . _ _ _ _ _ : _ ' , PopnStdDev ( ExArray ) : 8 : 4 );  
    Writeln ( ' Pop. _ stddev . _ ( b ) _ _ : _ ' , PopnStdDev ( @ExArray [ 1 ] , 100 ) : 8 : 4 );  
end.
```

popnvariance

Declaration: Function popnvariance(const data : array of float) : float; Function popnvariance(const data : PFloat; Const N : Integer) : float;

Description: Popnvariance returns the square root of the population variance of the values in the Data array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of N values.

Errors: None.

See also: popnstddev (256), mean (251), meanandstddev (252), stddev (261), momentskewkurtosis (255)

Listing: mathex/ex36.pp

Program Example36;

{ Program to demonstrate the PopnVariance function . }

Uses math;

Type

TExArray = **Array** [1 .. 100] **of** Float;

Var

I : Integer;

ExArray : TExArray;

begin

Randomize;

for I := 1 **to** 100 **do**

ExArray [i] := (Random - Random) * 100;

Writeln (' Max _ _ _ _ _ : _ ' , MaxValue (ExArray) : 8 : 4);

Writeln (' Min _ _ _ _ _ : _ ' , MinValue (ExArray) : 8 : 4);

Writeln (' Pop. _ var . _ _ _ _ _ : _ ' , PopnVariance (ExArray) : 8 : 4);

Writeln (' Pop. _ var . _ (b) _ _ : _ ' , PopnVariance (@ExArray [1] , 100) : 8 : 4);

end.

power

Declaration: Function power(base,exponent : float) : float;

Description: power raises base to the power power. This is equivalent to $\exp(\text{power} * \ln(\text{base}))$. Therefore base should be non-negative.

Errors: None.

See also: intpower (246)

Listing: mathex/ex34.pp

```
Program Example34;

{ Program to demonstrate the power function . }

Uses Math;

procedure dopower(x,y : float );

begin
  writeln (x:8:6, '^' ,y:8:6, '= ',power(x,y):8:6)
end;

begin
  dopower (2,2);
  dopower (2,-2);
  dopower (2,0.0);
end.
```

radtcycle

Declaration: Function radtcycle(rad : float) : float;

Description: Radtcycle converts its argument rad (an angle expressed in radians) to an angle in cycles.
(1 cycle equals 2 pi radians)

Errors: None.

See also: degtograd ([243](#)), degtorad ([243](#)), radtodeg ([258](#)), radtograd ([259](#)), cycletorad ([242](#))

Listing: mathex/ex37.pp

```
Program Example37;

{ Program to demonstrate the radtcycle function . }

Uses math;

begin
  writeln ( radtcycle (2*pi):8:6);
  writeln ( radtcycle ( pi):8:6);
  writeln ( radtcycle ( pi/2):8:6);
end.
```

radtodeg

Declaration: Function radtodeg(rad : float) : float;

Description: Radtodeg converts its argument rad (an angle expressed in radians) to an angle in degrees.
(180 degrees equals pi radians)

Errors: None.

See also: degtograd ([243](#)), degtorad ([243](#)), radtcycle ([258](#)), radtograd ([259](#)), cycletorad ([242](#))

Listing: mathex/ex38.pp

```
Program Example38;  
  
{ Program to demonstrate the radtodeg function . }  
  
Uses math;  
  
begin  
  writeln (radtodeg (2*pi):8:6);  
  writeln (radtodeg (pi):8:6);  
  writeln (radtodeg (pi/2):8:6);  
end.
```

radtograd

Declaration: Function `radtograd(rad : float) : float;`

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in grads.
(200 grads equals pi radians)

Errors: None.

See also: `degtograd` ([243](#)), `degtorad` ([243](#)), `radto cycle` ([258](#)), `radtodeg` ([258](#)), `cycletorad` ([242](#))

Listing: `mathex/ex39.pp`

```
Program Example39;  
  
{ Program to demonstrate the radtograd function . }  
  
Uses math;  
  
begin  
  writeln (radtograd (2*pi):8:6);  
  writeln (radtograd (pi):8:6);  
  writeln (radtograd (pi/2):8:6);  
end.
```

randg

Declaration: Function `randg(mean, stddev : float) : float;`

Description: `randg` returns a random number which - when produced in large quantities - has a Gaussian distribution with mean `mean` and standarddeviation `stddev`.

Errors: None.

See also: `mean` ([251](#)), `stddev` ([261](#)), `meanandstddev` ([252](#))

Listing: `mathex/ex40.pp`

```
Program Example40;  
  
{ Program to demonstrate the randg function . }
```

Uses Math;

Type

TExArray = **Array**[1..10000] **of** Float;

Var

I : Integer;
ExArray : TExArray;
Mean, Stddev : Float;

begin

Randomize;
for I:=1 **to** 10000 **do**
 ExArray[I]:= Randg(1,0.2);
MeanAndStdDev(ExArray , Mean, StdDev);
 WriteLn(' Mean_____:', Mean:8:4);
 WriteLn(' StdDev_____:', StdDev:8:4);

end.

sincos

Declaration: Procedure sincos(theta : float; var sinus, cosinus : float);

Description: Sincos calculates the sine and cosine of the angle **theta**, and returns the result in **sinus** and **cosinus**.

On Intel hardware, This calculation will be faster than making 2 calls to calculate the sine and cosine separately.

Errors: None.

See also: arcsin ([239](#)), arccos ([238](#)).

Listing: mathex/ex41.pp

Program Example41;

{ Program to demonstrate the sincos function . }

Uses math;

Procedure dosincos (Angle : Float);

Var

Sine , Cosine : Float ;

begin

sincos (angle , sine , cosine);
Write (' Angle _____:', Angle :8:6);
Write (' _____ Sine _____:', sine :8:6);
Write (' _____ Cosine _____:', cosine :8:6);

end;

begin

dosincos (**pi**);
dosincos (**pi** /2);
dosincos (**pi** /3);
dosincos (**pi** /4);

```
dosincos (pi / 6);  
end.
```

sinh

Declaration: Function `sinh(x : float) : float;`

Description: Sinh returns the hyperbolic sine of its argument x.

Errors:

See also: `cosh` ([242](#)), `arsinh` ([240](#)), `tanh` ([264](#)), `artanh` ([241](#))

Listing: mathex/ex42.pp

```
Program Example42;  
  
{ Program to demonstrate the sinh function . }  
  
Uses math;  
  
begin  
  writeln (sinh (0));  
  writeln (sinh (1));  
  writeln (sinh (-1));  
end.
```

stddev

Declaration: Function `stddev(const data : array of float) : float;` Function `stddev(const data : PFloat; Const N : Integer) : float;`

Description: Stddev returns the standard deviation of the values in Data. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: `mean` ([251](#)), `meanandstddev` ([252](#)), `variance` ([265](#)), `totalvariance` ([265](#))

Listing: mathex/ex43.pp

```
Program Example40;  
  
{ Program to demonstrate the stddev function . }  
  
Uses Math;  
  
Type  
  TExArray = Array [1..10000] of Float;  
  
Var  
  I : Integer;  
  ExArray : TExArray;
```

```

begin
  Randomize;
  for I:=1 to 10000 do
    ExArray[I]:=Randg(1,0.2);
    Writeln(' StdDev_:', StdDev(ExArray):8:4);
    Writeln(' StdDev_(b)_:', StdDev(@ExArray[0],10000):8:4);
end.

```

sum

Declaration: Function sum(const data : array of float) : float; Function sum(const data : PFloat; Const N : Integer) : float;

Description: Sum returns the sum of the values in the data array.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: sumofsquares (262), sumsandsquares (263), totalvariance (265) , variance (265)

Listing: mathex/ex44.pp

Program Example44;

{ Program to demonstrate the Sum function . }

Uses math;

Type

TExArray = **Array**[1..100] **of** Float;

Var

I : Integer;
ExArray : TExArray;

begin

```

  Randomize;
  for I:=1 to 100 do
    ExArray[I]:=( Random-Random)*100;
    Writeln(' Max_:', MaxValue(ExArray):8:4);
    Writeln(' Min_:', MinValue(ExArray):8:4);
    Writeln(' Sum_:', Sum(ExArray):8:4);
    Writeln(' Sum_(b)_:', Sum(@ExArray[1],100):8:4);
end.

```

sumofsquares

Declaration: Function sumofsquares(const data : array of float) : float; Function sumofsquares(const data : PFloat; Const N : Integer) : float;

Description: Sumofsquares returns the sum of the squares of the values in the data array.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: sum (262), sumsandsquares (263), totalvariance (265) , variance (265)

Listing: mathex/ex45.pp

```
Program Example45;

{ Program to demonstrate the SumOfSquares function . }

Uses math;

Type
  TExArray = Array[1..100] of Float;

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=1 to 100 do
    ExArray[I] := (Random Random)*100;
  Writeln('Max_____:', MaxValue(ExArray):8:4);
  Writeln('Min_____:', MinValue(ExArray):8:4);
  Writeln('Sum_squares_____:', SumOfSquares(ExArray):8:4);
  Writeln('Sum_squares_(b)_:_', SumOfSquares(@ExArray[1],100):8:4);
end.
```

sumsandsquares

Declaration: Procedure sumsandsquares(const data : array of float; var sum,sumofsquares : float); Procedure sumsandsquares(const data : PFloat; Const N : Integer; var sum,sumofsquares : float);

Description: sumsandsquares calculates the sum of the values and the sum of the squares of the values in the data array and returns the results in sum and sumofsquares.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: sum ([262](#)), sumofsquares ([262](#)), totalvariance ([265](#)), variance ([265](#))

Listing: mathex/ex46.pp

```
Program Example45;

{ Program to demonstrate the SumOfSquares function . }

Uses math;

Type
  TExArray = Array[1..100] of Float;

Var
  I : Integer;
  ExArray : TExArray;
  s,ss : float;

begin
```

```
Randomize;
for I:=1 to 100 do
  ExArray[I]:=(Random-Random)*100;
  Writeln('Max_____:', MaxValue(ExArray):8:4);
  Writeln('Min_____:', MinValue(ExArray):8:4);
  SumsAndSquares(ExArray, S, SS);
  Writeln('Sum_____:', S:8:4);
  Writeln('Sum_squares_____:', SS:8:4);
  SumsAndSquares(@ExArray[1], 100, S, SS);
  Writeln('Sum_(b)_____:', S:8:4);
  Writeln('Sum_squares_(b)_____:', SS:8:4);
end.
```

tan

Declaration: Function tan(x : float) : float;

Description: Tan returns the tangent of x.

Errors: If x (normalized) is $\pi/2$ or $3\pi/2$ then an overflow will occur.

See also: tanh ([264](#)), arcsin ([239](#)), sincos ([260](#)), arccos ([238](#))

Listing: mathex/ex47.pp

```
Program Example47;

{ Program to demonstrate the Tan function . }

Uses math;

Procedure DoTan(Angle : Float);

begin
  Write('Angle _____', RadToDeg(Angle):8:6);
  Writeln('_____Tangent_____:', Tan(Angle):8:6);
end;

begin
  DoTan(0);
  DoTan(Pi);
  DoTan(Pi/3);
  DoTan(Pi/4);
  DoTan(Pi/6);
end.
```

tanh

Declaration: Function tanh(x : float) : float;

Description: Tanh returns the hyperbolic tangent of x.

Errors: None.

See also: arcsin ([239](#)), sincos ([260](#)), arccos ([238](#))

Listing: mathex/ex48.pp

```
Program Example48;

{ Program to demonstrate the Tanh function . }

Uses math;

begin
  writeln ( tanh (0));
  writeln ( tanh (1));
  writeln ( tanh (-1));
end.
```

totalvariance

Declaration: Function totalvariance(const data : array of float) : float; Function totalvariance(const data : PFloat; Const N : Integer) : float;

Description: TotalVariance returns the total variance of the values in the data array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: variance ([265](#)), stddev ([261](#)), mean ([251](#))

Listing: mathex/ex49.pp

```
Program Example49;

{ Program to demonstrate the TotalVariance function . }

Uses math;

Type
  TExArray = Array [1..100] of Float;

Var
  I : Integer;
  ExArray : TExArray;
  TV : float;

begin
  Randomize;
  for I:=1 to 100 do
    ExArray[I]:=(RandomRandom)*100;
  TV:= TotalVariance ( ExArray );
  writeln ( ' Total_variance _:_:_:_:_:', TV:8:4);
  TV:= TotalVariance ( @ExArray[1],100);
  writeln ( ' Total_Variance _(b)_:_:_:', TV:8:4);
end.
```

variance

Declaration: Function variance(const data : array of float) : float; Function variance(const data : PFloat; Const N : Integer) : float;

Description: `Variance` returns the variance of the values in the `data` array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: `totalvariance` ([265](#)), `stddev` ([261](#)), `mean` ([251](#))

Listing: `mathex/ex50.pp`

```
Program Example50;

{ Program to demonstrate the Variance function . }

Uses math;

Type
  TExArray = Array [1..100] of Float;

Var
  I : Integer;
  ExArray : TExArray;
  V : float;

begin
  Randomize;
  for I:=1 to 100 do
    ExArray[I]:= (Random-Random)*100;
  V:= Variance ( ExArray );
  Writeln ( ' Variance _____', V:8:4 );
  V:= Variance ( @ExArray[1], 100 );
  Writeln ( ' Variance (b) _____', V:8:4 );
end.
```

Chapter 13

The MMX unit

This chapter describes the MMX unit. This unit allows you to use the MMX capabilities of the Free Pascal compiler. It was written by Florian Klämpfl for the I386 processor. It should work on all platforms that use the Intel processor.

13.1 Variables, Types and constants

The following types are defined in the MMX unit:

```
tmmxshortint = array[0..7] of shortint;  
tmmxbyte = array[0..7] of byte;  
tmmxword = array[0..3] of word;  
tmmxinteger = array[0..3] of integer;  
tmmxfixed = array[0..3] of fixed16;  
tmmxlongint = array[0..1] of longint;  
tmmxcardinal = array[0..1] of cardinal;  
{ for the AMD 3D }  
tmmxsingle = array[0..1] of single;
```

And the following pointers to the above types:

```
pmmxshortint = ^tmmxshortint;  
pmmxbyte = ^tmmxbyte;  
pmmxword = ^tmmxword;  
pmmxinteger = ^tmmxinteger;  
pmmxfixed = ^tmmxfixed;  
pmmxlongint = ^tmmxlongint;  
pmmxcardinal = ^tmmxcardinal;  
{ for the AMD 3D }  
pmmxsingle = ^tmmxsingle;
```

The following initialized constants allow you to determine if the computer has MMX extensions. They are set correctly in the unit's initialization code.

```
is_mmx_cpu : boolean = false;  
is_amd_3d_cpu : boolean = false;
```

13.2 Functions and Procedures

Emms

Declaration: Procedure Emms ;

Description: Emms sets all floating point registers to empty. This procedure must be called after you have used any MMX instructions, if you want to use floating point arithmetic. If you just want to move floating point data around, it isn't necessary to call this function, the compiler doesn't use the FPU registers when moving data. Only when doing calculations, you should use this function.

Errors: None.

See also: Programmers' guide

```
Example:: Program MMXDemo;
uses mmx;
var
  d1 : double;
  a : array[0..10000] of double;
  i : longint;
begin
  d1:=1.0;
  {$mmx+}
  { floating point data is used, but we do _no_ arithmetic }
  for i:=0 to 10000 do
    a[i]:=d2; { this is done with 64 bit moves }
  {$mmx-}
  emms; { clear fpu }
  { now we can do floating point arithmetic again }
end.
```

Chapter 14

The MsMouse unit

The msmouse unit provides basic mouse handling under DOS (Go32v1 and Go32v2) Some general remarks about the msmouse unit:

- The mouse driver does not know when the text screen scrolls. This results in unerased mouse cursors on the screen when the screen scrolls while the mouse cursor is visible. The solution is to hide the mouse cursor (using HideMouse) when you write something to the screen and to show it again afterwards (using ShowMouse).
- All Functions/Procedures that return and/or accept coordinates of the mouse cursor, always do so in pixels and zero based (so the upper left corner of the screen is (0,0)). To get the (column, row) in standard text mode, divide both x and y by 8 (and add 1 if you want to have it 1 based).
- The real resolution of graphic modes and the one the mouse driver uses can differ. For example, mode 13h (320*200 pixels) is handled by the mouse driver as 640*200, so you will have to multiply the X coordinates you give to the driver and divide the ones you get from it by 2 in that mode.
- By default the msmouse unit is compiled with the conditional define MouseCheck. This causes every procedure/function of the unit to check the MouseFound variable prior to doing anything. Of course this is not necessary, so if you are sure you are not calling any mouse unit procedures when no mouse is found, you can recompile the mouse unit without this conditional define.
- You will notice that several procedures/functions have longint sized parameters while only the lower 16 bits are used. This is because FPC is a 32 bit compiler and consequently 32 bit parameters result in faster code.

14.1 Constants, types and variables

The following constants are defined (to be used in e.g. the GetLastButtonPress ([270](#)) call).

```
LButton = 1; {left button}
RButton = 2; {right button}
MButton = 4; {middle button}
```

The following variable exist:

```
MouseFound: Boolean;
```

it is set to `True` or `False` in the unit's initialization code.

14.2 Functions and procedures

GetLastButtonPress

Declaration: Function GetLastButtonPress (Button: Longint; Var x,y:Longint) : Longint;

Description: GetLastButtonPress Stores the position where Button was last pressed in x and y and returns the number of times this button has been pressed since the last call to this function with Button as parameter. For Button you can use the LButton, RButton and MButton constants for resp. the left, right and middle button. With certain mouse drivers, checking the middle button when using a two-button mouse to gives and clears the stats of the right button.

Errors: None.

See also: GetLastButtonRelease ([271](#))

{example for GetLastButtonPress and GetLastButtonRelease}

Uses MsMouse, Crt;

Var x, y, times: Longint;
c: Char;

Begin

If MouseFound **Then**

Begin

 ClrScr;

 ShowMouse;

 WriteLn(' Move_the_mouse_and_click_the_buttons_(press_escape_to_quit).');

 WriteLn(' Press_the_L-key_to_see_the_stats_for_the_left_button.');

 WriteLn(' Press_the_R-key_to_see_the_stats_for_the_right_button.');

 WriteLn(' Press_the_M-key_to_see_the_stats_for_the_middle_button.');

 GotoXY(1,19);

 Write(' Since_the_last_call_to_GetLastButtonPress_with_this_button_as_parameter,the');

 GotoXY(1,22);

 Write(' Since_the_last_call_to_GetLastButtonRelease_with_this_button_as_parameter,the');

 Repeat

If Keypressed **Then**

Begin

 c := UpCase(Readkey);

Case c **Of**

 'L':

Begin

 GotoXY(1, 20);

 ClrEol;

 times := GetLastButtonPress(LButton, x, y);

 Write(' left_button_has_been_pressed_', times,
 ' _times,the_last_time_at_(' ,x, ', ', y, ')');

 times := GetLastButtonRelease(LButton, x, y);

 GotoXY(1,23);

 ClrEol;

 Write(' left_button_has_been_released_', times,
 ' _times,the_last_time_at_(' ,x, ', ', y, ')');

End;

 'R':

Begin

 GotoXY(1, 20);

 ClrEol;


```

        times := GetLastButtonPress (RButton, x, y);
        WriteLn (' right_button_has_been_pressed ', times,
            ' _times, _the _last _time _at _(' , x, ', ', y, ') ' );
        times := GetLastButtonRelease (RButton, x, y);
        GotoXY(1,23);
        ClrEol;
        Write (' right_button_has_been_released ', times,
            ' _times, _the _last _time _at _(' , x, ', ', y, ') ' )
    End;
'M' :
    Begin
        GotoXY(1, 20);
        ClrEol;
        times := GetLastButtonPress (MButton, x, y);
        WriteLn (' middle_button_has_been_pressed ', times,
            ' _times, _the _last _time _at _(' , x, ', ', y, ') ' );
        times := GetLastButtonRelease (MButton, x, y);
        GotoXY(1,23);
        ClrEol;
        Write (' middle_button_has_been_released ', times,
            ' _times, _the _last _time _at _(' , x, ', ', y, ') ' )
    End
End
End;
Until (c = #27); {escape}
While KeyPressed do ReadKey;
GotoXY(1,24);
HideMouse
End
End.

```

GetLastButtonRelease

Declaration: Function GetLastButtonRelease (Button: Longint; Var x,y:Longint) : Longint;

Description: GetLastButtonRelease stores the position where Button was last released in x and y and returns the number of times this button has been released since the last call to this function with Button as parameter. For button you can use the LButton, RButton and MButton constants for resp. the left, right and middle button. With certain mouse drivers, checking the middle button when using a two-button mouse to gives and clears the stats of the right button.

Errors: None.

See also: GetLastButtonPress ([270](#))

For an example, see GetLastButtonPress ([270](#)).

GetMouseState

Declaration: Procedure GetMouseState (Var x, y, buttons: Longint);

Description: GetMouseState Returns information on the current mouse position and which buttons are currently pressed. x and y return the mouse cursor coordinates in pixels. Buttons is a bitmask. Check the example program to see how you can get the necessary information from it.

Errors: None.

See also: LPressed ([273](#)), MPressed ([274](#)), RPressed ([274](#)), SetMousePos ([275](#))

{example for GetMouseState, IsLPressed, IsRPressed and IsMPressed}

Uses MsMouse, Crt;

Var X, Y, State : Longint;

Begin

If MouseFound **Then**

Begin

ClrScr;

 ShowMouse;

GotoXY(5,24);

Write(' Left_button: ');

GotoXY(30,24);

Write(' Right_button: ');

GotoXY(55,24);

Write(' Middle_button: ');

While KeyPressed **do** Readkey; *{clear keyboard buffer}*

Repeat

 GetMouseState(x, y, State);

GotoXY(20, 22);

Write('X: ',x:5, ' (column: ',(x **div** 8):2, ')_Y: ',y:5, ' (row: ',(y **div** 8):2, ')');

GotoXY(18, 24); *{left button}*

If (State **and** LButton) = LButton **Then**

{or: " If LPressed Then". If you use this function, no call to GetMouseState is necessary}

Write(' Down')

Else

Write(' Up_ ');

GotoXY(44, 24); *{right button}*

If (State **and** RButton) = RButton **Then**

{or: " If RPressed Then"}

Write(' Down')

Else

Write(' Up_ ');

GotoXY(70, 24); *{middle button}*

If (State **and** MButton) = MButton **Then**

{or: " If MPressed Then"}

Write(' Down')

Else

Write(' Up_ ');

Until KeyPressed;

 HideMouse;

While KeyPressed **Do** Readkey

End

End.

HideMouse

Declaration: Procedure HideMouse ;

Description: HideMouse makes the mouse cursor invisible. Multiple calls to HideMouse will require just as many calls to ShowMouse to make the mouse cursor visible again.

Errors: None.

See also: ShowMouse ([278](#)), SetMouseHideWindow ([275](#))

For an example, see ShowMouse ([278](#)).

InitMouse

Declaration: Procedure InitMouse ;

Description: InitMouse Initializes the mouse driver sets the variable MouseFound depending on whether or not a mouse is found. This is Automatically called at the start of your program. You should never have to call it, unless you want to reset everything to its default values.

Errors: None.

See also: MouseFound variable.

```
Program Mouse1;

{example for InitMouse and MouseFound}

Uses MsMouse;

Begin
  If MouseFound Then
    Begin
      {go into graphics mode 13h}
      Asm
        movl $0x013, %eax
        pushl %ebp
        int $0x010
        popl %ebp
      End;
      InitMouse;
      ShowMouse; {otherwise it stays invisible}
      WriteIn( ' Mouse_Found!_( press_enter_to_quit ) ' );
      ReadIn;
      {back to text mode}
      Asm
        movl $3, %eax
        pushl %ebp
        int $0x010
        popl %ebp
      End
    End
  End.
```

LPressed

Declaration: Function LPressed : Boolean;

Description: LPressed returns True if the left mouse button is pressed. This is simply a wrapper for the GetMouseState procedure.

Errors: None.

See also: GetMouseState ([271](#)), MPressed ([274](#)), RPressed ([274](#))

For an example, see GetMouseState ([271](#)).

MPressed

Declaration: `Function MPressed : Boolean;`

Description: `MPressed` returns `True` if the middle mouse button is pressed. This is simply a wrapper for the `GetMouseState` procedure.

Errors: None.

See also: `GetMouseState` ([271](#)), `LPressed` ([273](#)), `RPressed` ([274](#))

For an example, see `GetMouseState` ([271](#)).

RPressed

Declaration: `Function RPressed : Boolean;`

Description: `RPressed` returns `True` if the right mouse button is pressed. This is simply a wrapper for the `GetMouseState` procedure.

Errors: None.

See also: `GetMouseState` ([271](#)), `LPressed` ([273](#)), `MPressed` ([274](#))

For an example, see `GetMouseState` ([271](#)).

SetMouseAscii

Declaration: `Procedure SetMouseAscii (Ascii: Byte);`

Description: `SetMouseAscii` sets the `Ascii` value of the character that depicts the mouse cursor in text mode. The difference between this one and `SetMouseShape` ([276](#)), is that the foreground and background colors stay the same and that the `Ascii` code you enter is the character that you will get on screen; there's no XOR'ing.

Errors: None

See also: `SetMouseShape` ([276](#))

{example for SetMouseAscii}

{warning: no error checking is performed on the input}

Uses MsMouse, Crt;

Var ascii : Byte;
x,y: Longint;

Begin

If MouseFound **Then**

Begin

ClrScr;

WriteLn (' Press_any_mouse_button_to_quit_after_you''ve_entered_an_Ascii_value.');

WriteLn ;

WriteLn (' ASCII_value_of_mouse_cursor:');

ShowMouse;

Repeat

```
    GotoXY(30,3);
    ClrEol;
    Readln(ascii);
    SetMouseAscii(ascii)
  Until ( GetLastButtonPress(LButton,x,y) <> 0) Or
        ( GetLastButtonPress(RButton,x,y) <> 0) Or
        ( GetLastButtonPress(MButton,x,y) <> 0);
  HideMouse
End;
```

End.

SetMouseHideWindow

Declaration: Procedure SetMouseHideWindow (xmin,ymin,xmax,ymax: Longint);

Description: SetMouseHideWindow defines a rectangle on screen with top-left corner at (xmin,ymin) and bottom-right corner at (xmax,ymax), which causes the mouse cursor to be turned off when it is moved into it. When the mouse is moved into the specified region, it is turned off until you call ShowMouse again. However, once you've called ShowMouse (278), you'll have to call SetMouseHideWindow again to redefine the hide window... This may be annoying, but it's the way it's implemented in the mouse driver. While xmin, ymin, xmax and ymax are Longint parameters, only the lower 16 bits are used.

Warning: it seems Win98 SE doesn't (properly) support this function, maybe this already the case with earlier versions too!

Errors: None.

See also: ShowMouse (278), HideMouse (272)

nputlistingmouseex/mouse9.pp

SetMousePos

Declaration: Procedure SetMousePos (x,y:Longint);

Description: SetMousePos sets the position of the mouse cursor on the screen. x is the horizontal position in pixels, y the vertical position in pixels. The upper-left hand corner of the screen is the origin. While x and y are longints, only the lower 16 bits are used.

Errors: None.

See also: GetMouseState (271)

{example for SetMousePos}

Uses MsMouse, Crt;

Begin

If MouseFound **Then**

Begin

 ShowMouse;

While KeyPressed **do** ReadKey;

Repeat

 SetMousePos(Random(80*8), Random(25*8));

 delay(100);

```
    Until Keypressed;  
    HideMouse;  
    While KeyPressed do ReadKey;  
End;  
End.
```

SetMouseShape

Declaration: Procedure SetMouseShape (ForeColor,BackColor,Ascii: Byte);

Description: SetMouseShape defines how the mouse cursor looks in textmode The character and its attributes that are on the mouse cursor's position on screen are XOR'ed with resp. ForeColor, BackColor and Ascii. Set them all to 0 for a "transparent" cursor.

Errors: None.

See also: SetMouseAscii ([274](#))

{example for SetMouseShape}

{warning: no error checking is performed on the input}

{the Ascii value you enter is XOR'ed with the Ascii value of the character on the screen over which you move the cursor. To get a "transparent" cursor, use the Ascii value 0}

Uses MsMouse, Crt;

Var ascii , fc , bc: Byte;
x,y: Longint;

Begin

If MouseFound **Then**

Begin

ClrScr;

WriteLn(' Press_any_mouse_button_to_quit_after_you''ve_entered_a_sequence_of_numbers.');

WriteLn;

WriteLn(' ASCII_value_of_mouse_cursor:');

WriteLn(' Foreground_color:');

WriteLn(' Background_color:');

 ShowMouse;

Repeat

GotoXY(30,3);

ClrEol;

ReadLn(ascii);

GotoXY(18,4);

ClrEol;

ReadLn(fc);

GotoXY(19,5);

ClrEol;

ReadLn(bc);

 SetMouseShape(fc , bc , ascii)

Until (GetLastButtonPress(LButton , x , y) <> 0) **Or**

 (GetLastButtonPress(RButton , x , y) <> 0) **Or**

 (GetLastButtonPress(MButton , x , y) <> 0);

 HideMouse

End;

End.

SetMouseSpeed

Declaration: Procedure SetMouseSpeed (Horizontal, Vertical: Longint);

Description: SetMouseSpeed sets the mouse speed in mickeys per 8 pixels. A mickey is the smallest measurement unit handled by a mouse. With this procedure you can set how many mickeys the mouse should move to move the cursor 8 pixels horizontally or vertically. The default values are 8 for horizontal and 16 for vertical movement. While this procedure accepts longint parameters, only the low 16 bits are actually used.

Errors: None.

See also:

Uses MsMouse, Crt;

Var hor, vert: Longint;
x, y: Longint;

Begin

If MouseFound **Then**

Begin

ClrScr;

WriteLn(' Click any button to quit after you've entered a sequence of numbers.');

WriteLn;

WriteLn(' Horizontal mickey's_per_pixel:');

WriteLn(' Vertical mickey's_per_pixel:');

 ShowMouse;

Repeat

GotoXY(32,3);

ClrEol;

ReadLn(hor);

GotoXY(30,4);

ClrEol;

ReadLn(vert);

 SetMouseSpeed(hor, vert);

Until (GetLastButtonPress(LButton, x, y) <> 0) **Or**

 (GetLastButtonPress(RButton, x, y) <> 0) **Or**

 (GetLastButtonPress(MButton, x, y) <> 0);

End

End.

SetMouseWindow

Declaration: Procedure SetMouseWindow (xmin, ymin, xmax, ymax: Longint);

Description: SetMouseWindow defines a rectangle on screen with top-left corner at (xmin, ymin) and bottom-right corner at (xmax, ymax), out of which the mouse cursor can't move. This procedure is simply a wrapper for the SetMouseXRange (278) and SetMouseYRange (278) procedures. While xmin, ymin, xmax and ymax are Longint parameters, only the lower 16 bits are used.

Errors: None.

See also: SetMouseXRange (278), SetMouseYRange (278)

For an example, see [SetMouseXRange \(278\)](#).

SetMouseXRange

Declaration: Procedure SetMouseXRange (Min, Max: Longint);

Description: SetMouseXRange sets the minimum (Min) and maximum (Max) horizontal coordinates in between which the mouse cursor can move. While Min and Max are Longint parameters, only the lower 16 bits are used.

Errors: None.

See also: [SetMouseYRange \(278\)](#), [SetMouseWindow \(277\)](#)

{example for SetMouseXRange, SetMouseYRange and SetMouseWindow}

Uses MsMouse, Crt;

Begin

If MouseFound **Then**

Begin

SetMouseXRange(20*8,50*8); *{charracter width and height = 8 pixels}*

SetMouseYRange(10*8,15*8);

*{the two lines of code have exactly the same effect as
SetMouseWindow(20*8,10*8,50*8,15*8)}*

WriteIn(' Press_any_key_to_quit.');

ShowMouse;

While KeyPressed **Do** ReadKey;

Readkey;

While KeyPressed **Do** ReadKey;

HideMouse

End

End.

SetMouseYRange

Declaration: Procedure SetMouseYRange (Min, Max: Longint);

Description: SetMouseYRange sets the minimum (Min) and maximum (Max) vertical coordinates in between which the mouse cursor can move. While Min and Max are Longint parameters, only the lower 16 bits are used.

Errors: None.

See also: [SetMouseXRange \(278\)](#), [SetMouseWindow \(277\)](#)

For an example, see [SetMouseXRange \(278\)](#).

ShowMouse

Declaration: Procedure ShowMouse ;

Description: ShowMouse makes the mouse cursor visible. At the start of your program, the mouse cursor is invisible.

Errors: None.

See also: [HideMouse \(272\)](#), [SetMouseHideWindow \(275\)](#)

{example for ShowMouse and HideMouse}

Uses MsMouse;

Begin

ClrScr;

If MouseFound **Then**

Begin

WriteIn (' Now you can see the mouse ... (press enter to continue) ');

 ShowMouse;

ReadIn;

 HideMouse;

WriteIn (' And now you can ' ' t ... (press enter to quit) ');

ReadIn

End

End.

Chapter 15

The Objects unit.

This chapter documents the `objects` unit. The unit was implemented by many people, and was mainly taken from the FreeVision sources. It has been ported to all supported platforms.

The methods and fields that are in a `Private` part of an object declaration have been left out of this documentation.

15.1 Constants

The following constants are error codes, returned by the various stream objects.

```
CONST
    stOk          = 0; { No stream error }
    stError       = -1; { Access error }
    stInitError   = -2; { Initialize error }
    stReadError   = -3; { Stream read error }
    stWriteError  = -4; { Stream write error }
    stGetError    = -5; { Get object error }
    stPutError    = -6; { Put object error }
    stSeekError   = -7; { Seek error in stream }
    stOpenError   = -8; { Error opening stream }
```

These constants can be passed to constructors of file streams:

```
CONST
    stCreate      = $3C00; { Create new file }
    stOpenRead    = $3D00; { Read access only }
    stOpenWrite   = $3D01; { Write access only }
    stOpen        = $3D02; { Read/write access }
```

The following constants are error codes, returned by the collection list objects:

```
CONST
    coIndexError = -1; { Index out of range }
    coOverflow   = -2; { Overflow }
```

Maximum data sizes (used in determining how many data can be used).

```
CONST
  MaxBytes = 128*1024*1024;           { Maximum data size }
  MaxWords = MaxBytes DIV SizeOf(Word); { Max word data size }
  MaxPtrs = MaxBytes DIV SizeOf(Pointer); { Max ptr data size }
  MaxCollectionSize = MaxBytes DIV SizeOf(Pointer); { Max collection size }
```

15.2 Types

The following auxiliary types are defined:

```
TYPE
  { Character set }
  TCharSet = SET Of Char;
  PCharSet = ^TCharSet;

  { Byte array }
  TByteArray = ARRAY [0..MaxBytes-1] Of Byte;
  PByteArray = ^TByteArray;

  { Word array }
  TWordArray = ARRAY [0..MaxWords-1] Of Word;
  PWordArray = ^TWordArray;

  { Pointer array }
  TPointerArray = Array [0..MaxPtrs-1] Of Pointer;
  PPointerArray = ^TPointerArray;

  { String pointer }
  PString = ^String;

  { Filename array }
  AsciiZ = Array [0..255] Of Char;

  Sw_Word    = Cardinal;
  Sw_Integer = LongInt;
```

The following records are used internally for easy type conversion:

```
TYPE
  { Word to bytes}
  WordRec = packed RECORD
    Lo, Hi: Byte;
  END;

  { LongInt to words }
  LongRec = packed RECORD
    Lo, Hi: Word;
  END;

  { Pointer to words }
  PtrRec = packed RECORD
    ofs, Seg: Word;
  END;
```

The following record is used when streaming objects:

```
TYPE
  PStreamRec = ^TStreamRec;
  TStreamRec = Packed RECORD
    ObjType: Sw_Word;
    VmtLink: pointer;
    Load : Pointer;
    Store: Pointer;
    Next : PStreamRec;
  END;
```

The TPoint basic object is used in the TRect object (see section [15.4](#), page [285](#)):

```
TYPE
  PPoint = ^TPoint;
  TPoint = OBJECT
    X, Y: Sw_Integer;
  END;
```

15.3 Procedures and Functions

NewStr

Declaration: Function NewStr (Const S: String): PString;

Description: NewStr makes a copy of the string S on the heap, and returns a pointer to this copy.

The allocated memory is not based on the declared size of the string passed to NewStr, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: DisposeStr ([283](#))

```
Program ex40;

{ Program to demonstrate the NewStr function }

Uses Objects;

Var S : String;
    P : PString;

begin
  S:= 'Some_really_cute_string';
  WriteLn ( 'Memavail_', Memavail);
  P:=NewStr(S);
  If P^<>S then
    WriteLn ( 'Oh-oh... Something_is_wrong_!!' );
  WriteLn ( 'Allocated_string_', Memavail_, Memavail);
  DisposeStr(P);
  WriteLn ( 'Deallocated_string_', Memavail_, Memavail);
end.
```

DisposeStr

Declaration: Procedure DisposeStr (P: PString);

Description: DisposeStr removes a dynamically allocated string from the heap.

Errors: None.

See also: NewStr ([282](#))

For an example, see NewStr ([282](#)).

Abstract

Declaration: Procedure Abstract;

Description: When implementing abstract methods, do not declare them as **abstract**. Instead, define them simply as **virtual**. In the implementation of such abstract methods, call the **Abstract** procedure. This allows explicit control of what happens when an abstract method is called.

The current implementation of **Abstract** terminates the program with a run-time error 211.

Errors: None.

See also: Most abstract types.

RegisterObjects

Declaration: Procedure RegisterObjects;

Description: RegisterObjects registers the following objects for streaming:

1. TCollection, see section [15.10](#), page [309](#).
2. TStringCollection, see section [15.12](#), page [328](#).
3. TStrCollection, see section [15.13](#), page [330](#).

Errors: None.

See also: RegisterType ([283](#))

RegisterType

Declaration: Procedure RegisterType (Var S: TStreamRec);

Description: RegisterType registers a new type for streaming. An object cannot be streamed unless it has been registered first. The stream record S needs to have the following fields set:

ObjType: Sw_Word This should be a unique identifier. Each possible type should have it's own identifier.

VmtLink: pointer This should contain a pointer to the VMT (Virtual Method Table) of the object you try to register. You can get it with the following expression:

VmtLink: ofs(TypeOf(MyType)^);

Load : Pointer is a pointer to a method that initializes an instance of that object, and reads the initial values from a stream. This method should accept as it's sole argument a PStream type variable.

Store: Pointer is a pointer to a method that stores an instance of the object to a stream. This method should accept as its sole argument a **PStream** type variable.

Errors: In case of error (if a object with the same **ObjType**) is already registered), run-time error 212 occurs.

Unit MyObject;

Interface

Uses Objects;

Type

```
PMyObject = ^ TMyObject;
TMyObject = Object ( TObject )
    Field : Longint;
    Constructor Init ;
    Constructor Load ( Var Stream : TStream );
    Destructor Done;
    Procedure Store ( Var Stream : TStream );
    Function GetField : Longint;
    Procedure SetField ( Value : Longint );
    end;
```

Implementation

Constructor TMyobject.Init ;

begin

Inherited Init ;

 Field := -1;

end;

Constructor TMyobject.Load (**Var** Stream : TStream);

begin

 Stream.**Read**(Field , **Sizeof**(Field));

end;

Destructor TMyObject.Done;

begin

end;

Function TMyObject.GetField : Longint;

begin

 GetField := Field ;

end;

Procedure TMyObject.SetField (Value : Longint);

begin

 Field := Value ;

end;

```
Procedure TMyObject.Store (Var Stream : TStream);
```

```
begin
```

```
    Stream.Write( Field , SizeOf( Field ));
```

```
end;
```

```
Const MyObjectRec : TStreamRec = (
```

```
    Objtype : 666;
```

```
    vmtlink : Ofs( TypeOf( TMyObject )^);
```

```
    Load : @TMyObject.Load;
```

```
    Store : @TMyObject.Store;
```

```
);
```

```
begin
```

```
    RegisterObjects;
```

```
    RegisterType ( MyObjectRec );
```

```
end;
```

LongMul

Declaration: Function LongMul (X, Y: Integer): LongInt;

Description: LongMul multiplies X with Y. The result is of type Longint. This avoids possible overflow errors you would normally get when multiplying X and Y that are too big.

Errors: None.

See also: LongDiv ([285](#))

LongDiv

Declaration: Function LongDiv (X: Longint; Y: Integer): Integer;

Description: LongDiv divides X by Y. The result is of type Integer instead of type Longint, as you would get normally.

Errors: If Y is zero, a run-time error will be generated.

See also: LongMul ([285](#))

15.4 TRect

The TRect object is declared as follows:

```
TRect = OBJECT
```

```
    A, B: TPoint;
```

```
    FUNCTION Empty: Boolean;
```

```
    FUNCTION Equals (R: TRect): Boolean;
```

```
    FUNCTION Contains (P: TPoint): Boolean;
```

```
    PROCEDURE Copy (R: TRect);
```

```
    PROCEDURE Union (R: TRect);
```

```
    PROCEDURE Intersect (R: TRect);
```

```
    PROCEDURE Move (ADX, ADY: Sw_Integer);
```

```
    PROCEDURE Grow (ADX, ADY: Sw_Integer);
```

```
    PROCEDURE Assign (XA, YA, XB, YB: Sw_Integer);
```

```
END;
```

TRect.Empty

Declaration: Function TRect.Empty: Boolean;

Description: Empty returns True if the rectangle defined by the corner points A, B has zero or negative surface.

Errors: None.

See also: TRect.Equals ([286](#)), TRect.Contains ([287](#))

```
Program ex1;

{ Program to demonstrate TRect.Empty }

Uses objects;

Var ARect, BRect : TRect;
    P : TPoint;

begin
  With ARect.A do
    begin
      X:=10;
      Y:=10;
    end;
  With ARect.B do
    begin
      X:=20;
      Y:=20;
    end;
  { Offset B by (5,5) }
  With BRect.A do
    begin
      X:=15;
      Y:=15;
    end;
  With BRect.B do
    begin
      X:=25;
      Y:=25;
    end;
  { Point }
  With P do
    begin
      X:=15;
      Y:=15;
    end;
  Writeln ( 'A_empty_', ARect.Empty);
  Writeln ( 'B_empty_', BRect.Empty);
  Writeln ( 'A_Equals_B_', ARect.Equals(BRect));
  Writeln ( 'A_Contains_(15,15)_', ARect.Contains(P));
end.
```

TRect.Equals

Declaration: Function TRect.Equals (R: TRect): Boolean;

Description: `Equals` returns `True` if the rectangle has the same corner points A, B as the rectangle R, and `False` otherwise.

Errors: None.

See also: `Empty` ([286](#)), `Contains` ([287](#))

For an example, see `TRect.Empty` ([286](#))

TRect.Contains

Declaration: `Function TRect.Contains (P: TPoint): Boolean;`

Description: `Contains` returns `True` if the point P is contained in the rectangle (including borders), `False` otherwise.

Errors: None.

See also: `Intersect` ([288](#)), `Equals` ([286](#))

TRect.Copy

Declaration: `Procedure TRect.Copy (R: TRect);`

Description: Assigns the rectangle R to the object. After the call to `Copy`, the rectangle R has been copied to the object that invoked `Copy`.

Errors: None.

See also: `Assign` ([290](#))

```
Program ex2;

{ Program to demonstrate TRect.Copy }

Uses objects;

Var ARect, BRect, CRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  CRect.Copy(ARect);
  If ARect.Equals(CRect) Then
    WriteLn ( 'ARect_equals_CRect' )
  Else
    WriteLn ( 'ARect_does_not_equal_CRect_' );
end.
```

TRect.Union

Declaration: `Procedure TRect.Union (R: TRect);`

Description: `Union` enlarges the current rectangle so that it becomes the union of the current rectangle with the rectangle R.

Errors: None.

See also: [Intersect \(288\)](#)

```
Program ex3;

{ Program to demonstrate TRect.Union }

Uses objects;

Var ARect, BRect, CRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is union of ARect and BRect }
  CRect.Assign(10,10,25,25);
  { Calculate it explicitly }
  ARect.Union(BRect);
  If ARect.Equals(CRect) Then
    WriteLn ( 'ARect_equals_CRect' )
  Else
    WriteLn ( 'ARect_does_not_equal_CRect_' );
end.
```

TRect.Intersect

Declaration: Procedure TRect.Intersect (R: TRect);

Description: Intersect makes the intersection of the current rectangle with R. If the intersection is empty, then the rectangle is set to the empty rectangle at coordinate (0,0).

Errors: None.

See also: [Union \(287\)](#)

```
Program ex4;

{ Program to demonstrate TRect.Intersect }

Uses objects;

Var ARect, BRect, CRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is intersection of ARect and BRect }
  CRect.Assign(15,15,20,20);
  { Calculate it explicitly }
  ARect.Intersect(BRect);
  If ARect.Equals(CRect) Then
    WriteLn ( 'ARect_equals_CRect' )
  Else
```

```
    WriteLn ( ' ARect_does_not_equal_CRect_' );
    BRect.Assign (25,25,30,30);
    ARect.Intersect (BRect);
    If ARect.Empty Then
        WriteLn ( ' ARect_is_empty' );
end.
```

TRect.Move

Declaration: Procedure TRect.Move (ADX, ADY: Sw_Integer);

Description: Move moves the current rectangle along a vector with components (ADX, ADY). It adds ADX to the X-coordinate of both corner points, and ADY to both end points.

Errors: None.

See also: Grow ([289](#))

```
Program ex5;

{ Program to demonstrate TRect.Move }

Uses objects;

Var ARect, BRect : TRect;

begin
    ARect.Assign (10,10,20,20);
    ARect.Move(5,5);
    // Brect should be where new ARect is .
    BRect.Assign (15,15,25,25);
    If ARect.Equals (BRect) Then
        WriteLn ( ' ARect_equals_BRect' )
    Else
        WriteLn ( ' ARect_does_not_equal_BRect_' );
end.
```

TRect.Grow

Declaration: Procedure TRect.Grow (ADX, ADY: Sw_Integer);

Description: Grow expands the rectangle with an amount ADX in the X direction (both on the left and right side of the rectangle, thus adding a length 2*ADX to the width of the rectangle), and an amount ADY in the Y direction (both on the top and the bottom side of the rectangle, adding a length 2*ADY to the height of the rectangle).

ADX and ADY can be negative. If the resulting rectangle is empty, it is set to the empty rectangle at (0, 0).

Errors: None.

See also: Move ([289](#)).

```
Program ex6;  
  
{ Program to demonstrate TRect.Grow }  
  
Uses objects;  
  
Var ARect, BRect : TRect;  
  
begin  
  ARect.Assign(10,10,20,20);  
  ARect.Grow(5,5);  
  // Brect should be where new ARect is .  
  BRect.Assign(5,5,25,25);  
  If ARect.Equals(BRect) Then  
    WriteIn ( ' ARect_equals_BRect' )  
  Else  
    WriteIn ( ' ARect_does_not_equal_BRect_' );  
end.
```

TRect.Assign

Declaration: Procedure TRect.Assign (XA, YA, XB, YB: Sw_Integer);

Description: Assign sets the corner points of the rectangle to (XA, YA) and (Xb, Yb).

Errors: None.

See also: Copy ([287](#))

For an example, see TRect.Copy ([287](#)).

15.5 TObject

The full declaration of the TObject type is:

```
TYPE  
  TObject = OBJECT  
    CONSTRUCTOR Init;  
    PROCEDURE Free;  
    DESTRUCTOR Done;Virtual;  
  END;  
  PObject = ^TObject;
```

TObject.Init

Declaration: Constructor TObject.Init;

Description: Instantiates a new object of type TObject. It fills the instance up with Zero bytes.

Errors: None.

See also: Free ([291](#)), Done ([291](#))

For an example, see Free ([291](#))

TObject.Free

Declaration: Procedure TObject.Free;

Description: Free calls the destructor of the object, and releases the memory occupied by the instance of the object.

Errors: No checking is performed to see whether `self` is `nil` and whether the object is indeed allocated on the heap.

See also: Init ([290](#)), Done ([291](#))

```
program ex7;

{ Program to demonstrate the TObject.Free call }

Uses Objects;

Var O : PObject;

begin
  Writeln ( ' Memavail _:_', Memavail);
  // Allocate memory for object.
  O:=New(PObject, Init );
  Writeln ( ' Memavail _:_', Memavail);
  // Free memory of object.
  O^.free;
  Writeln ( ' Memavail _:_', Memavail);
end.
```

TObject.Done

Declaration: Destructor TObject.Done;Virtual;

Description: Done, the destructor of TObject does nothing. It is mainly intended to be used in the TObject.Free ([291](#)) method.

The destructore Done does not free the memory occupied by the object.

Errors: None.

See also: Free ([291](#)), Init ([290](#))

```
program ex8;

{ Program to demonstrate the TObject.Done call }

Uses Objects;

Var O : PObject;

begin
  Writeln ( ' Memavail _:_', Memavail);
  // Allocate memory for object.
  O:=New(PObject, Init );
  Writeln ( ' Memavail _:_', Memavail);
  O^.Done;
  Writeln ( ' Memavail _:_', Memavail);
end.
```

15.6 TStream

The TStream object is the ancestor for all streaming objects, i.e. objects that have the capability to store and retrieve data.

It defines a number of methods that are common to all objects that implement streaming, many of them are virtual, and are only implemented in the descendant types.

Programs should not instantiate objects of type TStream directly, but instead instantiate a descendant type, such as TDosStream, TMemoryStream.

This is the full declaration of the TStream object:

TYPE

```
TStream = OBJECT (TObject)
    Status      : Integer; { Stream status }
    ErrorInfo   : Integer; { Stream error info }
    StreamSize  : LongInt; { Stream current size }
    Position    : LongInt; { Current position }
    FUNCTION Get: PObject;
    FUNCTION StrRead: PChar;
    FUNCTION GetPos: Longint; Virtual;
    FUNCTION GetSize: Longint; Virtual;
    FUNCTION ReadStr: PString;
    PROCEDURE Open (OpenMode: Word); Virtual;
    PROCEDURE Close; Virtual;
    PROCEDURE Reset;
    PROCEDURE Flush; Virtual;
    PROCEDURE Truncate; Virtual;
    PROCEDURE Put (P: PObject);
    PROCEDURE StrWrite (P: PChar);
    PROCEDURE WriteStr (P: PString);
    PROCEDURE Seek (Pos: LongInt); Virtual;
    PROCEDURE Error (Code, Info: Integer); Virtual;
    PROCEDURE Read (Var Buf; Count: Sw_Word); Virtual;
    PROCEDURE Write (Var Buf; Count: Sw_Word); Virtual;
    PROCEDURE CopyFrom (Var S: TStream; Count: Longint);
END;
PStream = ^TStream;
```

TStream.Get

Declaration: Function TStream.Get : PObject;

Description: Get reads an object definition from a stream, and returns a pointer to an instance of this object.

Errors: On error, TStream.Status is set, and NIL is returned.

See also: Put ([296](#))

Program ex9;

{ Program to demonstrate TStream.Get and TStream.Put }

Uses Objects, MyObject; *{ Definition and registration of TMyObject }*

```
Var Obj : PMyObject;
    S : PStream;

begin
  Obj:=New(PMyObject, Init );
  Obj^. SetField ($1111) ;
  Writeln ( ' Field_value _:_', Obj^. GetField );
  { Since Stream is an abstract type, we instantiate a TMemoryStream }
  S:=New(PMemoryStream, Init (100,10));
  S^. Put( Obj);
  Writeln ( ' Disposing_object ' );
  S^. Seek(0);
  Dispose( Obj, Done);
  Writeln ( ' Reading_object ' );
  Obj:=PMyObject(S^. Get);
  Writeln ( ' Field_Value _:_', Obj^. GetField );
  Dispose( Obj, Done);
end.
```

TStream.StrRead

Declaration: Function TStream.StrRead: PChar;

Description: StrRead reads a string from the stream, allocates memory for it, and returns a pointer to a null-terminated copy of the string on the heap.

Errors: On error, Nil is returned.

See also: StrWrite ([297](#)), ReadStr ([295](#))

```
Program ex10;

{
  Program to demonstrate the TStream.StrRead TStream.StrWrite functions
}

Uses objects;

Var P : PChar;
    S : PStream;

begin
  P:= ' Constant_Pchar_string ' ;
  Writeln ( ' Writing _to _stream _:_', P, ' ' );
  S:=New(PMemoryStream, Init (100,10));
  S^. StrWrite (P);
  S^. Seek(0);
  P:= Nil ;
  P:=S^. StrRead ;
  Dispose ( S, Done);
  Writeln ( ' Read_from _stream _:_', P, ' ' );
  Freemem(P, Strlen (P)+1);
end.
```

TStream.GetPos

Declaration: TStream.GetPos : Longint; Virtual;

Description: If the stream's status is stOk, GetPos returns the current position in the stream. Otherwise it returns -1

Errors: -1 is returned if the status is an error condition.

See also: Seek ([297](#)), GetSize ([294](#))

```
Program ex11;

{ Program to demonstrate the TStream.GetPos function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L:= 'Some_kind_of_string ' ;
  S:=New(PMemoryStream, Init (100,10));
  Writeln ( ' Stream_position_before_write :_', S^. GetPos);
  S^. WriteStr (@L);
  Writeln ( ' Stream_position_after_write :_', S^. GetPos);
  Dispose(S, Done);
end.
```

TStream.GetSize

Declaration: Function TStream.GetSize: Longint; Virtual;

Description: If the stream's status is stOk then GetSize returns the size of the stream, otherwise it returns -1.

Errors: -1 is returned if the status is an error condition.

See also: Seek ([297](#)), GetPos ([294](#))

```
Program ex12;

{ Program to demonstrate the TStream.GetSize function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L:= 'Some_kind_of_string ' ;
  S:=New(PMemoryStream, Init (100,10));
  Writeln ( ' Stream_size_before_write :_', S^. GetSize);
  S^. WriteStr (@L);
  Writeln ( ' Stream_size_after_write :_', S^. GetSize);
  Dispose(S, Done);
end.
```

TStream.ReadStr

Declaration: Function TStream.ReadStr: PString;

Description: ReadStr reads a string from the stream, copies it to the heap and returns a pointer to this copy.
The string is saved as a pascal string, and hence is NOT null terminated.

Errors: On error (e.g. not enough memory), Nil is returned.

See also: StrRead ([293](#))

Program ex13;

```
{  
Program to demonstrate the TStream.ReadStr TStream.WriteStr functions  
}
```

Uses objects;

Var P : PString;
 L : **String**;
 S : PStream;

begin

```
  L:= ' Constant_string_line ' ;  
  Writeln ( ' Writing_to_stream_:_' , L, '' );  
  S:=New(PMemoryStream, Init (100,10));  
  S^. WriteStr (@L);  
  S^. Seek(0);  
  P:=S^. ReadStr;  
  L:=P^;  
  DisposeStr (P);  
  Dispose ( S, Done);  
  Writeln ( ' Read_from_stream_:_' , L, '' );
```

end.

TStream.Open

Declaration: Procedure TStream.Open (OpenMode: Word); Virtual;

Description: Open is an abstract method, that should be overridden by descendent objects. Since opening a stream depends on the stream's type this is not surprising.

Errors: None.

See also: Close ([295](#)), Reset ([296](#))

For an example, see TDosStream.Open ([302](#)).

TStream.Close

Declaration: Procedure TStream.Close; Virtual;

Description: Close is an abstract method, that should be overridden by descendent objects. Since Closing a stream depends on the stream's type this is not surprising.

Errors: None.

See also: [Open \(295\)](#), [Reset \(296\)](#)

for an example, see [TDosStream.Open \(302\)](#).

TStream.Reset

Declaration: `PROCEDURE TStream.Reset;`

Description: `Reset` sets the stream's status to 0, as well as the `ErrorInfo`

Errors: None.

See also: [Open \(295\)](#), [Close \(295\)](#)

TStream.Flush

Declaration: `Procedure TStream.Flush; Virtual;`

Description: `Flush` is an abstract method that should be overridden by descendent objects. It serves to enable the programmer to tell streams that implement a buffer to clear the buffer.

Errors: None.

See also: [Truncate \(296\)](#)

for an example, see [TBufStream.Flush \(305\)](#).

TStream.Truncate

Declaration: `Procedure TStream.Truncate; Virtual;`

Description: `Truncate` is an abstract procedure that should be overridden by descendent objects. It serves to enable the programmer to truncate the size of the stream to the current file position.

Errors: None.

See also: [Seek \(297\)](#)

For an example, see [TDosStream.Truncate \(301\)](#).

TStream.Put

Declaration: `Procedure TStream.Put (P: PObject);`

Description: `Put` writes the object pointed to by `P`. `P` should be non-nil. The object type must have been registered with [RegisterType \(283\)](#).

After the object has been written, it can be read again with [Get \(292\)](#).

Errors: No check is done whether `P` is `Nil` or not. Passing `Nil` will cause a run-time error 216 to be generated. If the object has not been registered, the status of the stream will be set to `stPutError`.

See also: [Get \(292\)](#)

For an example, see [TStream.Get \(292\)](#);

TStream.StrWrite

Declaration: Procedure TStream.StrWrite (P: PChar);

Description: StrWrite writes the null-terminated string P to the stream. P can only be 65355 bytes long.

Errors: None.

See also: WriteStr ([297](#)), StrRead ([293](#)), ReadStr ([295](#))

For an example, see TStream.StrRead ([293](#)).

TStream.WriteString

Declaration: Procedure TStream.WriteString (P: PString);

Description: StrWrite writes the pascal string pointed to by P to the stream.

Errors: None.

See also: StrWrite ([297](#)), StrRead ([293](#)), ReadStr ([295](#))

For an example, see TStream.ReadStr ([295](#)).

TStream.Seek

Declaration: PROCEDURE TStream.Seek (Pos: LongInt); Virtual;

Description: Seek sets the position to POS. This position is counted from the beginning, and is zero based. (i.e. seek(0) sets the position pointer on the first byte of the stream)

Errors: If Pos is larger than the stream size, Status is set to StSeekError.

See also: GetPos ([294](#)), GetSize ([294](#))

For an example, see TDosStream.Seek ([301](#)).

TStream.Error

Declaration: Procedure TStream.Error (Code, Info: Integer); Virtual;

Description: Error sets the stream's status to Code and ErrorInfo to Info. If the StreamError procedural variable is set, Error executes it, passing Self as an argument.

This method should not be called directly from a program. It is intended to be used in descendent objects.

Errors: None.

See also:

TStream.Read

Declaration: Procedure TStream.Read (Var Buf; Count: Sw_Word); Virtual;

Description: Read is an abstract method that should be overridden by descendent objects.

Read reads Count bytes from the stream into Buf. It updates the position pointer, increasing it's value with Count. Buf must be large enough to contain Count bytes.

Errors: No checking is done to see if Buf is large enough to contain Count bytes.

See also: Write ([298](#)), ReadStr ([295](#)), StrRead ([293](#))

```
program ex18;

{ Program to demonstrate the TStream.Read method }

Uses Objects;

Var Buf1, Buf2 : Array[1..1000] of Byte;
    I : longint;
    S : PMemoryStream;

begin
  For I:=1 to 1000 do
    Buf1[I]:=Random(1000);
  Buf2:=Buf1;
  S:=New(PMemoryStream, Init (100,10));
  S^.Write (Buf1, SizeOf (Buf1));
  S^.Seek(0);
  For I:=1 to 1000 do
    Buf1[I]:=0;
  S^.Read (Buf1, SizeOf (Buf1));
  For I:=1 to 1000 do
    If Buf1[I]<>Buf2[I] then
      Writeln ( ' Buffer differs at position ', I );
  Dispose (S, Done);
end.
```

TStream.Write

Declaration: Procedure TStream.Write (Var Buf; Count: Sw_Word); Virtual;

Description: Write is an abstract method that should be overridden by descendent objects.

Write writes Count bytes to the stream from Buf. It updates the position pointer, increasing it's value with Count.

Errors: No checking is done to see if Buf actually contains Count bytes.

See also: Read ([298](#)), WriteStr ([297](#)), StrWrite ([297](#))

For an example, see TStream.Read ([298](#)).

TStream.CopyFrom

Declaration: Procedure TStream.CopyFrom (Var S: TStream; Count: Longint);

Description: CopyFrom reads Count bytes from stream S and stores them in the current stream. It uses the Read (298) method to read the data, and the Write (298) method to write in the current stream.

Errors: None.

See also: Read (298), Write (298)

```
Program ex19;

{ Program to demonstrate the TStream.CopyFrom function }

Uses objects;

Var P : PString;
    L : String;
    S1,S2 : PStream;

begin
  L:= ' Constant_string_line ';
  Writeln ( ' Writing_to_stream_1_',L, '' );
  S1:=New(PMemoryStream, Init (100,10));
  S2:=New(PMemoryStream, Init (100,10));
  S1^. WriteStr (@L);
  S1^. Seek(0);
  Writeln ( ' Copying_contents_of_stream_1_to_stream_2' );
  S2^. Copyfrom(S1^, S1^. GetSize);
  S2^. Seek(0);
  P:= S2^. ReadStr;
  L:=P^;
  DisposeStr(P);
  Dispose ( S1, Done);
  Dispose ( S2, Done);
  Writeln ( ' Read_from_stream_2_',L, '' );
end.
```

15.7 TDosStream

TDosStream is a stream that stores it's contents in a file. it overrides a couple of methods of TStream for this.

In addition to the fields inherited from TStream (see section 15.6, page 292), there are some extra fields, that describe the file. (mainly the name and the OS file handle)

No buffering in memory is done when using TDosStream. All data are written directly to the file. For a stream that buffers in memory, see section 15.8, page 303.

Here is the full declaration of the TDosStream object:

```
TYPE
  TDosStream = OBJECT (TStream)
    Handle: THandle; { DOS file handle }
    FName : AsciiZ; { AsciiZ filename }
    CONSTRUCTOR Init (FileName: FNameStr; Mode: Word);
    DESTRUCTOR Done; Virtual;
    PROCEDURE Close; Virtual;
    PROCEDURE Truncate; Virtual;
```

```
PROCEDURE Seek (Pos: LongInt); Virtual;  
PROCEDURE Open (OpenMode: Word); Virtual;  
PROCEDURE Read (Var Buf; Count: Sw_Word); Virtual;  
PROCEDURE Write (Var Buf; Count: Sw_Word); Virtual;  
END;  
PDosStream = ^TDosStream;
```

TDosStream.Init

Declaration: Constructor `Init (FileName: FNameStr; Mode: Word);`

Description: `Init` instantiates an instance of `TDosStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

stCreateCreates a new file.

stOpenReadRead access only.

stOpenWriteWrite access only.

stOpenReadRead and write access.

Errors: On error, `Status` is set to `stInitError`, and `ErrorInfo` is set to the DOS error code.

See also: [Done \(300\)](#)

For an example, see `TDosStream.Truncate` ([301](#)).

TDosStream.Done

Declaration: Destructor `TDosStream.Done; Virtual;`

Description: `Done` closes the file if it was open and cleans up the instance of `TDosStream`.

Errors: None.

See also: `Init` ([300](#)), `Close` ([300](#))

for an example, see e.g. `TDosStream.Truncate` ([301](#)).

TDosStream.Close

Declaration: Procedure `TDosStream.Close; Virtual;`

Description: `Close` closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` ([300](#)) it does not clean up the instance of `TDosStream`

Errors: None.

See also: `TStream.Close` ([295](#)), `Init` ([300](#)), `Done` ([300](#))

For an example, see `TDosStream.Open` ([302](#)).

TDosStream.Truncate

Declaration: Procedure TDosStream.Truncate; Virtual;

Description: If the status of the stream is `stOK`, then `Truncate` tries to truncate the stream size to the current file position.

Errors: If an error occurs, the stream's status is set to `stError` and `ErrorInfo` is set to the OS error code.

See also: `TStream.Truncate` ([296](#)), `GetSize` ([294](#))

```
Program ex16;

{ Program to demonstrate the TStream.Truncate method }

Uses Objects;

Var L : String;
    P : PString;
    S : PDosStream; { Only one with Truncate implemented. }

begin
  L := 'Some_constant_string';
  { Buffer size of 100 }
  S := New(PDosStream, Init('test.dat', stcreate));
  Writeln (' Writing ', L, ' to stream with handle ', S^.Handle);
  S^.WriteStr(@L);
  S^.WriteStr(@L);
  { Close calls flush first }
  S^.Close;
  S^.Open(stOpen);
  Writeln (' Size of stream is ', S^.GetSize);
  P := S^.ReadStr;
  L := P^;
  DisposeStr(P);
  Writeln (' Read ', L, ' from stream with handle ', S^.Handle);
  S^.Truncate;
  Writeln (' Truncated stream Size is ', S^.GetSize);
  S^.Close;
  Dispose(S, Done);
end.
```

TDosStream.Seek

Declaration: Procedure TDosStream.Seek (Pos: LongInt); Virtual;

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `POS`. `POS` is a zero-based offset, counted from the beginning of the file.

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` ([297](#)), `GetPos` ([294](#))

```
Program ex17;

{ Program to demonstrate the TStream.Seek method }

Uses Objects;

Var L : String;
      Marker : Word;
      P : PString;
      S : PDosStream;

begin
  L:= 'Some_constant_string';
  { Buffer size of 100 }
  S:=New(PDosStream, Init ( ' test . dat', stcreate ));
  Writeln ( ' Writing "', L, '" to _stream.' );
  S^. WriteStr (@L);
  Marker:=S^. GetPos;
  Writeln ( ' Set _marker_at_', Marker);
  L:= 'Some_other_constant_String';
  Writeln ( ' Writing "', L, '" to _stream.' );
  S^. WriteStr (@L);
  S^. Close;
  S^. Open ( stOpenRead);
  Writeln ( ' Size_of _stream_is_', S^. GetSize );
  Writeln ( ' Seeking_to _marker' );
  S^. Seek(Marker);
  P:=S^. ReadStr;
  L:=P^;
  DisposeStr(P);
  Writeln ( ' Read "', L, '" from _stream.' );
  S^. Close;
  Dispose ( S, Done);
end.
```

TDosStream.Open

Declaration: Procedure TDosStream.Open (OpenMode: Word); Virtual;

Description: If the stream's status is stOK, and the stream is closed then Open re-opens the file stream with mode OpenMode. This call can be used after a Close (300) call.

Errors: If an error occurs when re-opening the file, then Status is set to stOpenError, and the OS error code is stored in ErrorInfo

See also: TStream.Open (295), Close (300)

```
Program ex14;

{ Program to demonstrate the TStream.Close method }

Uses Objects;

Var L : String;
      P : PString;
      S : PDosStream; { Only one with Close implemented. }
```



```
begin
  L:= 'Some_constant_string';
  S:=New(PDosStream, Init('test.dat', stcreate));
  Writeln('Writing ', L, ' to stream with handle ', S^.Handle);
  S^.WriteStr(@L);
  S^.Close;
  Writeln('Closed stream. File handle is ', S^.Handle);
  S^.Open(stOpenRead);
  P:=S^.ReadStr;
  L:=P^;
  DisposeStr(P);
  Writeln('Read ', L, ' from stream with handle ', S^.Handle);
  S^.Close;
  Dispose(S, Done);
end.
```

TDosStream.Read

Declaration: Procedure TDosStream.Read (Var Buf; Count: Sw_Word); Virtual;

Description: If the Stream is open and the stream status is stOK then Read will read Count bytes from the stream and place them in Buf.

Errors: In case of an error, Status is set to StReadError, and ErrorInfo gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: TStream.Read ([298](#)), Write ([303](#))

For an example, see TStream.Read ([298](#)).

TDosStream.Write

Declaration: Procedure TDosStream.Write (Var Buf; Count: Sw_Word); Virtual;

Description: If the Stream is open and the stream status is stOK then Write will write Count bytes from Buf and place them in the stream.

Errors: In case of an error, Status is set to StWriteError, and ErrorInfo gets the OS specific error.

See also: TStream.Write ([298](#)), Read ([303](#))

For an example, see TStream.Read ([298](#)).

15.8 TBufStream

Bufstream implements a buffered file stream. That is, all data written to the stream is written to memory first. Only when the buffer is full, or on explicit request, the data is written to disk.

Also, when reading from the stream, first the buffer is checked if there is any unread data in it. If so, this is read first. If not the buffer is filled again, and then the data is read from the buffer.

The size of the buffer is fixed and is set when constructing the file.

This is useful if you need heavy throughput for your stream, because it speeds up operations.

TYPE

```
TBufStream = OBJECT (TDosStream)
    LastMode: Byte;      { Last buffer mode }
    BufSize : Sw_Word;   { Buffer size }
    BufPtr  : Sw_Word;   { Buffer start }
    BufEnd  : Sw_Word;   { Buffer end }
    Buffer   : PByteArray; { Buffer allocated }
    CONSTRUCTOR Init (FileName: FNameStr; Mode, Size: Word);
    DESTRUCTOR Done; Virtual;
    PROCEDURE Close; Virtual;
    PROCEDURE Flush; Virtual;
    PROCEDURE Truncate; Virtual;
    PROCEDURE Seek (Pos: LongInt); Virtual;
    PROCEDURE Open (OpenMode: Word); Virtual;
    PROCEDURE Read (Var Buf; Count: Sw_Word); Virtual;
    PROCEDURE Write (Var Buf; Count: Sw_Word); Virtual;
END;
PBufStream = ^TBufStream;
```

TBufStream.Init

Declaration: Constructor Init (FileName: FNameStr; Mode, Size: Word);

Description: Init instantiates an instance of TBufStream. The name of the file that contains (or will contain) the data of the stream is given in FileName. The Mode parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

stCreate Creates a new file.

stOpenRead Read access only.

stOpenWrite Write access only.

stOpen Read and write access.

The Size parameter determines the size of the buffer that will be created. It should be different from zero.

Errors: On error, Status is set to stInitError, and ErrorInfo is set to the DOS error code.

See also: TDosStream.Init (300), Done (304)

For an example see TBufStream.Flush (305).

TBufStream.Done

Declaration: Destructor TBufStream.Done; Virtual;

Description: Done flushes and closes the file if it was open and cleans up the instance of TBufStream.

Errors: None.

See also: TDosStream.Done (300), Init (304), Close (305)

For an example see TBufStream.Flush (305).

TBufStream.Close

Declaration: POCEDURE TBufStream.Close; Virtual;

Description: Close flushes and closes the file if it was open, and sets Handle to -1. Contrary to Done (304) it does not clean up the instance of TBufStream

Errors: None.

See also: TStream.Close (295), Init (304), Done (304)

For an example see TBufStream.Flush (305).

TBufStream.Flush

Declaration: POCEDURE TBufStream.Flush; Virtual;

Description: When the stream is in write mode, the contents of the buffer are written to disk, and the buffer position is set to zero.

When the stream is in read mode, the buffer position is set to zero.

Errors: Write errors may occur if the file was in write mode. see Write (307) for more info on the errors.

See also: TStream.Close (295), Init (304), Done (304)

Program ex15;

{ Program to demonstrate the TStream.Flush method }

Uses Objects;

Var L : **String**;
P : PString;
S : PBufStream; *{ Only one with Flush implemented. }*

begin

```
L := 'Some_constant_string';  
{ Buffer size of 100 }  
S := New(PBufStream, Init('test.dat', stcreate, 100));  
Writeln('Writing ', L, ' to stream with handle ', S^.Handle);  
S^.WriteStr(@L);  
{ At this moment, there is no data on disk yet. }  
S^.Flush;  
{ Now there is. }  
S^.WriteStr(@L);  
{ Close calls flush first }  
S^.Close;  
Writeln('Closed stream. File handle is ', S^.Handle);  
S^.Open(stOpenRead);  
P := S^.ReadStr;  
L := P^;  
DisposeStr(P);  
Writeln('Read ', L, ' from stream with handle ', S^.Handle);  
S^.Close;  
Dispose(S, Done);
```

end.

TBufStream.Truncate

Declaration: Procedure TBufStream.Truncate; Virtual;

Description: If the status of the stream is `stOK`, then `Truncate` tries to flush the buffer, and then truncates the stream size to the current file position.

Errors: Errors can be those of `Flush` (305) or `TDosStream.Truncate` (301).

See also: `TStream.Truncate` (296), `TDosStream.Truncate` (301), `GetSize` (294)

For an example, see `TDosStream.Truncate` (301).

TBufStream.Seek

Declaration: Procedure TBufStream.Seek (Pos: LongInt); Virtual;

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` (297), `GetPos` (294)

For an example, see `TStream.Seek` (297);

TBufStream.Open

Declaration: Procedure TBufStream.Open (OpenMode: Word); Virtual;

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` (305) call.

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` (295), `Close` (305)

For an example, see `TDosStream.Open` (302).

TBufStream.Read

Declaration: Procedure TBufStream.Read (Var Buf; Count: Sw_Word); Virtual;

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

`Read` will first try to read the data from the stream's internal buffer. If insufficient data is available, the buffer will be filled before continuing to read. This process is repeated until all needed data has been read.

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` (298), `Write` (307)

For an example, see `TStream.Read` (298).

TBufStream.Write

Declaration: Procedure TBufStream.Write (Var Buf; Count: Sw_Word); Virtual;

Description: If the Stream is open and the stream status is stOK then Write will write Count bytes from Buf and place them in the stream.

Write will first try to write the data to the stream's internal buffer. When the internal buffer is full, then the contents will be written to disk. This process is repeated until all data has been written.

Errors: In case of an error, Status is set to StWriteError, and ErrorInfo gets the OS specific error.

See also: TStream.Write ([298](#)), Read ([306](#))

For an example, see TStream.Read ([298](#)).

15.9 TMemoryStream

The TMemoryStream object implements a stream that stores its data in memory. The data is stored on the heap, with the possibility to specify the maximum amount of data, and the size of the memory blocks being used.

TYPE

```
TMemoryStream = OBJECT (TStream)
    BlkCount: Sw_Word;      { Number of segments }
    BlkSize : Word;         { Memory block size }
    MemSize : LongInt;      { Memory alloc size }
    BlkList : PPointerArray; { Memory block list }
    CONSTRUCTOR Init (ALimit: Longint; ABlockSize: Word);
    DESTRUCTOR Done;
    PROCEDURE Truncate;
    PROCEDURE Read (Var Buf; Count: Sw_Word);
    PROCEDURE Write (Var Buf; Count: Sw_Word);
END;
PMemoryStream = ^TMemoryStream;
```

Virtual;
Virtual;
Virtual;
Virtual;

TMemoryStream.Init

Declaration: Constructor TMemoryStream.Init (ALimit: Longint; ABlockSize: Word);

Description: Init instantiates a new TMemoryStream object. The memorystreamobject will initially allocate at least ALimit bytes memory, divided into memory blocks of size ABlockSize. The number of blocks needed to get to ALimit bytes is rounded up.

By default, the number of blocks is 1, and the size of a block is 8192. This is selected if you specify 0 as the blocksize.

Errors: If the stream cannot allocate the initial memory needed for the memory blocks, then the stream's status is set to stInitError.

See also: Done ([308](#))

For an example, see e.g TStream.CopyFrom ([298](#)).

TMemoryStream.Done

Declaration: Destructor TMemoryStream.Done; Virtual;

Description: Done releases the memory blocks used by the stream, and then cleans up the memory used by the stream object itself.

Errors: None.

See also: Init ([307](#))

For an example, see e.g TStream.CopyFrom ([298](#)).

TMemoryStream.Truncate

Declaration: Procedure TMemoryStream.Truncate; Virtual;

Description: Truncate sets the size of the memory stream equal to the current position. It de-allocates any memory-blocks that are no longer needed, so that the new size of the stream is the current position in the stream, rounded up to the first multiple of the stream blocksize.

Errors: If an error occurs during memory de-allocation, the stream's status is set to stError

See also: TStream.Truncate ([296](#))

```
Program ex20;

{ Program to demonstrate the TMemoryStream.Truncate method }

Uses Objects;

Var L : String;
    P : PString;
    S : PMemoryStream;
    I, InitMem : Longint;

begin
  InitMem := Memavail;
  L := 'Some_constant_string';
  { Buffer size of 100 }
  S := New(PMemoryStream, Init(1000,100));
  Writeln('Free_memory_', Memavail);
  Writeln('Writing_100_times_', L, ' to stream. ');
  For I := 1 to 100 do
    S^.WriteStr(@L);
  Writeln('Finished_ Free_memory_', Memavail);
  S^.Seek(100);
  S^.Truncate;
  Writeln('Truncated_at_byte_100_ Free_memory_', Memavail);
  Dispose(S, Done);
  Writeln('Finished_ Lost_', InitMem - Memavail, ' Bytes. ');
end.
```

TMemoryStream.Read

Declaration: Procedure Read (Var Buf; Count: Sw_Word); Virtual;

Description: Read reads Count bytes from the stream to Buf. It updates the position of the stream.

Errors: If there is not enough data available, no data is read, and the stream's status is set to `stReadError`.

See also: `TStream.Read`, `Write` (309)

For an example, see `TStream.Read` (298).

TMemoryStream.Write

Declaration: `Procedure Write (Var Buf; Count: Sw_Word); Virtual;`

Description: Write copies Count bytes from Buf to the stream. It updates the position of the stream.

If not enough memory is available to hold the extra Count bytes, then the stream will try to expand, by allocating as much blocks with size `BlkSize` (as specified in the constructor call `Init` (307)) as needed.

Errors: If the stream cannot allocate more memory, then the status is set to `stWriteError`

See also: `TStream.Write` (298), `Read` (308)

For an example, see `TStream.Read` (298).

15.10 TCollection

The `TCollection` object manages a collection of pointers or objects. It also provides a series of methods to manipulate these pointers or objects.

Whether or not objects are used depends on the kind of calls you use. All kinds come in 2 flavors, one for objects, one for pointers.

This is the full declaration of the `TCollection` object:

TYPE

```
TItemList = Array [0..MaxCollectionSize - 1] Of Pointer;
PItemList = ^TItemList;

TCollection = OBJECT (TObject)
  Items: PItemList; { Item list pointer }
  Count: Sw_Integer; { Item count }
  Limit: Sw_Integer; { Item limit count }
  Delta: Sw_Integer; { Inc delta size }
  Constructor Init (ALimit, ADelta: Sw_Integer);
  Constructor Load (Var S: TStream);
  Destructor Done; Virtual;
  Function At (Index: Sw_Integer): Pointer;
  Function IndexOf (Item: Pointer): Sw_Integer; Virtual;
  Function GetItem (Var S: TStream): Pointer; Virtual;
  Function LastThat (Test: Pointer): Pointer;
  Function FirstThat (Test: Pointer): Pointer;
  Procedure Pack;
  Procedure FreeAll;
  Procedure DeleteAll;
  Procedure Free (Item: Pointer);
```

```
Procedure Insert (Item: Pointer); Virtual;  
Procedure Delete (Item: Pointer);  
Procedure AtFree (Index: Sw_Integer);  
Procedure FreeItem (Item: Pointer); Virtual;  
Procedure AtDelete (Index: Sw_Integer);  
Procedure ForEach (Action: Pointer);  
Procedure SetLimit (ALimit: Sw_Integer); Virtual;  
Procedure Error (Code, Info: Integer); Virtual;  
Procedure AtPut (Index: Sw_Integer; Item: Pointer);  
Procedure AtInsert (Index: Sw_Integer; Item: Pointer);  
Procedure Store (Var S: TStream);  
Procedure PutItem (Var S: TStream; Item: Pointer); Virtual;  
END;  
PCollection = ^TCollection;
```

TCollection.Init

Declaration: Constructor TCollection.Init (ALimit, ADelta: Sw_Integer);

Description: Init initializes a new instance of a collection. It sets the (initial) maximum number of items in the collection to ALimit. ADelta is the increase size : The number of memory places that will be allocated in case ALimit is reached, and another element is added to the collection.

Errors: None.

See also: Load ([310](#)), Done ([311](#))

For an example, see TCollection.ForEach ([320](#)).

TCollection.Load

Declaration: Constructor TCollection.Load (Var S: TStream);

Description: Load initializes a new instance of a collection. It reads from stream S the item count, the item limit count, and the increase size. After that, it reads the specified number of items from the stream.

Errors: Errors returned can be those of GetItem ([313](#)).

See also: Init ([310](#)), GetItem ([313](#)), Done ([311](#)).

Program ex22;

{ Program to demonstrate the TCollection.Load method }

Uses Objects, MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
M : PMyObject;
I : Longint;
S : PMemoryStream;

begin

C:=New(PCollection, Init(100,10));
For I:=1 to 100 do
begin


```
M:=New(PMyObject, Init );
M^. SetField(100-I);
C^. Insert(M);
end;
Writeln ( ' Inserted _',C^. Count, '_ objects ' );
S:=New(PMemoryStream, Init (1000,10));
C^. Store(S^);
C^. FreeAll;
Dispose(C, Done);
S^. Seek(0);
C^. Load(S^);
Writeln ( ' Read_',C^. Count, '_ objects _from _stream .' );
Dispose(S, Done);
Dispose(C, Done);
end.
```

TCollection.Done

Declaration: Destructor TCollection.Done; Virtual;

Description: Done frees all objects in the collection, and then releases all memory occupied by the instance.

Errors: None.

See also: Init ([310](#)), FreeAll ([315](#))

For an example, see TCollection.ForEach ([320](#)).

TCollection.At

Declaration: Function TCollection.At (Index: Sw_Integer): Pointer;

Description: At returns the item at position Index.

Errors: If Index is less than zero or larger than the number of items in the collection, seepErrorTCollection.Error is called with coIndexError and Index as arguments, resulting in a run-time error.

See also: Insert ([317](#))

Program ex23;

{ Program to demonstrate the TCollection.At method }

Uses Objects, MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
M : PMyObject;
I : Longint;

begin
C:=New(PCollection , Init (100,10));
For I:=1 **to** 100 **do**
 begin
 M:=New(PMyObject, Init);
 M^. SetField(100-I);
 C^. Insert(M);

```
    end;  
    For I:=0 to C^.Count-1 do  
    begin  
        M:=C^.At(I);  
        Writeln ( ' Object _', i, '_has_field _:',M^.GetField );  
    end;  
    C^.FreeAll;  
    Dispose(C,Done);  
end.
```

TCollection.IndexOf

Declaration: Function TCollection.IndexOf (Item: Pointer): Sw_Integer; Virtual;

Description: IndexOf returns the index of Item in the collection. If Item isn't present in the collection, -1 is returned.

Errors:

See also:

```
Program ex24;  
  
{ Program to demonstrate the TCollection.IndexOf method }  
  
Uses Objects,MyObject; { For TMyObject definition and registration }  
  
Var C : PCollection;  
    M,Keep : PMyObject;  
    I : Longint;  
  
begin  
    Randomize;  
    C:=New( PCollection , Init (100,10));  
    Keep:=Nil;  
    For I:=1 to 100 do  
    begin  
        M:=New(PMyObject, Init );  
        M^.SetField (I-1);  
        If Random<0.1 then  
            Keep:=M;  
        C^.Insert (M);  
    end;  
    If Keep=Nil then  
    begin  
        Writeln ( ' Please_run_again._No_object_selected ' );  
        Halt (1);  
    end;  
    Writeln ( ' Selected_object_has_field _:',Keep^.GetField );  
    Write ( ' Selected_object_has_index _:',C^.IndexOf(Keep));  
    Writeln ( ' _should_match_it ' 's_field .' );  
    C^.FreeAll;  
    Dispose(C,Done);  
end.
```

TCollection.GetItem

Declaration: Function TCollection.GetItem (Var S: TStream): Pointer; Virtual;

Description: GetItem reads a single item off the stream S, and returns a pointer to this item. This method is used internally by the Load method, and should not be used directly.

Errors: Possible errors are the ones from TStream.Get ([292](#)).

See also: TStream.Get ([292](#)), seeplStoreTCollection.Store

TCollection.LastThat

Declaration: Function TCollection.LastThat (Test: Pointer): Pointer;

Description: This function returns the last item in the collection for which Test returns a non-nil result. Test is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: FirstThat ([314](#))

```
Program ex21;

{ Program to demonstrate the TCollection.Foreach method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;

Function CheckField (Dummy: Pointer; P : PMyObject) : Longint;

begin
  If P^.GetField<56 then
    Checkfield:=1
  else
    CheckField:=0;
end;

begin
  C:=New(PCollection, Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I);
      C^.Insert(M);
    end;
  Writeln ( ' Inserted ', C^.Count, ' objects ' );
  Writeln ( ' Last_one_for_which_Field<56_has_index_(should_be_54): ',
    C^.IndexOf(C^.LastThat (@CheckField)));
  C^.FreeAll;
  Dispose(C, Done);
end.
```

TCollection.FirstThat

Declaration: `Function TCollection.FirstThat (Test: Pointer): Pointer;`

Description: This function returns the first item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: [LastThat \(313\)](#)

```
Program ex21;

{ Program to demonstrate the TCollection.FirstThat method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;

Function CheckField (Dummy: Pointer; P : PMyObject) : Longint;

begin
    If P^.GetField > 56 then
        Checkfield := 1
    else
        CheckField := 0;
    end;

begin
    C := New( PCollection, Init (100, 10));
    For I := 1 to 100 do
        begin
            M := New( PMyObject, Init );
            M^.SetField (I);
            C^.Insert (M);
        end;
    Writeln ( ' Inserted ', C^.Count, ' objects ' );
    Writeln ( ' first one for which Field > 56 has index (should be 56) ',
        C^.IndexOf( C^.FirstThat ( @CheckField )) );
    C^.FreeAll;
    Dispose(C, Done);
end.
```

TCollection.Pack

Declaration: `Procedure TCollection.Pack;`

Description: `Pack` removes all `Nil` pointers from the collection, and adjusts `Count` to reflect this change. No memory is freed as a result of this call. In order to free any memory, you can call `SetLimit` with an argument of `Count` after a call to `Pack`.

Errors: None.

See also: [SetLimit \(321\)](#)

```
Program ex21;

{ Program to demonstrate the TCollection.FirstThat method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

Function CheckField (Dummy: Pointer; P : PMyObject) : Longint;

begin
  If P^.GetField > 56 then
    Checkfield := 1
  else
    CheckField := 0;
end;

begin
  C := New(PCollection, Init(100, 10));
  For I := 1 to 100 do
    begin
      M := New(PMyObject, Init);
      M^.SetField(I);
      C^.Insert(M);
    end;
  Writeln (' Inserted ', C^.Count, ' objects ');
  Writeln (' first one for which Field > 56 has index ',
    C^.IndexOf(C^.FirstThat(@CheckField)));
  C^.FreeAll;
  Dispose(C, Done);
end.
```

TCollection.FreeAll

Declaration: Procedure TCollection.FreeAll;

Description: FreeAll calls the destructor of each object in the collection. It doesn't release any memory occupied by the collection itself, but it does set Count to zero.

Errors:

See also: DeleteAll ([316](#)), FreeItem ([319](#))

```
Program ex28;

{ Program to demonstrate the TCollection.FreeAll method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I, InitMem : Longint;

begin
```

```
Randomize;
C:=New( PCollection , Init (120,10));
InitMem:=Memavail;
Writeln ( ' Initial _memory_:_', InitMem);
For I:=1 to 100 do
begin
M:=New( PMyObject, Init );
M^. SetField (I-1);
C^. Insert (M);
end;
Writeln ( ' Added_100_Items._Memory_available _:', Memavail);
Write ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
Write ( '( Should_be_100*', SizeOf(TMyObject));
Writeln ( '= ', 100*SizeOf(TMyObject), ' )' );
C^. FreeAll;
Writeln ( ' Freed_all_objects._Memory_available _:', Memavail);
Writeln ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
Dispose(C, Done);
end.
```

TCollection.DeleteAll

Declaration: Procedure TCollection.DeleteAll;

Description: DeleteAll deletes all elements from the collection. It just sets the Count variable to zero.
Contrary to FreeAll (315), DeleteAll doesn't call the destructor of the objects.

Errors: None.

See also: FreeAll (315), Delete (318)

```
Program ex29;

{
  Program to demonstrate the TCollection.DeleteAll method
  Compare with example 28, where FreeAll is used.
}

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I, InitMem : Longint;

begin
  Randomize;
  C:=New( PCollection , Init (120,10));
  InitMem:=Memavail;
  Writeln ( ' Initial _memory_:_', InitMem);
  For I:=1 to 100 do
begin
M:=New( PMyObject, Init );
M^. SetField (I-1);
C^. Insert (M);
end;
Writeln ( ' Added_100_Items._Memory_available _:', Memavail);
Write ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
```

```
Write    ('( Should_be_100*', SizeOf(TMyObject));
Writeln ('=', 100*SizeOf(TMyObject), ')');
C^. DeleteAll;
Writeln (' Deleted_all_objects .Memory_available _:', Memavail);
Writeln (' Lost _:', Initmem-Memavail, '_bytes .');
Dispose(C, Done);
end.
```

TCollection.Free

Declaration: Procedure TCollection.Free (Item: Pointer);

Description: Free Deletes Item from the collection, and calls the destructor Done of the object.

Errors: If the Item is not in the collection, Error will be called with coIndexError.

See also: FreeItem (319),

```
Program ex30;

{ Program to demonstrate the TCollection.Free method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I, InitMem : Longint;

begin
  Randomize;
  C:=New( PCollection, Init (120,10));
  InitMem:=Memavail;
  Writeln (' Initial_memory_:', InitMem);
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init );
      M^. SetField (I-1);
      C^. Insert (M);
    end;
  Writeln (' Added_100_Items .Memory_available _:', Memavail);
  Write (' Lost _:', Initmem-Memavail, '_bytes .');
  Write    ('( Should_be_100*', SizeOf(TMyObject));
  Writeln ('=', 100*SizeOf(TMyObject), ')');
  With C^ do
    While Count>0 do Free (At( Count-1));
  Writeln (' Freed_all_objects .Memory_available _:', Memavail);
  Writeln (' Lost _:', Initmem-Memavail, '_bytes .');
  Dispose(C, Done);
end.
```

TCollection.Insert

Declaration: Procedure TCollection.Insert (Item: Pointer); Virtual;

Description: Insert inserts Item in the collection. TCollection inserts this item at the end, but descendent objects may insert it at another place.

Errors: None.

See also: AtInsert ([322](#)), AtPut ([321](#)),

TCollection.Delete

Declaration: Procedure TCollection.Delete (Item: Pointer);

Description: Delete deletes Item from the collection. It doesn't call the item's destructor, though. For this the Free ([317](#)) call is provided.

Errors: If the Item is not in the collection, Error will be called with coIndexError.

See also: AtDelete ([319](#)), Free ([317](#))

```
Program ex31;

{ Program to demonstrate the TCollection.Delete method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I, InitMem : Longint;

begin
  Randomize;
  C:=New( PCollection , Init (120,10));
  InitMem:=Memavail;
  Writeln ( ' Initial _memory_:_', InitMem );
  For I:=1 to 100 do
    begin
      M:=New( PMyObject, Init );
      M^. SetField ( I -1);
      C^. Insert (M);
    end;
  Writeln ( ' Added_100_Items._Memory_available _:', Memavail);
  Write ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
  Write ( '( Should_be_100*_', SizeOf( TMyObject ));
  Writeln ( '=' , 100* SizeOf( TMyObject), ' ) ' );
  With C^ do
    While Count>0 do Delete ( At( Count-1));
  Writeln ( ' Freed_all_objects._Memory_available _:', Memavail);
  Writeln ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
  Dispose (C, Done);
end.
```

TCollection.AtFree

Declaration: Procedure TCollection.AtFree (Index: Sw_Integer);

Description: AtFree deletes the item at position Index in the collection, and calls the item's destructor if it is not Nil.

Errors: If Index isn't valid then Error ([321](#)) is called with CoIndexError.

See also: Free ([317](#)), AtDelete ([319](#))

```
Program ex32;

{ Program to demonstrate the TCollection.AtFree method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I, InitMem : Longint;

begin
  Randomize;
  C:=New(PCollection, Init (120,10));
  InitMem:=Memavail;
  Writeln ( ' Initial _memory_:_', InitMem );
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init );
      M^. SetField (I-1);
      C^. Insert (M);
    end;
  Writeln ( ' Added_100_Items._Memory_available _:_', Memavail );
  Write ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
  Write ( '( Should _be_100*', SizeOf(TMyObject));
  Writeln ( '= ', 100* SizeOf(TMyObject), ' )' );
  With C^ do
    While Count>0 do AtFree (Count-1);
  Writeln ( ' Freed_all _objects._Memory_available _:_', Memavail );
  Writeln ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
  Dispose(C, Done);
end.
```

TCollection.FreeItem

Declaration: Procedure TCollection.FreeItem (Item: Pointer); Virtual;

Description: FreeItem calls the destructor of Item if it is not nil.

This function is used internally by the TCollection object, and should not be called directly.

Errors: None.

See also: Free ([318](#)), seeplAtFreeTCollection.AtFree

TCollection.AtDelete

Declaration: Procedure TCollection.AtDelete (Index: Sw_Integer);

Description: AtDelete deletes the pointer at position Index in the collection. It doesn't call the object's destructor.

Errors: If Index isn't valid then Error ([321](#)) is called with CoIndexError.

See also: Delete ([318](#))

```
Program ex33;

{ Program to demonstrate the TCollection.Delete method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I, InitMem : Longint;

begin
  Randomize;
  C:=New(PCollection, Init (120,10));
  InitMem:=Memavail;
  Writeln ( ' Initial _memory_:_', InitMem );
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init );
      M^. SetField (I-1);
      C^. Insert (M);
    end;
  Writeln ( ' Added_100_Items._Memory_available _:', Memavail );
  Write ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
  Write ( '( Should_be_100*', SizeOf(TMyObject));
  Writeln ( '= ', 100* SizeOf(TMyObject), ' )' );
  With C^ do
    While Count>0 do AtDelete (Count-1);
  Writeln ( ' Freed_all _objects._Memory_available _:', Memavail );
  Writeln ( ' Lost _:', Initmem-Memavail, '_ bytes .' );
  Dispose(C, Done);
end.
```

TCollection.ForEach

Declaration: Procedure TCollection.ForEach (Action: Pointer);

Description: ForEach calls Action for each element in the collection, and passes the element as an argument to Action.

Action is a procedural type variable that accepts a pointer as an argument.

Errors: None.

See also: FirstThat ([314](#)), LastThat ([313](#))

```
Program ex21;

{ Program to demonstrate the TCollection.ForEach method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer;P : PMyObject);
```

```
begin
  Writeln ( ' Field _:',P^.GetField );
end;

begin
  C:=New( PCollection , Init (100,10));
  For I:=1 to 100 do
    begin
      M:=New( PMyObject, Init );
      M^.SetField (100-I);
      C^.Insert (M);
    end;
  Writeln ( ' Inserted _',C^.Count, '_ objects ' );
  C^.ForEach( @PrintField );
  C^.FreeAll;
  Dispose(C, Done);
end.
```

TCollection.SetLimit

Declaration: Procedure TCollection.SetLimit (ALimit: Sw_Integer); Virtual;

Description: SetLimit sets the maximum number of elements in the collection. ALimit must not be less than Count, and should not be larger than MaxCollectionSize

Errors: None.

See also: Init ([310](#))

For an example, see Pack ([314](#)).

TCollection.Error

Declaration: Procedure TCollection.Error (Code, Info: Integer); Virtual;

Description: Error is called by the various TCollection methods in case of an error condition. The default behaviour is to make a call to RunError with an error of 212-Code.

This method can be overridden by descendent objects to implement a different error-handling.

Errors:

See also: Abstract ([283](#))

TCollection.AtPut

Declaration: Procedure TCollection.AtPut (Index: Sw_Integer; Item: Pointer);

Description: AtPut sets the element at position Index in the collection to Item. Any previous value is overwritten.

Errors: If Index isn't valid then Error ([321](#)) is called with CoIndexError.

See also:

For an example, see Pack ([314](#)).

TCollection.AtInsert

Declaration: Procedure TCollection.AtInsert (Index: Sw_Integer; Item: Pointer);

Description: AtInsert inserts Item in the collection at position Index, shifting all elements by one position.
In case the current limit is reached, the collection will try to expand with a call to SetLimit

Errors: If Index isn't valid then Error (321) is called with CoIndexError. If the collection fails to expand, then coOverflow is passed to Error.

See also: Insert (317)

```
Program ex34;  
  
  { Program to demonstrate the TCollection.AtInsert method }  
  
  Uses Objects, MyObject; { For TMyObject definition and registration }  
  
  Var C : PCollection;  
       M : PMyObject;  
       I : Longint;  
  
  Procedure PrintField (Dummy: Pointer; P : PMyObject);  
  
  begin  
    Writeln ( ' Field _:_', P^.GetField );  
  end;  
  
  begin  
    Randomize;  
    C:=New( PCollection, Init (120,10));  
    Writeln ( ' Inserting _100_records_at_random_places.' );  
    For I:=1 to 100 do  
      begin  
        M:=New( PMyObject, Init );  
        M^.SetField (I-1);  
        If I=1 then  
          C^.Insert (M)  
        else  
          With C^ do  
            AtInsert (Random(Count), M);  
        end;  
        Writeln ( ' Values _:_');  
        C^.Foreach ( @PrintField );  
        Dispose (C, Done);  
  end.
```

TCollection.Store

Declaration: Procedure TCollection.Store (Var S: TStream);

Description: Store writes the collection to the stream S. It does this by writing the current Count, Limit and Delta to the stream, and then writing each item to the stream.

The contents of the stream are then suitable for instantiating another collection with Load (310).

Errors: Errors returned are those by TStream.Put (296).

See also: [Load \(310\)](#), [PutItem \(323\)](#)

For an example, see `seepLoadTCollection.Load`.

TCollection.PutItem

Declaration: `Procedure TCollection.PutItem (Var S: TStream; Item: Pointer); Virtual;`

Description: `PutItem` writes `Item` to stream `S`. This method is used internally by the `TCollection` object, and should not be called directly.

Errors: Errors are those returned by `TStream.Put` ([296](#)).

See also: [Store \(322\)](#), [GetItem \(313\)](#).

15.11 TSortedCollection

`TSortedCollection` is an abstract class, implementing a sorted collection. You should never use an instance of `TSortedCollection` directly, instead you should declare a descendent type, and override the `Compare` ([325](#)) method.

Because the collection is ordered, `TSortedCollection` overrides some `TCollection` methods, to provide faster routines for lookup.

The `Compare` ([325](#)) method decides how elements in the collection should be ordered. Since `TCollection` has no way of knowing how to order pointers, you must override the compare method.

Additionally, `TCollection` provides a means to filter out duplicates. if you set `Duplicates` to `False` (the default) then duplicates will not be allowed.

Here is the complete declaration of `TSortedCollection`

TYPE

```
TSortedCollection = OBJECT (TCollection)
  Duplicates: Boolean; { Duplicates flag }
  Constructor Init (ALimit, ADelta: Sw_Integer);
  Constructor Load (Var S: TStream);
  Function KeyOf (Item: Pointer): Pointer; Virtual;
  Function IndexOf (Item: Pointer): Sw_Integer; Virtual;
  Function Compare (Key1, Key2: Pointer): Sw_Integer; Virtual;
  Function Search (Key: Pointer; Var Index: Sw_Integer): Boolean; Virtual;
  Procedure Insert (Item: Pointer); Virtual;
  Procedure Store (Var S: TStream);
END;
PSortedCollection = ^TSortedCollection;
```

In the subsequent examples, the following descendent of `TSortedCollection` is used:

Unit `MySortC`;

Interface

Uses `Objects`;

Type

```
PMysortedCollection = ^ TMySortedCollection ;  
TMySortedCollection = Object ( TSortedCollection )  
    Function Compare ( Key1,Key2 : Pointer ): Sw_integer ; virtual ;  
    end ;
```

Implementation

Uses MyObject;

Function TMySortedCollection . Compare (Key1,Key2 : Pointer) : sw_integer ;

begin

Compare:= PMyobject (Key1) ^ . GetField – PMyObject (Key2) ^ . GetField ;

end ;

end .

TSortedCollection.Init

Declaration: Constructor TSortedCollection.Init (ALimit, ADelta: Sw_Integer);

Description: Init calls the inherited constructor (see TCollection.Init (310)) and sets the Duplicates flag to false.

You should not call this method directly, since TSortedCollection is a abstract class. Instead, the descendent classes should call it via the *inherited* keyword.

Errors: None.

See also: Load (324), Done (311)

For an example, see

TSortedCollection.Load

Declaration: Constructor Load (Var S: TStream);

Description: Load calls the inherited constructor (see TCollection.Load (310)) and reads the Duplicates flag from the stream..

You should not call this method directly, since TSortedCollection is a abstract class. Instead, the descendent classes should call it via the *inherited* keyword.

Errors: None.

See also: Init (324), Done (311)

For an example, see TCollection.Load (310).

TSortedCollection.KeyOf

Declaration: Function TSortedCollection.KeyOf (Item: Pointer): Pointer; Virtual;

Description: KeyOf returns the key associated with Item. TSortedCollection returns the item itself as the key, descendent objects can override this method to calculate a (unique) key based on the item passed (such as hash values).

Keys are used to sort the objects, they are used to search and sort the items in the collection. If descendent types override this method then it allows possibly for faster search/sort methods based on keys rather than on the objects themselves.

Errors: None.

See also: [IndexOf \(325\)](#), [Compare \(325\)](#).

TSortedCollection.IndexOf

Declaration: `Function TSortedCollection.IndexOf (Item: Pointer): Sw_Integer; Virtual;`

Description: `IndexOf` returns the index of `Item` in the collection. It searches for the object based on it's key.

If duplicates are allowed, then it returns the index of last object that matches `Item`.

In case `Item` is not found in the collection, -1 is returned.

Errors: None.

See also: [Search \(326\)](#), [Compare \(325\)](#).

For an example, see [TCollection.IndexOf \(312\)](#)

TSortedCollection.Compare

Declaration: `Function TSortedCollection.Compare (Key1, Key2: Pointer): Sw_Integer; Virtual;`

Description: `Compare` is an abstract method that should be overridden by descendent objects in order to compare two items in the collection. This method is used in the [Search \(326\)](#) method and in the [Insert \(327\)](#) method to determine the ordering of the objects.

The function should compare the two keys of items and return the following function results:

Result < 0If `Key1` is logically before `Key2` (`Key1<Key2`)

Result = 0If `Key1` and `Key2` are equal. (`Key1=Key2`)

Result > 0If `Key1` is logically after `Key2` (`Key1>Key2`)

Errors: An 'abstract run-time error' will be generated if you call `TSortedCollection.Compare` directly.

See also: [IndexOf \(325\)](#), [Search \(326\)](#)

Unit MySortC;

Interface

Uses Objects;

Type

PMysortedCollection = ^ TMySortedCollection ;

TMySortedCollection = **Object**(TSortedCollection)

Function Compare (Key1,Key2 : Pointer): Sw_integer ; **virtual** ;
end;

Implementation

Uses MyObject;

Function TMySortedCollection.Compare (Key1,Key2 : Pointer) : sw_integer;

begin

 Compare:=PMyObject(Key1)^.GetField - PMyObject(Key2)^.GetField;

end;

end.

TSortedCollection.Search

Declaration: Function TSortedCollection.Search (Key: Pointer; Var Index: Sw_Integer): Boolean;Virtual;

Description: Search looks for the item with key Key and returns the position of the item (if present) in the collection in Index.

Instead of a linear search as TCollection does, TSortedCollection uses a binary search based on the keys of the objects. It uses the Compare ([325](#)) function to implement this search.

If the item is found, Search returns True, otherwise False is returned.

Errors: None.

See also: IndexOf ([312](#)).

Program ex36;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;

{ For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection;

 M : PMyObject;

 I : Longint;

Procedure PrintField (Dummy: Pointer;P : PMyObject);

begin

 Writeln (' Field _:_',P^.GetField);

end;

begin

 Randomize;

 C:=New(PMySortedCollection , Init (120,10));

 C^.Duplicates:=True;

 Writeln (' Inserting _100_records_at_random_places.');

 For I:=1 to 100 do

begin

 M:=New(PMyObject, Init);

 M^.SetField (Random(100));

 C^.Insert (M)

end;

 M:=New(PMyObject, Init);

 Repeat;


```
Write ( ' Value_to_search_for_(-1_stops)_:' );
read ( I );
If I<>-1 then
begin
M^. SetField ( i );
If Not C^. Search ( M, I ) then
Writeln ( ' No_such_value_found ' )
else
begin
Write ( ' Value_', PMyObject ( C^. At ( I ) )^. GetField );
Writeln ( ' _present_at_position_', I );
end;
end;
Until I=-1;
Dispose ( M, Done );
Dispose ( C, Done );
end.
```

TSortedCollection.Insert

Declaration: Procedure TSortedCollection.Insert (Item: Pointer); Virtual;

Description: Insert inserts an item in the collection at the correct position, such that the collection is ordered at all times. You should never use AtInsert ([322](#)), since then the collection ordering is not guaranteed.

If Item is already present in the collection, and Duplicates is False, the item will not be inserted.

Errors: None.

See also: AtInsert ([322](#))

Program ex35;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;

{ For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection ;

M : PMyObject;

I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin

Writeln (' Field_', P^. GetField);

end;

begin

Randomize;

C:=New(PMySortedCollection, Init (120,10));

Writeln (' Inserting_100_records_at_random_places.');

For I:=1 **to** 100 **do**

begin

M:=New(PMyObject, Init);

```
M^. SetField (Random(100));  
C^. Insert (M)  
end;  
Writeln ( ' Values _:_ ');  
C^. Foreach ( @PrintField );  
Dispose (C, Done);  
end.
```

TSortedCollection.Store

Declaration: Procedure TSortedCollection.Store (Var S: TStream);

Description: Store writes the collection to the stream S. It does this by calling the inherited TCollection.Store (322), and then writing the Duplicates flag to the stream.

After a Store, the collection can be loaded from the stream with the constructor Load (324)

Errors: Errors can be those of TStream.Put (296).

See also: Load (324)

For an example, see TCollection.Load (310).

15.12 TStringCollection

The TStringCollection object manages a sorted collection of pascal strings. To this end, it overrides the Compare (325) method of TSortedCollection, and it introduces methods to read/write strings from a stream.

Here is the full declaration of the TStringCollection object:

```
TYPE  
  TStringCollection = OBJECT (TSortedCollection)  
    Function GetItem (Var S: TStream): Pointer; Virtual;  
    Function Compare (Key1, Key2: Pointer): Sw_Integer; Virtual;  
    Procedure FreeItem (Item: Pointer); Virtual;  
    Procedure PutItem (Var S: TStream; Item: Pointer); Virtual;  
  END;  
  PStringCollection = ^TStringCollection;
```

TStringCollection.GetItem

Declaration: Function TStringCollection.GetItem (Var S: TStream): Pointer; Virtual;

Description: GetItem reads a string from the stream S and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of TStream.ReadStr (295).

See also: PutItem (330)

TStringCollection.Compare

Declaration: Function TStringCollection.Compare (Key1, Key2: Pointer): Sw_Integer;
Virtual;

Description: TStringCollection overrides the Compare function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns the following results:

-1if the first string is alphabetically earlier than the second string.

0if the two strings are equal.

1if the first string is alphabetically later than the second string.

Errors: None.

See also: TSortedCollection.Compare ([325](#))

```
Program ex37;  
  
{ Program to demonstrate the TStringCollection.Compare method }  
  
Uses Objects;  
  
Var C : PStringCollection;  
      S : String;  
      I : longint;  
  
begin  
  Randomize;  
  C:=New(PStringCollection, Init(120,10));  
  C^.Duplicates:=True; { Duplicates allowed }  
  Writeln ( ' Inserting _100_records_at_random_places.' );  
  For I:=1 to 100 do  
    begin  
      Str(Random(100), S);  
      S:=' String _with _value _'+S;  
      C^.Insert(NewStr(S));  
    end;  
  For I:=0 to 98 do  
    With C^ do  
      If Compare ( At(i), At(I+1))=0 then  
        Writeln ( ' Duplicate _string _found _at _position _', i );  
  Dispose(C, Done);  
end.
```

TStringCollection.FreeItem

Declaration: Procedure TStringCollection.FreeItem (Item: Pointer); Virtual;

Description: TStringCollection overrides FreeItem so that the string pointed to by Item is disposed from memory.

Errors: None.

See also: TCollection.FreeItem ([319](#))

TStringCollection.PutItem

Declaration: `Procedure TStringCollection.PutItem (Var S: TStream; Item: Pointer); Virtual;`

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.WriteString` (297).

See also: `GetItem` (328)

15.13 TStrCollection

The `TStrCollection` object manages a sorted collection of null-terminated strings (pchar strings). To this end, it overrides the `Compare` (325) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

Here is the full declaration of the `TStrCollection` object:

```
TYPE
  TStrCollection = OBJECT (TSortedCollection)
    Function Compare (Key1, Key2: Pointer): Sw_Integer; Virtual;
    Function GetItem (Var S: TStream): Pointer; Virtual;
    Procedure FreeItem (Item: Pointer); Virtual;
    Procedure PutItem (Var S: TStream; Item: Pointer); Virtual;
  END;
  PStrCollection = ^TStrCollection;
```

TStrCollection.GetItem

Declaration: `Function TStrCollection.GetItem (Var S: TStream): Pointer; Virtual;`

Description: `GetItem` reads a null-terminated string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.StrRead` (293).

See also: `PutItem` (331)

TStrCollection.Compare

Declaration: `Function TStrCollection.Compare (Key1, Key2: Pointer): Sw_Integer; Virtual;`

Description: `TStrCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: TSortedCollection.Compare ([325](#))

```
Program ex38;

{ Program to demonstrate the TStrCollection.Compare method }

Uses Objects, Strings;

Var C : PStrCollection;
    S : String;
    I : longint;
    P : Pchar;

begin
  Randomize;
  C:=New( PStrCollection, Init (120,10));
  C^. Duplicates:=True; { Duplicates allowed }
  Writeln ( ' Inserting 100 records at random places. ');
  For I:=1 to 100 do
    begin
      Str (Random(100), S);
      S:= ' String with value ' +S;
      P:= StrAlloc (Length(S)+1);
      C^. Insert (StrPCopy(P,S));
    end;
  For I:=0 to 98 do
    With C^ do
      If Compare ( At(I), At(I+1))=0 then
        Writeln ( ' Duplicate string found at position ', I);
  Dispose(C, Done);
end.
```

TStrCollection.FreeItem

Declaration: Procedure TStrCollection.FreeItem (Item: Pointer); Virtual;

Description: TStrCollection overrides FreeItem so that the string pointed to by Item is disposed from memory.

Errors: None.

See also: TCollection.FreeItem ([319](#))

TStrCollection.PutItem

Declaration: Procedure TStrCollection.PutItem (Var S: TStream; Item: Pointer); Virtual;

Description: PutItem writes the string pointed to by Item to the stream S.

This method is primarily used in the Load and Store methods, and should not be used directly.

Errors: Errors are those of TStream.StrWrite ([297](#)).

See also: GetItem ([330](#))

15.14 TUnSortedStrCollection

The TUnSortedStrCollection object manages an unsorted list of objects. To this end, it overrides the TSortedCollection.Insert (327) method to add strings at the end of the collection, rather than in the alphabetically correct position.

Take care, the Search (326) and IndexOf (312) methods will not work on an unsorted string collection.

Here is the full declaration of the TUnsortedStrCollection object:

```
TYPE
  TUnSortedStrCollection = OBJECT (TStringCollection)
    Procedure Insert (Item: Pointer); Virtual;
  END;
  PUnSortedStrCollection = ^TUnSortedStrCollection;
```

TUnSortedStrCollection.Insert

Declaration: Procedure TUnSortedStrCollection.Insert (Item: Pointer); Virtual;

Description: Insert inserts a string at the end of the collection, instead of on it's alphabetical place, resulting in an unsorted collection of strings.

Errors:

See also:

```
Program ex39;

{ Program to demonstrate the TUnsortedStrCollection.Insert method }

Uses Objects, Strings;

Var C : PUnsortedStrCollection;
    S : String;
    I : longint;
    P : Pchar;

begin
  Randomize;
  C:=New(PUnsortedStrCollection, Init(120,10));
  Writeln(' Inserting 100 records at random places. ');
  For I:=1 to 100 do
    begin
      Str(Random(100), S);
      S:=' String with value ' + S;
      P:= StrAlloc (Length(S)+1);
      C^.Insert(StrPCopy(P,S));
    end;
  For I:=0 to 99 do
    Writeln(I:2, ': ', PChar(C^.At(i)));
  Dispose(C, Done);
end.
```

15.15 TResourceCollection

A `TResourceCollection` manages a collection of resource names. It stores the position and the size of a resource, as well as the name of the resource. It stores these items in records that look like this:

```
TYPE
  TResourceItem = packed RECORD
    Posn: LongInt;
    Size: LongInt;
    Key : String;
  End;
  PResourceItem = ^TResourceItem;
```

It overrides some methods of `TStringCollection` in order to accomplish this.

Remark that the `TResourceCollection` manages the names of the resources and their associated positions and sizes, it doesn't manage the resources themselves.

Here is the full declaration of the `TResourceCollection` object:

```
TYPE
  TResourceCollection = OBJECT (TStringCollection)
    Function KeyOf (Item: Pointer): Pointer; Virtual;
    Function GetItem (Var S: TStream): Pointer; Virtual;
    Procedure FreeItem (Item: Pointer); Virtual;
    Procedure PutItem (Var S: TStream; Item: Pointer); Virtual;
  END;
  PResourceCollection = ^TResourceCollection;
```

TResourceCollection.KeyOf

Declaration: `Function TResourceCollection.KeyOf (Item: Pointer): Pointer; Virtual;`

Description: `KeyOf` returns the key of an item in the collection. For resources, the key is a pointer to the string with the resource name.

Errors: None.

See also: `TStringCollection.Compare` ([329](#))

TResourceCollection.GetItem

Declaration: `Function TResourceCollection.GetItem (Var S: TStream): Pointer; Virtual;`

Description: `GetItem` reads a resource item from the stream `S`. It reads the position, size and name from the stream, in that order. It DOES NOT read the resource itself from the stream.

The resulting item is not inserted in the collection. This call is mainly for internal use by the `TCollection.Load` ([310](#)) method.

Errors: Errors returned are those by `TStream.Read` ([298](#))

See also: `TCollection.Load` ([310](#)), `TStream.Read` ([298](#))

TResourceCollection.FreeItem

Declaration: Procedure TResourceCollection.FreeItem (Item: Pointer); Virtual;

Description: FreeItem releases the memory occupied by Item. It de-allocates the name, and then the resourceitem record.

It does NOT remove the item from the collection.

Errors: None.

See also: TCollection.FreeItem ([319](#))

TResourceCollection.PutItem

Declaration: Procedure TResourceCollection.PutItem (Var S: TStream; Item: Pointer); Virtual;

Description: PutItem writes Item to the stream S. It does this by writing the position and size and name of the resource item to the stream.

This method is used primarily by the Store ([322](#)) method.

Errors: Errors returned are those by TStream.Write ([298](#)).

See also: Store ([322](#))

15.16 TResourceFile

TYPE

```
TResourceFile = OBJECT (TObject)
    Stream : PStream; { File as a stream }
    Modified: Boolean; { Modified flag }
    Constructor Init (AStream: PStream);
    Destructor Done; Virtual;
    Function Count: Sw_Integer;
    Function KeyAt (I: Sw_Integer): String;
    Function Get (Key: String): PObject;
    Function SwitchTo (AStream: PStream; Pack: Boolean): PStream;
    Procedure Flush;
    Procedure Delete (Key: String);
    Procedure Put (Item: PObject; Key: String);
END;
PResourceFile = ^TResourceFile;
```

TResourceFile Fields

TResourceFile has the following fields:

Stream contains the (file) stream that has the executable image and the resources. It can be initialized by the Init ([335](#)) constructor call.

Modified is set to TRUE if one of the resources has been changed. It is set by the SwitchTo ([335](#)), Delete ([336](#)) and Put ([336](#)) methods. Calling Flush ([336](#)) will clear the Modified flag.

TResourceFile.Init

Declaration: Constructor `TResourceFile.Init (AStream: PStream);`

Description: `Init` instantiates a new instance of a `TResourceFile` object. If `AStream` is not `nil` then it is considered as a stream describing an executable image on disk.

`Init` will try to position the stream on the start of the resources section, and read all resources from the stream.

Errors: None.

See also: `Done` ([335](#))

TResourceFile.Done

Declaration: Destructor `TResourceFile.Done; Virtual;`

Description: `Done` cleans up the instance of the `TResourceFile` Object. If `Stream` was specified at initialization, then `Stream` is disposed of too.

Errors: None.

See also: `Init` ([335](#))

TResourceFile.Count

Declaration: Function `TResourceFile.Count: Sw_Integer;`

Description: `Count` returns the number of resources. If no resources were read, zero is returned.

Errors: None.

See also: `Init` ([335](#))

TResourceFile.KeyAt

Declaration: Function `TResourceFile.KeyAt (I: Sw_Integer): String;`

Description: `KeyAt` returns the key (the name) of the `I`-th resource.

Errors: In case `I` is invalid, `TCollection.Error` will be executed.

See also: `Get` ([335](#))

TResourceFile.Get

Declaration: Function `TResourceFile.Get (Key: String): PObject;`

Description: `Get` returns a pointer to a instance of a resource identified by `Key`. If `Key` cannot be found in the list of resources, then `Nil` is returned.

Errors: Errors returned may be those by `TStream.Get`

See also:

TResourceFile.SwitchTo

Declaration: Function TResourceFile.SwitchTo (AStream: PStream; Pack: Boolean): PStream;

Description: SwitchTo switches to a new stream to hold the resources in. AStream will be the new stream after the call to SwitchTo.

If Pack is true, then all the known resources will be copied from the current stream to the new stream (AStream). If Pack is False, then only the current resource is copied.

The return value is the value of the original stream: Stream.

The Modified flag is set as a consequence of this call.

Errors: Errors returned can be those of TStream.Read (298) and TStream.Write (298).

See also: Flush (336)

TResourceFile.Flush

Declaration: Procedure TResourceFile.Flush;

Description: If the Modified flag is set to True, then Flush writes the resources to the stream Stream. It sets the Modified flag to true after that.

Errors: Errors can be those by TStream.Seek (297) and TStream.Write (298).

See also: SwitchTo (336)

TResourceFile.Delete

Declaration: Procedure TResourceFile.Delete (Key: String);

Description: Delete deletes the resource identified by Key from the collection. It sets the Modified flag to true.

Errors: None.

See also: Flush (336)

TResourceFile.Put

Declaration: Procedure TResourceFile.Put (Item: PObject; Key: String);

Description: Put sets the resource identified by Key to Item. If no such resource exists, a new one is created. The item is written to the stream.

Errors: Errors returned may be those by TStream.Put (296) and TStream.Seek

See also: Get (335)

15.17 TStringList

A TStringList object can be used to read a collection of strings stored in a stream. If you register this object with the RegisterType (283) function, you cannot register the TStrListMaker object.

This is the public declaration of the TStringList object:

TYPE

```
TStrIndexRec = Packed RECORD
    Key, Count, Offset: Word;
END;

TStrIndex = Array [0..9999] Of TStrIndexRec;
PStrIndex = ^TStrIndex;

TStringList = OBJECT (TObject)
    Constructor Load (Var S: TStream);
    Destructor Done; Virtual;
    Function Get (Key: Sw_Word): String;
END;
PStringList = ^TStringList;
```

TStringList.Load

Declaration: Constructor TStringList.Load (Var S: TStream);

Description: The Load constructor reads the TStringList object from the stream S. It also reads the descriptions of the strings from the stream. The string descriptions are stored as an array of TStrIndexrec records, where each record describes a string on the stream. These records are kept in memory.

Errors: If an error occurs, a stream error is triggered.

See also: Done ([337](#))

TStringList.Done

Declaration: Destructor TStringList.Done; Virtual;

Description: The Done destructor frees the memory occupied by the string descriptions, and destroys the object.

Errors: None.

See also: Load ([337](#)), TObject.Done ([291](#))

TStringList.Get

Declaration: Function TStringList.Get (Key: Sw_Word): String;

Description: Get reads the string with key Key from the list of strings on the stream, and returns this string. If there is no string with such a key, an empty string is returned.

Errors: If no string with key Key is found, an empty string is returned. A stream error may result if the stream doesn't contain the needed strings.

See also: TStrListMaker.Put ([338](#))

15.18 TStrListMaker

The TStrListMaker object can be used to generate a stream with strings, which can be read with the TStringList object. If you register this object with the RegisterType ([283](#)) function, you cannot register the TStringList object.

This is the public declaration of the TStrListMaker object:

TYPE

```
TStrListMaker = OBJECT (TObject)
  Constructor Init (AStrSize, AIndexSize: Sw_Word);
  Destructor Done; Virtual;
  Procedure Put (Key: SwWord; S: String);
  Procedure Store (Var S: TStream);
END;
PStrListMaker = ^TStrListMaker;
```

TStrListMaker.Init

Declaration: Constructor TStrListMaker.Init (AStrSize, AIndexSize: SwWord);

Description: The Init constructor creates a new instance of the TStrListMaker object. It allocates AStrSize bytes on the heap to hold all the strings you wish to store. It also allocates enough room for AIndexSize key description entries (of the type TStrIndexrec).

AStrSize must be large enough to contain all the strings you wish to store. If not enough memory is allocated, other memory will be overwritten. The same is true for AIndexSize : maximally AIndexSize strings can be written to the stream.

Errors: None.

See also: TObject.Init ([290](#)), Done ([338](#))

TStrListMaker.Done

Declaration: Destructor TStrListMaker.Done; Virtual;

Description: The Done destructor de-allocates the memory for the index description records and the string data, and then destroys the object.

Errors: None.

See also: TObject.Done ([291](#)), Init ([338](#))

TStrListMaker.Put

Declaration: Procedure TStrListMaker.Put (Key: Sw_Word; S: String);

Description: Put adds the string S with key Key to the collection of strings. This action doesn't write the string to a stream. To write the strings to the stream, see the Store ([338](#)) method.

Errors: None.

See also: Store ([338](#)).

TStrListMaker.Store

Declaration: Procedure TStrListMaker.Store (Var S: TStream);

Description: Store writes the collection of strings to the stream S. The collection can then be read with the TStringList object.

Errors: A stream error may occur when writing the strings to the stream.

See also: TStringList.Load ([337](#)), Put ([338](#)).

Chapter 16

The PORTS unit

16.1 Introduction

The ports unit implements the `port` constructs found in Turbo Pascal. It uses classes and default array properties to do this.

The unit exists on LINUX, OS/2 and DOS. It is implemented only for compatibility with Turbo Pascal. It's usage is discouraged, because using ports is not portable programming, and the operating system may not even allow it (for instance WINDOWS).

Under LINUX, your program must be run as root, or the `IOPerm` call must be set in order to set appropriate permissions on the port access.

16.2 Types, constants and variables

Types

The following types are defined to implement the port access.

```
tport = class
  protected
    procedure writeport(p : longint; data : byte);
    function readport(p : longint) : byte;
  public
    property pp[w : longint] : byte read readport write writeport; default;
end;
```

```
tportw = class
  protected
    procedure writeport(p : longint; data : word);
    function readport(p : longint) : word;
  public
    property pp[w : longint] : word read readport write writeport; default;
end;
```

```
tportl = class
  Protected
    procedure writeport(p : longint; data : longint);
    function readport(p : longint) : longint;
```

```
Public
  property pp[w : Longint] : longint read readport write writeport;default;
end;
```

Each of these types allows access to the ports using respectively, a byte, a word or a longint sized argument.

Since there is a default property for each of this types, a sentence as

```
port[221]:=12;
```

Will result in the byte 12 being written to port 221, if port is defined as a variable of type tport

variables

The following variables are defined:

```
port,
portb : tport;
portw : tportw;
portl : tportl;
```

They allow access to the ports in a Turbo Pascal compatible way.

Chapter 17

The PRINTER unit.

This chapter describes the PRINTER unit for Free Pascal. It was written for DOS by Florian klämpfl, and it was written for LINUX by Michaël Van Canneyt, and has been ported to WINDOWS as well. Its basic functionality is the same for both systems, although there are minor differences on LINUX.

The chapter is divided in 2 sections:

- The first section lists types, constants and variables from the interface part of the unit.
- The second section describes the functions defined in the unit.

17.1 Types, Constants and variables :

```
var
  Lst : text;
```

Lst is the standard printing device.

On LINUX, Lst is set up using AssignLst('/tmp/PID.Lst'). You can change this behaviour at compile time, setting the DefFile constant.

17.2 Procedures and functions

AssignLst

Declaration: Procedure AssignLst (Var F : text; ToFile : string[255]);

Description: LINUX only.

Assigns to F a printing device. ToFile is a string with the following form:

- '|filename options' : This sets up a pipe with the program filename, with the given options, such as in the popen() call.
- 'filename' : Prints to file filename. Filename can contain the string 'PID' (No Quotes), which will be replaced by the PID of your program. When closing lst, the file will be sent to lpr and deleted. (lpr should be in PATH)
- 'filename|' Idem as previous, only the file is NOT sent to lpr, nor is it deleted. (useful for opening /dev/printer or for later printing)

Errors: Errors are reported in Linuxerror.

See also: `lpr` (1)

```
program testprn ;

uses printer ;

var i : integer ;
    f : text ;

begin
  writeln ( 'Test_of_printer_unit' );
  writeln ( 'Writing_to_lst ...' );
  for i:=1 to 80 do writeln ( lst, 'This_is_line ', i, '.' #13);
  close ( lst );
  writeln ( 'Done.' );
  { $ifdef linux }
  writeln ( 'Writing_to_pipe ...' );
  assignlst ( f, '/usr/bin/lpr -m' );
  rewrite ( f );
  for i:=1 to 80 do writeln ( f, 'This_is_line ', i, '.' #13);
  close ( f );
  writeln ( 'Done.' )
  { $endif }
end.
```

Chapter 18

The SOCKETS unit.

This chapter describes the SOCKETS unit for Free Pascal. it was written for LINUX by Michaël Van Canneyt, and ported to WINDOWS by Florian Klaempfl. The chapter is divided in 2 sections:

- The first section lists types, constants and variables from the interface part of the unit.
- The second section describes the functions defined in the unit.

18.1 Types, Constants and variables :

The following constants identify the different socket types, as needed in the `Socket` ([353](#)) call.

```
SOCK_STREAM      = 1; { stream (connection) socket  }
SOCK_DGRAM       = 2; { datagram (conn.less) socket }
SOCK_RAW         = 3; { raw socket                  }
SOCK_RDM         = 4; { reliably-delivered message  }
SOCK_SEQPACKET   = 5; { sequential packet socket    }
SOCK_PACKET      = 10;
```

The following constants determine the socket domain, they are used in the `Socket` ([353](#)) call.

```
AF_UNSPEC        = 0;
AF_UNIX          = 1; { Unix domain sockets          }
AF_INET          = 2; { Internet IP Protocol         }
AF_AX25          = 3; { Amateur Radio AX.25          }
AF_IPX           = 4; { Novell IPX                   }
AF_APPLETALK     = 5; { Appletalk DDP                }
AF_NETROM        = 6; { Amateur radio NetROM         }
AF_BRIDGE        = 7; { Multiprotocol bridge         }
AF_AAL5          = 8; { Reserved for Werner's ATM    }
AF_X25           = 9; { Reserved for X.25 project    }
AF_INET6         = 10; { IP version 6                }
AF_MAX           = 12;
```

The following constants determine the protocol family, they are used in the `Socket` ([353](#)) call.

```
PF_UNSPEC        = AF_UNSPEC;
PF_UNIX          = AF_UNIX;
```

```
PF_INET      = AF_INET;
PF_AX25      = AF_AX25;
PF_IPX       = AF_IPX;
PF_APPLETALK = AF_APPLETALK;
PF_NETROM    = AF_NETROM;
PF_BRIDGE    = AF_BRIDGE;
PF_AAL5      = AF_AAL5;
PF_X25       = AF_X25;
PF_INET6     = AF_INET6;
PF_MAX       = AF_MAX;
```

The following types are used to store different kinds of addresses for the [Bind \(346\)](#), [Recv \(351\)](#) and [Send \(351\)](#) calls.

```
TSockAddr = packed Record
  family:word;
  data :array [0..13] of char;
end;
TUnixSockAddr = packed Record
  family:word;
  path:array[0..108] of char;
end;
TInetSockAddr = packed Record
  family:Word;
  port :Word;
  addr :Cardinal;
  pad :array [1..8] of byte;
end;
```

The following type is returned by the [SocketPair \(353\)](#) call.

```
TSockArray = Array[1..2] of Longint;
```

18.2 Functions and Procedures

Accept

Declaration: `Function Accept (Sock:Longint;Var Addr;Var Addrlen:Longint) : Longint;`

Description: `Accept` accepts a connection from a socket `Sock`, which was listening for a connection. If a connection is accepted, a file descriptor is returned. On error -1 is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The `Accept` call fills the address of the connecting entity in `Addr`, and sets its length in `Addrlen`. `Addr` should be pointing to enough space, and `Addrlen` should be set to the amount of space available, prior to the call.

Errors: On error, -1 is returned, and errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the `Listen` operation.

SYS_EFAULT`Addr` points outside your address space.

SYS_EWOULDBLOCKThe requested operation would block the process.

See also: Listen ([350](#)), Connect ([347](#))

```
Program server ;

{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}

uses Linux, Sockets ;
const
  SPath=' ServerSoc ' ;

Var
  FromName : string ;
  Buffer    : string [255];
  S         : Longint ;
  Sin, Sout : Text ;

procedure perror ( const S: string );
begin
  writeln ( S, SocketError );
  halt (100);
end;

begin
  S:= Socket ( AF_UNIX, SOCK_STREAM, 0 );
  if SocketError <> 0 then
    Perror ( ' Server_:_Socket_:_ ' );
  UnLink ( SPath );
  if not Bind ( S, SPath ) then
    Perror ( ' Server_:_Bind_:_ ' );
  if not Listen ( S, 1 ) then
    Perror ( ' Server_:_Listen_:_ ' );
  Writeln ( ' Waiting_:_for_:_Connect_:_from_:_Client_:_run_:_now_:_sock_cli_:_in_:_an_:_other_:_tty ' );
  if not Accept ( S, FromName, Sin, Sout ) then
    Perror ( ' Server_:_Accept_:_ ' + fromname );
  Reset ( Sin );
  ReWrite ( Sout );
  Writeln ( Sout, ' Message_:_From_:_Server ' );
  Flush ( SOut );
  while not eof ( sin ) do
    begin
      Readln ( Sin, Buffer );
      Writeln ( ' Server_:_read_:_ ' , buffer );
    end;
  UnLink ( SPath );
end.
```

Accept

Declaration: `Function Accept (Sock:longint;var addr:string;var SockIn,SockOut:text) : Boolean;`

Description: This is an alternate form of the `Accept` (344) command. It is equivalent to subsequently calling the regular `Accept` (344) function and the `Sock2Text` (353) function. The function returns `True` if successful, `False` otherwise.

Errors: The errors are those of `Accept` (344).

See also: `Accept` (344)

Accept

Declaration: `Function Accept (Sock:longint;var addr:string;var SockIn,SockOut:File) : Boolean;`

Description: This is an alternate form of the `Accept` (344) command. It is equivalent to subsequently calling the regular `Accept` (344) function and the `Sock2File` (352) function. The `Addr` parameter contains the name of the unix socket file to be opened. The function returns `True` if successful, `False` otherwise.

Errors: The errors are those of `Accept` (344).

See also: `Accept` (344)

Accept

Declaration: `Function Accept (Sock:longint;var addr:TInetSockAddr;var SockIn,SockOut:File) : Boolean;`

Description: This is an alternate form of the `Accept` (344) command. It is equivalent to subsequently calling the regular `Accept` (344) function and the `Sock2File` (352) function. The `Addr` parameter contains the parameters of the internet socket that should be opened. The function returns `True` if successful, `False` otherwise.

Errors: The errors are those of `Accept` (344).

See also: `Accept` (344)

Bind

Declaration: `Function Bind (Sock:Longint;Var Addr;AddrLen:Longint) : Boolean;`

Description: `Bind` binds the socket `Sock` to address `Addr`. `Addr` has length `AddrLen`. The function returns `True` if the call was successful, `False` if not.

Errors: Errors are returned in `SocketError` and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_EINVALThe socket is already bound to an address,

SYS_EACCESSAddress is protected and you don't have permission to open it.

More errors can be found in the Unix man pages.

See also: `Socket` (353)

Bind

Declaration: `Function Bind (Sock:longint;const addr:string) : boolean;`

Description: This is an alternate form of the `Bind` command. This form of the `Bind` command is equivalent to subsequently calling `Str2UnixSockAddr` (353) and the regular `Bind` (346) function. The function returns `True` if successful, `False` otherwise.

Errors: Errors are those of the regular `Bind` (346) command.

See also: `Bind` (346)

Connect

Declaration: `Function Connect (Sock:Longint;Var Addr;Addrlen:Longint) : Longint;`

Description: `Connect` opens a connection to a peer, whose address is described by `Addr`. `AddrLen` contains the length of the address. The type of `Addr` depends on the kind of connection you're trying to make, but is generally one of `TSockAddr` or `TUnixSockAddr`.

The `Connect` function returns a file descriptor if the call was successful, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in `SocketError`.

See also: `Listen` (350), `Bind` (346), `Accept` (344)

Program Client;

```
{  
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman  
  Client Version, First Run sock_svr to let it create a socket and then  
  sock_cli to connect to that socket  
}
```

uses Sockets, Linux;

```
procedure PError(const S : string);  
begin  
  writeln(S, SocketError);  
  halt(100);  
end;
```

Var

```
Saddr   : String[25];  
Buffer  : string[255];  
S        : Longint;  
Sin, Sout : Text;  
i         : integer;
```

begin

```
S:=Socket ( AF_UNIX, SOCK_STREAM, 0);  
if SocketError<>0 then  
  PError(' Client _:_ Socket _:_ ');  
Saddr:=' ServerSoc';  
if not Connect ( S, Saddr, Sin, Sout) then  
  PError(' Client _:_ Connect _:_ ');  
Reset(Sin);  
ReWrite(Sout);
```

```
Buffer := ' This_is_a_textstring_sent_by_the_Client . ' ;  
for i := 1 to 10 do  
  WriteLn ( Sout , Buffer ) ;  
  Flush ( Sout ) ;  
  ReadLn ( SIn , Buffer ) ;  
  WriteLn ( Buffer ) ;  
  Close ( sout ) ;  
end.
```

Connect

Declaration: Function Connect (Sock:longint;const addr:string;var SockIn,SockOut:text)
: Boolean;

Description: This is an alternate form of the Connect (347) command. It is equivalent to subsequently calling the regular Connect (347) function and the Sock2Text (353) function. The function returns True if successful, False otherwise.

Errors: The errors are those of Connect (347).

See also: Connect (347)

Connect

Declaration: Function Connect (Sock:longint;const addr:string;var SockIn,SockOut:file)
: Boolean;

Description: This is an alternate form of the Connect (347) command. The parameter `addr` contains the name of the unix socket file to be opened. It is equivalent to subsequently calling the regular Connect (347) function and the Sock2File (352) function. The function returns True if successful, False otherwise.

Errors: The errors are those of Connect (347).

See also: Connect (347)

Connect

Declaration: Function Connect (Sock:longint;const addr: TInetSockAddr;var SockIn,SockOut:file)
: Boolean;

Description: This is another alternate form of the Connect (347) command. It is equivalent to subsequently calling the regular Connect (347) function and the Sock2File (352) function. The `Addr` parameter contains the parameters of the internet socket to connect to. The function returns True if successful, False otherwise.

Errors: The errors are those of Connect (347).

See also: Connect (347)

```
program pfinger ;  
  
uses sockets , errors ;  
  
Var Addr : TInetSockAddr ;
```

```
S : Longint;  
  Sin, Sout : Text;  
  Line : string;  
  
begin  
  Addr.family:=AF_INET;  
  { port 79 in network order }  
  Addr.port:=79 shl 8;  
  { localhost : 127.0.0.1 in network order }  
  Addr.addr:=((1 shl 24) or 127);  
  S:=Socket(AF_INET,SOCK_STREAM,0);  
  If Not Connect ( S,ADDR,SIN,SOUT) Then  
    begin  
      Writeln ( ' Couldn't connect to localhost ' );  
      Writeln ( ' Socket_error _:_', strerror ( SocketError ) );  
      halt (1);  
    end;  
    rewrite ( sout);  
    reset ( sin );  
    writeln ( sout,paramstr (1));  
    flush (sout);  
    while not eof (sin) do  
      begin  
        readln ( Sin, line );  
        writeln ( line );  
      end;  
    Shutdown (s,2);  
    close ( sin );  
    close ( sout );  
  end.
```

GetPeerName

Declaration: Function GetPeerName (Sock:Longint;Var Addr;Var AddrLen:Longint) : Longint;

Description: GetPeerName returns the name of the entity connected to the specified socket Sock. The Socket must be connected for this call to work. Addr should point to enough space to store the name, the amount of space pointed to should be set in Addr Len. When the function returns successfully, Addr will be filled with the name, and Addr Len will be set to the length of Addr.

Errors: Errors are reported in SocketError, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOBUFSThe system doesn't have enough buffers to perform the operation.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULTAddr points outside your address space.

SYS_ENOTCONNThe socket isn't connected.

See also: Connect ([347](#)), Socket ([353](#)), connect (2)

GetSocketName

Declaration: Function GetSocketName (Sock:Longint;Var Addr;Var AddrLen:Longint) : Longint;

Description: `GetSockName` returns the current name of the specified socket `Sock`. `Addr` should point to enough space to store the name, the amount of space pointed to should be set in `Addr len`. When the function returns successfully, `Addr` will be filled with the name, and `Addr len` will be set to the length of `Addr`.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOBUFSThe system doesn't have enough buffers to perform the operation.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULT`Addr` points outside your address space.

See also: `Bind` ([346](#))

GetSocketOptions

Declaration: Function `GetSocketOptions` (`Sock`, `Level`, `OptName`:`Longint`; `Var` `OptVal`; `opt len`:`longint`) : `Longint`;

Description: `GetSocketOptions` gets the connection options for socket `Sock`. The socket may be obtained from different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKETFrom the socket itself.

XXXset `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

For more information on this call, refer to the unix manual page `getsockopt` (2).

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULT`OptVal` points outside your address space.

See also: `GetSocketOptions` ([350](#))

Listen

Declaration: Function `Listen` (`Sock`, `MaxConnect`:`Longint`) : `Boolean`;

Description: `Listen` listens for up to `MaxConnect` connections from socket `Sock`. The socket `Sock` must be of type `SOCK_STREAM` or `Sock_SEQPACKET`. The function returns `True` if a connection was accepted, `False` if an error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the `Listen` operation.

See also: `Socket` ([353](#)), `Bind` ([346](#)), `Connect` ([347](#))

Recv

Declaration: `Function Recv (Sock:Longint;Var Addr;AddrLen,Flags:Longint) : Longint;`

Description: `Recv` reads at most `AddrLen` bytes from socket `Sock` into address `Addr`. The socket must be in a connected state. `Flags` can be one of the following:

- 1: Process out-of band data.
- 4: Bypass routing, use a direct interface.
- ?: Wait for full request or report an error.

The function returns the number of bytes actually read from the socket, or -1 if a detectable error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

- SYS_EBADF**The socket descriptor is invalid.
- SYS_ENOTCONN**The socket isn't connected.
- SYS_ENOTSOCK**The descriptor is not a socket.
- SYS_EFAULT**The address is outside your address space.
- SYS EMSGSIZE**The message cannot be sent atomically.
- SYS_EWOULDBLOCK**The requested operation would block the process.
- SYS_ENOBUFS**The system doesn't have enough free buffers available.

See also: `Send` ([351](#))

Send

Declaration: `Function Send (Sock:Longint;Var Addr;AddrLen,Flags:Longint) : Longint;`

Description: `Send` sends `AddrLen` bytes starting from address `Addr` to socket `Sock`. `Sock` must be in a connected state. The function returns the number of bytes sent, or -1 if a detectable error occurred. `Flags` can be one of the following:

- 1: Process out-of band data.
- 4: Bypass routing, use a direct interface.

Errors: Errors are reported in `SocketError`, and include the following:

- SYS_EBADF**The socket descriptor is invalid.
- SYS_ENOTSOCK**The descriptor is not a socket.
- SYS_EFAULT**The address is outside your address space.
- SYS EMSGSIZE**The message cannot be sent atomically.
- SYS_EWOULDBLOCK**The requested operation would block the process.
- SYS_ENOBUFS**The system doesn't have enough free buffers available.

See also: `Recv` ([351](#)), `send` (2)

SetSocketOptions

Declaration: `Function SetSocketOptions (Sock,Level,OptName:Longint;Var OptVal;optlen:longint) : Longint;`

Description: `SetSocketOptions` sets the connection options for socket `Sock`. The socket may be manipulated at different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKETTo manipulate the socket itself.

XXXset `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

For more information on this call, refer to the unix manual page `setsockopt (2)`.

Errors: Errors are reported in `SocketError`, and include the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTSOCKThe descriptor is not a socket.

SYS_EFAULT`OptVal` points outside your address space.

See also: `GetSocketOptions` ([350](#))

Shutdown

Declaration: `Function Shutdown (Sock:Longint;How:Longint) : Longint;`

Description: `Shutdown` closes one end of a full duplex socket connection, described by `Sock`. `How` determines how the connection will be shut down, and can be one of the following:

0: Further receives are disallowed.

1: Further sends are disallowed.

2: Sending nor receiving are allowed.

On succes, the function returns 0, on error -1 is returned.

Errors: `SocketError` is used to report errors, and includes the following:

SYS_EBADFThe socket descriptor is invalid.

SYS_ENOTCONNThe socket isn't connected.

SYS_ENOTSOCKThe descriptor is not a socket.

See also: `Socket` ([353](#)), `Connect` ([347](#))

Sock2File

Declaration: `Procedure Sock2File (Sock:Longint;Var SockIn,SockOut:File);`

Description: `Sock2File` transforms a socket `Sock` into 2 Pascal file descriptors of type `File`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `Socket` ([353](#)), `Sock2Text` ([353](#))

Sock2Text

Declaration: Procedure Sock2Text (Sock:Longint;Var SockIn,SockOut: Text);

Description: Sock2Text transforms a socket Sock into 2 Pascal file descriptors of type Text, one for reading from the socket (SockIn), one for writing to the socket (SockOut).

Errors: None.

See also: Socket ([353](#)), Sock2File ([352](#))

Socket

Declaration: Function Socket (Domain,SocketType,Protocol:Longint) : Longint;

Description: Socket creates a new socket in domain Domain, from type SocketType using protocol Protocol. The Domain, Socket type and Protocol can be specified using predefined constants (see the section on constants for available constants) If succesfull, the function returns a socket descriptor, which can be passed to a subsequent Bind ([346](#)) call. If unsuccessful, the function returns -1.

Errors: Errors are returned in SocketError, and include the follwing:

SYS_EPROTONOSUPPORTThe protocol type or the specified protocol is not supported within this domain.

SYS_EMFILEThe per-process descriptor table is full.

SYS_ENFILEThe system file table is full.

SYS_EACCESSPermission to create a socket of the specified type and/or protocol is denied.

SYS_ENOBUFSInsufficient buffer space is available. The socket cannot be created until sufficient resources are freed.

See also: SocketPair ([353](#)), socket (2)

for an example, see Accept ([344](#)).

SocketPair

Declaration: Function SocketPair (Domain,SocketType,Protocol:Longint;var Pair:TSockArray) : Longint;

Description: SocketPair creates 2 sockets in domain Domain, from type SocketType and using protocol Protocol. The pair is returned in Pair, and they are indistinguishable. The function returns -1 upon error and 0 upon success.

Errors: Errors are reported in SocketError, and are the same as in Socket ([353](#))

See also: Str2UnixSockAddr ([353](#))

Str2UnixSockAddr

Declaration: Procedure Str2UnixSockAddr(const addr:string;var t:TUnixSockAddr;var len:longint)

Description: Str2UnixSockAddr transforms a Unix socket address in a string to a TUnixSockAddr structure which can be passed to the Bind ([346](#)) call.

Errors: None.

See also: Socket ([353](#)), Bind ([346](#))

Chapter 19

The STRINGS unit.

This chapter describes the STRINGS unit for Free Pascal. This unit is system independent, and therefore works on all supported platforms.

Since the unit only provides some procedures and functions, there is only one section, which gives the declarations of these functions, together with an explanation.

19.1 Functions and procedures.

StrAlloc

Declaration: `Function StrAlloc (Len : Longint);PChar`

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Errors: If there is not enough memory, a run-time error occurs.

See also: `StrNew` ([361](#)), `StrPCopy` ([362](#)).

StrCat

Declaration: `Function StrCat (Dest,Source : PChar) : PChar;`

Description: Attaches `Source` to `Dest` and returns `Dest`.

Errors: No length checking is performed.

See also: `Concat` ()

Program Example11;

Uses strings;

{ Program to demonstrate the StrCat function . }

Const P1 : PChar = ' This_is_a_PChar_String . ' ;

Var P2 : PChar;

```
begin
  P2:= StrAlloc ( StrLen(P1)*2+1);
  StrMove ( P2,P1,StrLen(P1)+1); { P2=P1 }
  StrCat ( P2,P1);                { Append P2 once more }
  Writeln ( ' P2_:_',P2);
end.
```

StrComp

Declaration: Function StrComp (S1,S2 : PChar) : Longint;

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrLComp ([358](#)), StrIComp ([357](#)), StrLComp ([360](#))

For an example, see StrLComp ([358](#)).

StrCopy

Declaration: Function StrCopy (Dest,Source : PChar) : PChar;

Description: Copy the null terminated string in Source to Dest, and returns a pointer to Dest. Dest needs enough room to contain Source, i.e. StrLen(Source)+1 bytes.

Errors: No length checking is performed.

See also: StrPCopy ([362](#)), StrLCopy ([359](#)), StrECopy ([356](#))

```
Program Example4;

Uses strings;

{ Program to demonstrate the StrCopy function. }

Const P : PChar = ' This_is_a_PCHAR_string .' ;

var PP : PChar;

begin
  PP:= StrAlloc ( Strlen (P)+1);
  StrCopy ( PP,P);
  If StrComp ( PP,P)<>0 then
    Writeln ( ' Oh-oh_problems ... ' )
  else
    Writeln ( ' All_is_well_:_PP=',PP);
end.
```

StrDispose

Declaration: Procedure StrDispose (P : PChar);

Description: Removes the string in P from the heap and releases the memory.

Errors: None.

See also: Dispose () , StrNew ([361](#))

```
Program Example17;

Uses strings;

{ Program to demonstrate the StrDispose function . }

Const P1 : PChar = ' This_is_a_PChar_string ' ;

var P2 : PChar;

begin
  Writeln ( ' Before_StrNew:_Memory_available _:_ ' , MemAvail );
  P2:=StrNew ( P1 );
  Writeln ( ' After_StrNew:_Memory_available _:_ ' , MemAvail );
  Writeln ( ' P2:_ ' , P2 );
  StrDispose (P2);
  Writeln ( ' After_StrDispose:_Memory_available _:_ ' , MemAvail );
end.
```

StrECopy

Declaration: Function StrECopy (Dest,Source : PChar) : PChar;

Description: Copies the Null-terminated string in Source to Dest, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: StrLCopy ([359](#)), StrCopy ([355](#))

```
Program Example6;

Uses strings;

{ Program to demonstrate the StrECopy function . }

Const P : PChar = ' This_is_a_PCHAR_string . ' ;

Var PP : PChar;

begin
  PP:= StrAlloc ( StrLen(P)+1);
  If Longint (StrECopy(PP,P)) – Longint (PP)<>StrLen(P) then
    Writeln ( ' Something_is_wrong_here _!' )
  else
    Writeln ( ' PP=_ ' , PP );
end.
```

StrEnd

Declaration: Function StrEnd (P : PChar) : PChar;

Description: Returns a pointer to the end of P. (i.e. to the terminating null-character.

Errors: None.

See also: StrLen ([359](#))

```
Program Example6;

Uses strings;

{ Program to demonstrate the StrEnd function . }

Const P : PChar = ' This _is _a _PCHAR _string .' ;

begin
  If Longint ( StrEnd(P)) – Longint (P) <> StrLen(P) then
    WriteLn ( ' Something _is _wrong _here _!' )
  else
    WriteLn ( ' All _is _well ..' );
end.
```

StrIComp

Declaration: Function StrIComp (S1,S2 : PChar) : Longint;

Description: Compares the null-terminated strings S1 and S2, ignoring case. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrLComp ([358](#)), StrComp ([355](#)), StrLIComp ([360](#))

```
Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function . }

Const P1 : PChar = ' This _is _the _first _string .' ;
      P2 : PChar = ' This _is _the _second _string .' ;

Var L : Longint;

begin
  Write ( ' P1 _and _P2 _are _' );
  If StrComp ( P1,P2) <> 0 then write ( ' NOT _' );
  write ( ' equal _The _first _' );
  L := 1;
  While StrLComp(P1,P2,L)=0 do inc ( L);
```

```
    dec(1);  
    Writeln (1, ' characters are the same. ');  
end.
```

StrLCat

Declaration: Function StrLCat (Dest,Source : PChar; MaxLen : Longint) : PChar;

Description: Adds MaxLen characters from Source to Dest, and adds a terminating null-character. Returns Dest.

Errors: None.

See also: StrCat ([354](#))

```
Program Example12;  
  
Uses strings;  
  
{ Program to demonstrate the StrLCat function . }  
  
Const P1 : PChar = '1234567890';  
  
Var P2 : PChar;  
  
begin  
    P2:= StrAlloc ( StrLen(P1)*2+1);  
    P2^:=#0; { Zero length }  
    StrCat ( P2,P1);  
    StrLCat ( P2,P1,5);  
    Writeln ( ' P2= ',P2);  
end.
```

StrLComp

Declaration: Function StrLComp (S1,S2 : PChar; L : Longint) : Longint;

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrComp ([355](#)), StrlComp ([357](#)), StrLIComp ([360](#))

```
Program Example8;  
  
Uses strings;  
  
{ Program to demonstrate the StrLComp function . }  
  
Const P1 : PChar = ' This is the first string . ';
```

```
    P2 : PChar = 'This_is_the_second_string.';

Var L : Longint;

begin
    Write ('P1_and_P2_are ');
    If StrComp (P1,P2)<>0 then write ('NOT ');
    write ('equal. The first ');
    L:=1;
    While StrLComp(P1,P2,L)=0 do inc (L);
    dec(L);
    Writeln (L, ' characters are the same. ');
end.
```

StrLCopy

Declaration: Function StrLCopy (Dest,Source : PChar; MaxLen : Longint) : PChar;

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: StrCopy ([355](#)), StrECopy ([356](#))

```
Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin
    PP:= StrAlloc (11);
    Writeln (' First 10 characters of P: ', StrLCopy (PP,P,10));
end.
```

StrLen

Declaration: Function StrLen (p : PChar) : Longint;

Description: Returns the length of the null-terminated string P.

Errors: None.

See also: Length ()

```
Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }
```

```
Const P : PChar = 'This_is_a_constant_pchar_string';

begin
  Writeln ('P_:',P);
  Writeln ('length(P)_:',StrLen(P));
end.
```

StrLIComp

Declaration: Function StrLIComp (S1,S2 : PChar; L : Longint) : Longint;

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrLComp ([358](#)), StrComp ([355](#)), StrIComp ([357](#))

For an example, see StrIComp ([357](#))

StrLower

Declaration: Function StrLower (P : PChar) : PChar;

Description: Converts P to an all-lowercase string. Returns P.

Errors: None.

See also: Upcase () , StrUpper ([364](#))

Program Example14;

Uses strings;

{ Program to demonstrate the StrLower and StrUpper functions. }

Const

```
P1 : PChar = 'THIS_IS_AN_UPPERCASE_PCHAR_STRING';
P2 : PChar = 'this_is_a_lowercase_string';
```

begin

```
  Writeln (' Uppercase _:',StrUpper(P2));
  StrLower ( P1);
  Writeln (' Lowercase _:',P1);
```

end.

StrMove

Declaration: Function StrMove (Dest,Source : PChar; MaxLen : Longint) : PChar;

Description: Copies MaxLen characters from Source to Dest. No terminating null-character is copied. Returns Dest.

Errors: None.

See also: StrLCopy ([359](#)), StrCopy ([355](#))

```
Program Example10;

Uses strings;

{ Program to demonstrate the StrMove function . }

Const P1 : PCHAR = ' This_is_a_pchar_string . ' ;

Var P2 : Pchar;

begin
  P2:= StrAlloc (StrLen(P1)+1);
  StrMove ( P2,P1,StrLen(P1)+1); { P2:=P1 }
  Writeln ( ' P2=_',P2);
end.
```

StrNew

Declaration: Function StrNew (P : PChar) : PChar;

Description: Copies P to the Heap, and returns a pointer to the copy.

Errors: Returns Nil if no memory was available for the copy.

See also: New () , StrCopy ([355](#)), StrDispose ([356](#))

```
Program Example16;

Uses strings;

{ Program to demonstrate the StrNew function . }

Const P1 : PChar = ' This_is_a_PChar_string ' ;

var P2 : PChar;

begin
  P2:=StrNew ( P1);
  If P1=P2 then
    writeln ( ' This_can''t_be_happening ... ' )
  else
    writeln ( ' P2:_',P2);
end.
```

StrPas

Declaration: `Function StrPas (P : PChar) : String;`

Description: Converts a null terminated string in `P` to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

See also: `StrPCopy` ([362](#))

```
Program Example3;

Uses strings;

{ Program to demonstrate the StrPas function . }

Const P : PChar = ' This_is_a_PCHAR_string ';

var S : string;

begin
  S:=StrPas (P);
  Writeln ( 'S:',S);
end.
```

StrPCopy

Declaration: `Function StrPCopy (Dest : PChar; Const Source : String) : PChar;`

Description: Converts the Pascal string in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the string `Source`, i.e. `Length(Source)+1` bytes.

Errors: No length checking is performed.

See also: `StrPas` ([362](#))

```
Program Example2;

Uses strings;

{ Program to demonstrate the StrPCopy function . }

Const S = ' This_is_a_normal_string . ';

Var P : Pchar;

begin
  p:= StrAlloc ( length(S)+1);
  if StrPCopy (P,S)<>P then
    Writeln ( ' This_is_impossible _!!' )
  else
    writeln (P);
end.
```

StrPos

Declaration: Function StrPos (S1,S2 : PChar) : PChar;

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: Pos () , StrScan ([363](#)), StrRScan ([363](#))

```
Program Example15;

Uses strings;

{ Program to demonstrate the StrPos function . }

Const P : PChar = 'This_is_a_PChar_string.';
        S : PChar = 'is';
begin
    Writeln ( ' Position_of ' is ' ' in P: ', longint ( StrPos (P,S)) – Longint (P));
end.
```

StrRScan

Declaration: Function StrRScan (P : PChar; C : Char) : PChar;

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: Pos () , StrScan ([363](#)), StrPos ([363](#))

For an example, see StrScan ([363](#)).

StrScan

Declaration: Function StrScan (P : PChar; C : Char) : PChar;

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: Pos () , StrRScan ([363](#)), StrPos ([363](#))

```
Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions . }

Const P : PChar = 'This_is_a_PCHAR_string.';
        S : Char = 's' ;

begin
```

```
    Writeln ( 'P, starting from first 's' ', StrScan(P,s));  
    Writeln ( 'P, starting from last 's' ', StrRScan(P,s));  
end.
```

StrUpper

Declaration: Function StrUpper (P : PChar) : PChar;

Description: Converts P to an all-uppercase string. Returns P.

Errors: None.

See also: Upcase () , StrLower ([360](#))

For an example, see StrLower ([360](#))

Chapter 20

The SYSUTILS unit.

This chapter describes the `sysutils` unit. The `sysutils` unit was largely written by Gertjan Schouten, and completed by Michael Van Canneyt. It aims to be compatible to the Delphi `sysutils` unit, but in contrast with the latter, it is designed to work on multiple platforms. It is implemented on all supported platforms.

This chapter starts out with a definition of all types and constants that are defined, followed by an overview of functions grouped by functionality, and lastly the complete explanation of each function.

20.1 Constants and types

The following general-purpose types are defined:

```
tfilename = string;

tsyscharset = set of char;
tintegerset = set of 0..sizeof(integer)*8-1;

longrec = packed record
    lo,hi : word;
end;

wordrec = packed record
    lo,hi : byte;
end;

TMethod = packed record
    Code, Data: Pointer;
end;
```

The use and meaning of these types should be clear, so no extra information will be provided here.

The following general-purpose constants are defined:

```
const
    SecsPerDay = 24 * 60 * 60; // Seconds and milliseconds per day
    MSecsPerDay = SecsPerDay * 1000;
    DateDelta = 693594;        // Days between 1/1/0001 and 12/31/1899
    Eoln = #10;
```

The following types are used frequently in date and time functions. They are the same on all platforms.

```
type
  TSystemTime = record
    Year, Month, Day: word;
    Hour, Minute, Second, MilliSecond: word;
  end ;

  TDateTime = double;

  TTimeStamp = record
    Time: integer;  { Number of milliseconds since midnight }
    Date: integer;  { One plus number of days since 1/1/0001 }
  end ;
```

The following type is used in the [FindFirst \(402\)](#), [FindNext \(403\)](#) and [FindClose \(402\)](#) functions. The win32 version differs from the other versions. If code is to be portable, that part shouldn't be used.

```
Type
  THandle = Longint;
  TSearchRec = Record
    Time, Size, Attr : Longint;
    Name : TFileName;
    ExcludeAttr : Longint;
    FindHandle : THandle;
    {$ifdef Win32}
    FindData : TWin32FindData;
    {$endif}
  end;
```

The following constants are file-attributes that need to be matched in the findfirst call.

```
Const
  faReadOnly    = $00000001;
  faHidden      = $00000002;
  faSysFile     = $00000004;
  faVolumeId    = $00000008;
  faDirectory   = $00000010;
  faArchive     = $00000020;
  faAnyFile     = $0000003f;
```

The following constants can be used in the [FileOpen \(399\)](#) call.

```
Const
  fmOpenRead      = $0000;
  fmOpenWrite     = $0001;
  fmOpenReadWrite = $0002;
```

The following constants can be used in the [FileSeek \(400\)](#) call.

```
Const
  fsFromBeginning = 0;
```



```
fsFromCurrent    = 1;
fsFromEnd        = 2;
```

The following variables are used in the case translation routines.

```
type
  TCaseTranslationTable = array[0..255] of char;
var
  UpperCaseTable: TCaseTranslationTable;
  LowerCaseTable: TCaseTranslationTable;
```

The initialization code of the `sysutils` unit fills these tables with the appropriate values. For the win32 and go32v2 versions, this information is obtained from the operating system.

The following constants control the formatting of dates. For the Win32 version of the `sysutils` unit, these constants are set according to the internationalization settings of Windows by the initialization code of the unit.

```
Const
  DateSeparator: char = '-';
  ShortDateFormat: string = 'd/m/y';
  LongDateFormat: string = 'dd" "mmm" "yyyy';
  ShortMonthNames: array[1..12] of string[128] =
    ('Jan', 'Feb', 'Mar', 'Apr', 'May', 'Jun',
     'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec');
  LongMonthNames: array[1..12] of string[128] =
    ('January', 'February', 'March', 'April',
     'May', 'June', 'July', 'August',
     'September', 'October', 'November', 'December');
  ShortDayNames: array[1..7] of string[128] =
    ('Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat');
  LongDayNames: array[1..7] of string[128] =
    ('Sunday', 'Monday', 'Tuesday', 'Wednesday',
     'Thursday', 'Friday', 'Saturday');
```

The following constants control the formatting of times. For the Win32 version of the `sysutils` unit, these constants are set according to the internationalization settings of Windows by the initialization code of the unit.

```
Const
  ShortTimeFormat: string = 'hh:nn';
  LongTimeFormat: string = 'hh:nn:ss';
  TimeSeparator: char = ':';
  TimeAMString: string[7] = 'AM';
  TimePMString: string[7] = 'PM';
```

The following constants control the formatting of currencies and numbers. For the Win32 version of the `sysutils` unit, these constants are set according to the internationalization settings of Windows by the initialization code of the unit.

```
Const
  DecimalSeparator : Char = '.';
  ThousandSeparator : Char = ',';
  CurrencyDecimals : Byte = 2;
```

```
CurrencyString : String[7] = '$';
{ Format to use when formatting currency :
  0 = $1          1 = 1$          2 = $ 1          3 = 1 $
  4 = Currency string replaces decimal indicator.
    e.g. 1$50
}
CurrencyFormat : Byte = 1;
{ Same as above, only for negative currencies:
  0 = ($1)
  1 = -$1
  2 = $-1
  3 = $1-
  4 = (1$)
  5 = -1$
  6 = 1-$
  7 = 1$-
  8 = -1 $
  9 = -$ 1
  10 = $ 1-
}
NegCurrFormat : Byte = 5;
```

The following types are used in various string functions.

```
type
  PString = ^String;
  TFloatFormat = (ffGeneral, ffExponent, fffixed, ffNumber, ffCurrency);
```

The following constants are used in the file name handling routines. Do not use a slash or backslash character directly as a path separator; instead use the `OsDirSeparator` character.

```
Const
  DirSeparators : set of char = ['/', '\'];
{$ifdef Linux}
  OsDirSeparator = '/';
{$else}
  OsDirSeparator = '\';
{$endif}
```

20.2 Function list by category

What follows is a listing of the available functions, grouped by category. For each function there is a reference to the page where you can find the function.

String functions

Functions for handling strings.

Name	Description	Page
<code>AnsiCompareStr</code>	Compare two strings	408
<code>AnsiCompareText</code>	Compare two strings, case insensitive	408

AnsiExtractQuotedStr	Removes quotes from string	409
AnsiLastChar	Get last character of string	410
AnsiLowerCase	Convert string to all-lowercase	410
AnsiQuotedStr	Quotes a string	411
AnsiStrComp	Compare strings case-sensitive	411
AnsiStrlComp	Compare strings case-insensitive	412
AnsiStrLComp	Compare L characters of strings case sensitive	413
AnsiStrLlComp	Compare L characters of strings case insensitive	414
AnsiStrLastChar	Get last character of string	413
AnsiStrLower	Convert string to all-lowercase	415
AnsiStrUpper	Convert string to all-uppercase	416
AnsiUpperCase	Convert string to all-uppercase	416
AppendStr	Append 2 strings	417
AssignStr	Assign value of strings on heap	417
CompareStr	Compare two strings case sensitive	419
CompareText	Compare two strings case insensitive	420
DisposeStr	Remove string from heap	421
IsValidIdent	Is string a valid pascal identifier	431
LastDelimiter	Last occurrence of character in a string	432
LeftStr	Get first N characters of a string	432
LoadStr	Load string from resources	433
LowerCase	Convert string to all-lowercase	433
NewStr	Allocate new string on heap	433
RightStr	Get last N characters of a string	434
StrAlloc	Allocate memory for string	405
StrBufSize	Reserve memory for a string	406
StrDispose	Remove string from heap	406
StrPas	Convert PChar to pascal string	407
StrPCopy	Copy pascal string	406
StrPLCopy	Copy N bytes of pascal string	407
UpperCase	Convert string to all-uppercase	439

Formatting strings

Functions for formatting strings.

Name	Description	Page
AdjustLineBreaks	Convert line breaks to line breaks for system	407
FormatBuf	Format a buffer	430
Format	Format arguments in string	424
FmtStr	Format buffer	424

QuotedStr	Quote a string	434
StrFmt	Format arguments in a string	435
StrLFmt	Format maximum L characters in a string	435
TrimLeft	Remove whitespace at the left of a string	437
TrimRight	Remove whitespace at the right of a string	438
Trim	Remove whitespace at both ends of a string	437

File input/output routines

Functions for reading/writing to file.

Name	Description	Page
FileCreate	Create a file and return handle	396
FileOpen	Open file and return handle	399
FileRead	Read from file	399
FileSeek	Set file position	400
FileTruncate	Truncate file length	401
FileWrite	Write to file	401
FileClose	Close file handle	395

File handling routines

Functions for file manipulation.

Name	Description	Page
AddDisk	Add disk to list of disk drives	387
ChangeFileExt	Change extension of file name	390
CreateDir	Create a directory	387
DeleteFile	Delete a file	391
DiskFree	Free space on disk	388
DiskSize	Total size of disk	389
ExpandFileName	Create full file name	392
ExpandUNCFileName	Create full UNC file name	392
ExtractFileDir	Extract directory part of filename	393
ExtractFileDrive	Extract drive part of filename	393
ExtractFileExt	Extract extension part of filename	393
ExtractFileName	Extract name part of filename	394
ExtractFilePath	Extract path part of filename	394
ExtractRelativePath	Construct relative path between two files	394
FileAge	Return file age	395
FileDateToDateTime	Convert file date to system date	380
FileExists	Determine whether a file exists on disk	397

FileGetAttr	Get attributes of file	397
FileGetDate	Get date of last file modification	398
FileSearch	Search for file in path	399
FileSetAttr	Get file attributes	401
FileSetDate	Get file dates	401
FindFirst	Start finding a file	402
FindNext	Find next file	403
GetCurrentDir	Return current working directory	389
RemoveDir	Remove a directory from disk	390
RenameFile	Rename a file on disk	403
SetCurrentDir	Set current working directory	390
SetDirSeparators	Set directory separator characters	404
FindClose	Stop searching a file	402
DoDirSeparators	Replace directory separator characters	391

Date/time routines

Functions for date and time handling.

Name	Description	Page
DateTimeToFileDate	Convert DateTime type to file date	374
DateTimeToStr	Construct string representation of DateTime	374
DateTimeToString	Construct string representation of DateTime	375
DateTimeToSystemTime	Convert DateTime to system time	376
DateTimeToTimeStamp	Convert DateTime to timestamp	376
DateToStr	Construct string representation of date	377
Date	Get current date	373
DayOfWeek	Get day of week	377
DecodeDate	Decode DateTime to year month and day	377
DecodeTime	Decode DateTime to hours, minutes and seconds	378
EncodeDate	Encode year, day and month to DateTime	378
EncodeTime	Encode hours, minutes and seconds to DateTime	379
FormatDateTime	Return string representation of DateTime	380
IncMonth	Add 1 to month	381
IsLeapYear	Determine if year is leap year	381
MSecsToTimeStamp	Convert nr of milliseconds to timestamp	382
Now	Get current date and time	382
StrToDateTime	Convert string to DateTime	383
StrToDate	Convert string to date	383
StrToTime	Convert string to time	384
SystemTimeToDateTime	Convert system time to datetime	385

TimeStampToDateTime	Convert time stamp to DateTime	386
TimeStampToMSecs	Convert Timestamp to number of milliseconds	386
TimeToStr	return string representation of Time	387
Time	Get current tyme	385

20.3 Miscellaneous conversion routines

Functions for various conversions.

Name	Description	Page
BCDToInt	Convert BCD number to integer	418
CompareMem	Compare two memory regions	419
FloatToStrF	Convert float to formatted string	422
FloatToStr	Convert float to string	421
FloatToText	Convert float to string	423
GetDirs	Split string in list of directories	403
IntToHex	return hexadecimal representation of integer	430
IntToStr	return decumal representation of integer	431
StrToIntDef	Convert string to integer with default value	436
StrToInt	Convert string to integer	436

20.4 Date and time functions

Date and time formatting characters

Various date and time formatting routines accept a format string, to format the date and or time. The following characters can be used to control the date and time formatting:

c : shortdateformat + ' ' + shorttimeformat

d : day of month

dd : day of month (leading zero)

ddd : day of week (abbreviation)

dddd : day of week (full)

dddddd : shortdateformat

ddddddd : longdateformat

m : month

mm : month (leading zero)

mmm : month (abbreviation)

mmmm : month (full)

y : year (four digits)
yy : year (two digits)
yyyy : year (with century)
h : hour
hh : hour (leading zero)
n : minute
nn : minute (leading zero)
s : second
ss : second (leading zero)
t : shorttimeformat
tt : longtimeformat
am/pm : use 12 hour clock and display am and pm accordingly
a/p : use 12 hour clock and display a and p accordingly
/ : insert date separator
: : insert time separator
"xx" : literal text
'xx' : literal text

TDateTime

Declaration: `TDateTime = Double;`

Description: Many functions return or require a `TDateTime` type, which contains a date and time in encoded form. The date and time are converted to a double as follows:

- The date part is stored in the integer part of the double as the number of days passed since January 1, 1900.
- The time part is stored in the fractional part of the double, as the number of milliseconds passed since midnight (00:00), divided by the total number of milliseconds in a day.

Date

Declaration: `Function Date: TDateTime;`

Description: `Date` returns the current date in `TDateTime` format. For more information about the `TDateTime` type, see `TDateTime` (373).

Errors: None.

See also: `Time` (385), `Now` (382), `TDateTime` (373).

Listing: `sysutex/ex1.pp`

```
Program Example1;

{ This program demonstrates the Date function }

uses sysutils;

Var YY,MM,DD : Word;

Begin
  WriteLn ( ' Date _:_', Date );
  DecodeDate ( Date,YY,MM,DD);
  WriteLn ( format ( ' Date_is _(DD/MM/YY):_%d/%d/%d_', [ dd,mm,yy ] ));
End.
```

DateTimeToFileDate

Declaration: `Function DateTimeToFileDate(DateTime : TDateTime) : Longint;`

Description: `DateTimeToFileDate` function converts a date/time indication in `TDateTime` format to a filedate function, such as returned for instance by the `FileAge` (395) function.

Errors: None.

See also: `Time` (385), `Date` (373), `FileDateToDateTime` (380), `DateTimeToSystemTime` (376), `DateTimeToTimeStamp` (376)

Listing: sysutex/ex2.pp

```
Program Example2;

{ This program demonstrates the DateTimeToFileDate function }

Uses sysutils;

Begin
  WriteLn ( ' FileTime_of_now_would_be:_', DateTimeToFileDate ( Now ));
End.
```

DateTimeToStr

Declaration: `Function DateTimeToStr(DateTime: TDateTime): string;`

Description: `DateTimeToStr` returns a string representation of `DateTime` using the formatting specified in `ShortDateTimeFormat`. It corresponds to a call to `FormatDateTime('c',DateTime)` (see section 20.4, page 372).

Errors: None.

See also: `FormatDateTime` (380), `TDateTime` (373).

Listing: sysutex/ex3.pp

```
Program Example3;

{ This program demonstrates the DateTimeToStr function }
```


Uses sysutils;

Begin

```
  Writeln ( ' Today_is _:_', DateTimeToStr(Now));  
  Writeln ( ' Today_is _:_', FormatDateTime('c',Now));
```

End.

DateTimeToString

Declaration: Procedure DateTimeToString(var Result: string; const FormatStr: string; const DateTime: TDateTime);

Description: DateTimeToString returns in Result a string representation of DateTime using the formatting specified in FormatStr.

for a list of characters that can be used in the FormatStr formatting string, see section [20.4](#), page [372](#).

Errors: In case a wrong formatting character is found, an EConvertError is raised.

See also: FormatDateTime ([380](#)), section [20.4](#), page [372](#).

Listing: sysutex/ex4.pp

Program Example4;

{ This program demonstrates the DateTimeToString function }

Uses sysutils;

Procedure today (Fmt : string);

Var S : AnsiString;

begin

```
  DateTimeToString ( S, Fmt, Date);  
  Writeln ( S);
```

end;

Procedure Now (Fmt : string);

Var S : AnsiString;

begin

```
  DateTimeToString ( S, Fmt, Time);  
  Writeln ( S);
```

end;

Begin

```
  Today ( '" Today_is _"dddd_dd_mmm_y' );  
  Today ( '" Today_is _"d_mmm_yy' );  
  Today ( '" Today_is _"d/mmm/yy' );  
  Now ( '" 'The_time_is _'am/pmh:n:s' );  
  Now ( '" 'The_time_is _'hh:nn:ssam/pm' );  
  Now ( '" 'The_time_is _'tt' );
```

End.

DateTimeToSystemTime

Declaration: Procedure DateTimeToSystemTime(DateTime: TDateTime; var SystemTime: TSystemTime);

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a system time SystemTime.

Errors: None.

See also: DateTimeToFileDate ([374](#)), SystemTimeToDateTime ([385](#)), DateTimeToTimeStamp ([376](#))

Listing: sysutex/ex5.pp

```
Program Example5;

{ This program demonstrates the DateTimeToSystemTime function }

Uses sysutils;

Var ST : TSystemTime;

Begin
  DateTimeToSystemTime (Now, ST);
  With St do
    begin
      WriteLn ( ' Today_is _____, year, '/' , month, '/' , Day);
      WriteLn ( ' The_time_is _____, Hour, ':' , minute, ':' , Second, '.' , MilliSecond );
    end;
End.
```

DateTimeToTimeStamp

Declaration: Function DateTimeToTimeStamp(DateTime: TDateTime): TTimeStamp;

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a TTimeStamp format.

Errors: None.

See also: DateTimeToFileDate ([374](#)), SystemTimeToDateTime ([385](#)), DateTimeToSystemTime ([376](#))

Listing: sysutex/ex6.pp

```
Program Example6;

{ This program demonstrates the DateTimeToTimeStamp function }

Uses sysutils;

Var TS : TTimeStamp;

Begin
  TS:= DateTimeToTimeStamp (Now);
  With TS do
    begin
      WriteLn ( ' Now_is _____, time, '_____ millisecond _____past _____midnight ' );
    end;
End.
```

```
    WriteLn ( ' Today is _ ' , Date , ' _ days past _1/1/0001' );  
end;  
End.
```

DateToStr

Declaration: Function DateToStr(Date: TDateTime): string;

Description: DateToStr converts Date to a string representation. It uses ShortDateFormat as it's formatting string. It is hence completely equivalent to a FormatDateTime('dddd', Date).

Errors: None.

See also: TimeToStr ([387](#)), DateTimeToStr ([374](#)), FormatDateTime ([380](#)), StrToDate ([383](#))

Listing: sysutex/ex7.pp

```
Program Example7;  
  
{ This program demonstrates the DateToStr function }  
  
Uses sysutils ;  
  
Begin  
    WriteLn ( Format ( ' Today is :_%s' , [ DateToStr ( Date ) ] ) );  
End.
```

DayOfWeek

Declaration: Function DayOfWeek(DateTime: TDateTime): integer;

Description: DayOfWeek returns the day of the week from DateTime. Sunday is counted as day 1, Saturday is counted as day 7. The result of DayOfWeek can serve as an index to the LongDayNames constant array, to retrieve the name of the day.

Errors: None.

See also: Date ([373](#)), DateToStr ([377](#))

Listing: sysutex/ex8.pp

```
Program Example8;  
  
{ This program demonstrates the DayOfWeek function }  
  
Uses sysutils ;  
  
Begin  
    WriteLn ( ' Today ' ' s _ day _ is _ ' , LongDayNames [ DayOfWeek ( Date ) ] );  
End.
```

DecodeDate

Declaration: Procedure DecodeDate(Date: TDateTime; var Year, Month, Day: word);

Description: DecodeDate decodes the Year, Month and Day stored in Date, and returns them in the Year, Month and Day variables.

Errors: None.

See also: EncodeDate ([378](#)), DecodeTime ([378](#)).

Listing: sysutex/ex9.pp

```
Program Example9;

{ This program demonstrates the DecodeDate function }

Uses sysutils;

Var YY,MM,DD : Word;

Begin
  DecodeDate( Date ,YY,MM,DD);
  Writeln ( Format ( ' Today is %d/%d/%d' ,[ dd,mm,yy ]));
End.
```

DecodeTime

Declaration: Procedure DecodeTime(Time: TDateTime; var Hour, Minute, Second, MilliSecond: word);

Description: DecodeDate decodes the hours, minutes, second and milliseconds stored in Time, and returns them in the Hour, Minute and Second and MilliSecond variables.

Errors: None.

See also: EncodeTime ([379](#)), DecodeDate ([377](#)).

Listing: sysutex/ex10.pp

```
Program Example10;

{ This program demonstrates the DecodeTime function }

Uses sysutils;

Var HH,MM,SS,MS: Word;

Begin
  DecodeTime( Time ,HH,MM,SS,MS);
  Writeln ( format( ' The time is %d:%d:%d.%d' ,[ hh,mm,ss,ms ]));
End.
```

EncodeDate

Declaration: Function EncodeDate(Year, Month, Day :word): TDateTime;

Description: EncodeDate encodes the Year, Month and Day variables to a date in TDateTime format. It does the opposite of the DecodeDate ([377](#)) procedure.

The parameters must lie withing valid ranges (boundaries included):

Year must be between 1 and 9999.

Month must be within the range 1-12.

Days must be between 1 and 31.

Errors: In case one of the parameters is out of its valid range, 0 is returned.

See also: [EncodeTime \(379\)](#), [DecodeDate \(377\)](#).

Listing: sysutex/ex11.pp

```
Program Example11;

{ This program demonstrates the EncodeDate function }

Uses sysutils;

Var YY,MM,DD : Word;

Begin
  DecodeDate ( Date,YY,MM,DD);
  WriteLn ( ' Today is _:', FormatDateTime ( ' dd_mmm_yyyy ', EncodeDate(YY,Mm,Dd)));
End.
```

EncodeTime

Declaration: `Function EncodeTime(Hour, Minute, Second, MilliSecond:word): TDateTime;`

Description: `EncodeTime` encodes the `Hour`, `Minute`, `Second`, `MilliSecond` variables to a `TDateTime` format result. It does the opposite of the [DecodeTime \(378\)](#) procedure.

The parameters must have a valid range (boundaries included):

Hour must be between 0 and 23.

Minute, **second** must both be between 0 and 59.

Millisecond must be between 0 and 999.

Errors: In case one of the parameters is outside of its valid range, 0 is returned.

See also: [EncodeDate \(378\)](#), [DecodeTime \(378\)](#).

Listing: sysutex/ex12.pp

```
Program Example12;

{ This program demonstrates the EncodeTime function }

Uses sysutils;

Var Hh,MM,SS,MS : Word;

Begin
  DecodeTime ( Time, Hh,MM,SS,MS);
  WriteLn ( ' Present Time is _:', FormatDateTime ( ' hh:mm:ss ', EncodeTime ( Hh,MM,SS,MS)));
End.
```

FileDateToDateTime

Declaration: Function FileDateToDateTime(Filedate : Longint) : TDateTime;

Description: FileDateToDateTime converts the date/time encoded in filedate to a TDateTime encoded form. It can be used to convert date/time values returned by the FileAge (395) or FindFirst (402)/FindNext (403) functions to TDateTime form.

Errors: None.

See also: DateTimeToFileDate (374)

Listing: sysutex/ex13.pp

```
Program Example13;

{ This program demonstrates the FileDateToDateTime function }

Uses sysutils;

Var
  ThisAge : Longint;

Begin
  Write ( ' ex13.pp_created_on_:' );
  ThisAge := FileAge ( ' ex13.pp' );
  Writeln ( DateTimeToStr ( FileDateToDateTime ( ThisAge ) ));
End.
```

FormatDateTime

Declaration: Function FormatDateTime(FormatStr: string; DateTime: TDateTime):string;

Description: FormatDateTime formats the date and time encoded in DateTime according to the formatting given in FormatStr. The complete list of formatting characters can be found in section 20.4, page 372.

Errors: On error (such as an invalid character in the formatting string), and EConvertError exception is raised.

See also: DateTimeToStr (374), DateToStr (377), TimeToStr (387), StrToDateTime (383)

Listing: sysutex/ex14.pp

```
Program Example14;

{ This program demonstrates the FormatDateTime function }

Uses sysutils;

Var ThisMoment : TDateTime;

Begin
  ThisMoment := Now;
  Writeln ( ' Now_:', FormatDateTime ( ' hh:mm' , ThisMoment ) );
  Writeln ( ' Now_:', FormatDateTime ( ' DD_MM_YYYY' , ThisMoment ) );
  Writeln ( ' Now_:', FormatDateTime ( ' c' , ThisMoment ) );
End.
```

IncMonth

Declaration: Function IncMonth(const DateTime: TDateTime; NumberOfMonths: integer): TDateTime;

Description: IncMonth increases the month number in DateTime with NumberOfMonths. It wraps the result as to get a month between 1 and 12, and updates the year accordingly. NumberOfMonths can be negative, and can be larger than 12 (in absolute value).

Errors: None.

See also: Date ([373](#)), Time ([385](#)), Now ([382](#))

Listing: sysutex/ex15.pp

```
Program Example15;

{ This program demonstrates the IncMonth function }

Uses sysutils;

Var ThisDay : TDateTime;

Begin
  ThisDay := Date;
  Writeln ( ' ThisDay _:', DateToStr ( ThisDay ));
  Writeln ( '6_months_ago _:', DateToStr ( IncMonth ( ThisDay , - 6)));
  Writeln ( '6_months_from_now _:', DateToStr ( IncMonth ( ThisDay , 6)));
  Writeln ( '12_months_ago _:', DateToStr ( IncMonth ( ThisDay , - 12)));
  Writeln ( '12_months_from_now _:', DateToStr ( IncMonth ( ThisDay , 12)));
  Writeln ( '18_months_ago _:', DateToStr ( IncMonth ( ThisDay , - 18)));
  Writeln ( '18_months_from_now _:', DateToStr ( IncMonth ( ThisDay , 18)));
End.
```

IsLeapYear

Declaration: Function IsLeapYear(Year: Word): boolean;

Description: IsLeapYear returns True if Year is a leap year, False otherwise.

Errors: None.

See also: IncMonth ([381](#)), Date ([373](#))

Listing: sysutex/ex16.pp

```
Program Example16;

{ This program demonstrates the IsLeapYear function }

Uses sysutils;

Var YY,MM,dd : Word;

Procedure TestYear ( Y : Word);

begin
```

```
    Writeln (Y, ' is leap year ', IsLeapYear(Y));  
end;
```

Begin

```
    DeCodeDate( Date, YY, mm, dd);  
    TestYear(yy);  
    TestYear(2000);  
    TestYear(1900);  
    TestYear(1600);  
    TestYear(1992);  
    TestYear(1995);
```

End.

MSecsToTimeStamp

Declaration: Function MSecsToTimeStamp(MSecs: Comp): TTimeStamp;

Description: MSecsToTimeStamp converts the given number of milliseconds to a TTimeStamp date/time notation.

Use TTimeStamp variables if you need to keep very precise track of time.

Errors: None.

See also: TimeStampToMSecs ([386](#)), DateTimeToTimeStamp ([376](#)),

Listing: sysutex/ex17.pp

Program Example17;

{ This program demonstrates the MSecsToTimeStamp function }

Uses sysutils;

Var MS : Comp;

TS : TTimeStamp;

DT : TDateTime;

Begin

```
    TS:= DateTimeToTimeStamp(Now);  
    Writeln ( ' Now_in_days_since_1/1/0001', TS.Date);  
    Writeln ( ' Now_in_millisecs_since_midnight ', TS.Time);  
    MS:= TimeStampToMSecs(TS);  
    Writeln ( ' Now_in_millisecs_since_1/1/0001', MS);  
    MS:=MS-1000*3600*24;  
    TS:= MSecsToTimeStamp(MS);  
    DT:= TimeStampToDateTime(TS);  
    Writeln ( ' Now_minus_1_day ', DateTimeToStr(DT));
```

End.

Now

Declaration: Function Now: TDateTime;

Description: Now returns the current date and time. It is equivalent to Date+Time.

Errors: None.

See also: [Date \(373\)](#), [Time \(385\)](#)

Listing: sysutex/ex18.pp

```
Program Example18;  
  
{ This program demonstrates the Now function }  
  
Uses sysutils ;  
  
Begin  
  WriteLn ( 'Now_:_:', DateTimeToStr(Now));  
End.
```

StrToDate

Declaration: `Function StrToDate(const S: string): TDateTime;`

Description: `StrToDate` converts the string `S` to a `TDateTime` date value. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not supported in Delphi*)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: [StrToTime \(384\)](#), [DateToStr \(377\)](#) and [TimeToStr \(387\)](#).

Listing: sysutex/ex19.pp

```
Program Example19;  
  
{ This program demonstrates the StrToDate function }  
  
Uses sysutils ;  
  
Procedure TestStr ( S : String );  
  
begin  
  WriteLn ( S, ' _:_:', DateToStr ( StrToDate (S)));  
end;  
  
Begin  
  
  WriteLn ( ' ShortDateFormat_:', ShortDateFormat );  
  TestStr ( DateTimeToStr ( Date ));  
  TestStr ( '05/05/1999' );  
  TestStr ( '5/5' );  
  TestStr ( '5' );  
End.
```

StrToDateTime

Declaration: `Function StrToDateTime(const S: string): TDateTime;`

Description: `StrToDateTime` converts the string `S` to a `TDateTime` date and time value. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not supported in Delphi*)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: `StrToDate` ([383](#)), `StrToTime` ([384](#)), `DateTimeToStr` ([374](#))

Listing: sysutex/ex20.pp

```
Program Example20;

{ This program demonstrates the StrToDateTime function }

Uses sysutils;

Procedure TestStr ( S : String );

begin
  WriteLn ( S, '␣:␣', DateTimeToStr(StrToDateTime(S)));
end;

Begin

  WriteLn ( ' ShortDateFormat␣', ShortDateFormat );
  TestStr ( DateTimeToStr(Now));
  TestStr ( '05-05-1999␣15:50' );
  TestStr ( '5-5␣13:30' );
  TestStr ( '5␣1:30PM' );
End.
```

StrToTime

Declaration: `Function StrToTime(const S: string): TDateTime;`

Description: `StrToTime` converts the string `S` to a `TDateTime` time value. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: `StrToDate` ([383](#)), `StrToDateTime` ([383](#)), `TimeToStr` ([387](#))

Listing: sysutex/ex21.pp

```
Program Example21;

{ This program demonstrates the StrToTime function }

Uses sysutils;

Procedure TestStr ( S : String );

begin
```

```
    WriteLn ( S, ' : ', TimeToStr( StrToTime(S)));  
end;
```

```
Begin  
    teststr ( TimeToStr(Time));  
    teststr ( '12:00');  
    teststr ( '15:30');  
    teststr ( '3:30PM');  
End.
```

SystemTimeToDateTime

Declaration: Function SystemTimeToDateTime(const SystemTime: TSystemTime): TDateTime;

Description: SystemTimeToDateTime converts a TSystemTime record to a TDateTime style date/time indication.

Errors: None.

See also: DateTimeToSystemTime ([376](#))

Listing: sysutex/ex22.pp

```
Program Example22;  
  
{ This program demonstrates the SystemTimeToDateTime function }  
  
Uses sysutils ;  
  
Var ST : TSystemTime;  
  
Begin  
    DateTimeToSystemTime(Now, ST);  
    With St do  
        begin  
            WriteLn ( ' Today is _____', year, '/' , month, '/' , Day);  
            WriteLn ( ' The time is _____', Hour, ':' , minute, ':' , Second, '.' , MilliSecond );  
        end;  
    WriteLn ( ' Converted _____', DateTimeToStr( SystemTimeToDateTime(ST)));  
End.
```

Time

Declaration: Function Time: TDateTime;

Description: Time returns the current time in TDateTime format. The date part of the TDateTimeValue is set to zero.

Errors: None.

See also: Now ([382](#)), Date ([373](#))

Listing: sysutex/ex23.pp

```
Program Example23;
```

```
{ This program demonstrates the Time function }  
  
Uses sysutils;  
  
Begin  
  Writeln ( 'The_time_is _:', TimeToStr(Time));  
End.
```

TimeStampToDateTime

Declaration: Function TimeStampToDateTime(const TimeStamp: TTimeStamp): TDateTime;

Description: TimeStampToDateTime converts TimeStamp to a TDateTime format variable. It is the inverse operation of DateTimeToTimeStamp ([376](#)).

Errors: None.

See also: DateTimeToTimeStamp ([376](#)), TimeStampToMSecs ([386](#))

Listing: sysutex/ex24.pp

```
Program Example24;  
  
{ This program demonstrates the TimeStampToDateTime function }  
  
Uses sysutils;  
  
Var TS : TTimeStamp;  
    DT : TDateTime;  
  
Begin  
  TS:= DateTimeToTimeStamp (Now);  
  With TS do  
    begin  
      Writeln ( 'Now_is _', time, '_ millisecond _past _midnight ');  
      Writeln ( 'Today_is _', Date, '_ days _past _1/1/0001 ');  
    end;  
  DT:= TimeStampToDateTime(TS);  
  Writeln ( 'Together _this _is _:', DateTimeToStr(DT));  
End.
```

TimeStampToMSecs

Declaration: Function TimeStampToMSecs(const TimeStamp: TTimeStamp): comp;

Description: TimeStampToMSecs converts TimeStamp to the number of seconds since 1/1/0001.

Use TTimeStamp variables if you need to keep very precise track of time.

Errors: None.

See also: MSecsToTimeStamp ([382](#)), TimeStampToDateTime ([386](#))

For an example, see MSecsToTimeStamp ([382](#)).

TimeToStr

Declaration: `Function TimeToStr(Time: TDateTime): string;`

Description: `TimeToStr` converts the time in `Time` to a string. It uses the `ShortTimeFormat` variable to see what formatting needs to be applied. It is therefore entirely equivalent to a `FormatDateTime('t', Time)` call.

Errors: None.

See also:

Listing: `sysutex/ex25.pp`

```
Program Example25;

{ This program demonstrates the TimeToStr function }

Uses sysutils;

Begin
  WriteLn ( 'The current time is ', TimeToStr(Time));
End.
```

20.5 Disk functions

AddDisk (Linux only)

Declaration: `Function AddDisk (Const Path : String) : Longint;`

Description: On Linux both the `DiskFree` ([42](#)) and `DiskSize` ([42](#)) functions need a file on the specified drive, since is required for the `statfs` system call.

These filenames are set in `drivestr[0..26]`, and the first 4 have been preset to :

Disk 0 ' .' default drive - hence current directory is used.

Disk 1 '/fd0/ .' floppy drive 1.

Disk 2 '/fd1/ .' floppy drive 2.

Disk 3 '/' C: equivalent of DOS is the root partition.

Drives 4..26 can be set by your own applications with the `AddDisk` call.

The `AddDisk` call adds `Path` to the names of drive files, and returns the number of the disk that corresponds to this drive. If you add more than 21 drives, the count is wrapped to 4.

Errors: None.

See also: `DiskFree` ([388](#)), `DiskSize` ([389](#))

CreateDir

Declaration: `Function CreateDir(Const NewDir : String) : Boolean;`

Description: `CreateDir` creates a new directory with name `NewDir`. If the directory doesn't contain an absolute path, then the directory is created below the current working directory.

The function returns `True` if the directory was successfully created, `False` otherwise.

Errors: In case of an error, the function returns `False`.

See also: `RemoveDir` ([390](#))

Listing: `sysutex/ex26.pp`

```
Program Example26;  
  
{ This program demonstrates the CreateDir and RemoveDir functions }  
{ Run this program twice in the same directory }  
  
Uses sysutils;  
  
Begin  
  If Not FileExists ( 'NewDir' ) then  
    If Not CreateDir ( 'NewDir' ) Then  
      WriteLn ( 'Failed _to_create_directory _!' )  
    else  
      WriteLn ( 'Created _"NewDir"_ directory ' )  
    Else  
      If Not RemoveDir ( 'NewDir' ) Then  
        WriteLn ( 'Failed _to_remove_directory _!' )  
      else  
        WriteLn ( 'Removed _"NewDir"_ directory ' );  
End.
```

DiskFree

Declaration: `Function DiskFree(Drive : Byte) : Longint;`

Description: `DiskFree` returns the free space (in bytes) on disk `Drive`. `Drive` is the number of the disk drive:

- `0`for the current drive.
- `1`for the first floppy drive.
- `2`for the second floppy drive.
- `3`for the first hard-disk partition.
- `4-26`for all other drives and partitions.

Remark Under `LINUX`, and `Unix` in general, the concept of disk is different than the `DOS` one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` and `DiskSize` ([42](#)) functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` ([387](#))

Errors: On error, `-1` is returned.

See also: `DiskSize` ([389](#)), `AddDisk` ([387](#))

Listing: `sysutex/ex27.pp`

```
Program Example27;  
  
{ This program demonstrates the DiskFree function }  
  
Uses sysutils;
```

```
Begin
  Write ( ' Size_of_current_disk _____: ', DiskSize (0));
  Writeln ( '_(=_', DiskSize (0) div 1024, ' k)' );
  Write ( ' Free_space_of_current_disk_: ', Diskfree (0));
  Writeln ( '_(=_', Diskfree (0) div 1024, ' k)' );
End.
```

DiskSize

Declaration: `Function DiskSize(Drive : Byte) : Longint;`

Description: `DiskSize` returns the size (in bytes) of disk `Drive`. `Drive` is the number of the disk drive:

0for the current drive.

1for the first floppy drive.

2for the second floppy drive.

3for the first hard-disk partition.

4-26for all other drives and partitions.

Remark Under `LINUX`, and `Unix` in general, the concept of disk is different than the `DOS` one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` ([42](#)) and `DiskSize` functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` ([387](#))

Errors: On error, `-1` is returned.

See also: `DiskFree` ([388](#)), `AddDisk` ([387](#))

For an example, see `DiskFree` ([388](#)).

GetCurrentDir

Declaration: `Function GetCurrentDir : String;`

Description: `GetCurrentDir` returns the current working directory.

Errors: None.

See also: `SetCurrentDir` ([390](#)), `DiskFree` ([42](#)), `DiskSize` ([42](#))

Listing: `sysutex/ex28.pp`

```
Program Example28;

{ This program demonstrates the GetCurrentDir function }

Uses sysutils;

Begin
  Writeln ( ' Current_Directory_is _:_ ', GetCurrentDir );
End.
```

RemoveDir

Declaration: `Function RemoveDir(Const Dir : String) : Boolean;`

Description: `RemoveDir` removes directory `Dir` from the disk. If the directory is not absolute, it is appended to the current working directory.

Errors: In case of error (e.g. the directory isn't empty) the function returns `False`. If successful, `True` is returned.

See also:

For an example, see `CreateDir` ([387](#)).

SetCurrentDir

Declaration: `Function SetCurrentDir(Const NewDir : String) : Boolean;`

Description: `SetCurrentDir` sets the current working directory of your program to `NewDir`. It returns `True` if the function was successful, `False` otherwise.

Errors: In case of error, `False` is returned.

See also: `GetCurrentDir` ([389](#))

Listing: `sysutex/ex29.pp`

```
Program Example29;

{ This program demonstrates the SetCurrentDir function }

Uses sysutils;

Begin
  If SetCurrentDir ( '..' ) Then
    WriteLn ( 'Now_in_directory_', GetCurrentDir )
  else
    WriteLn ( 'Change_directory_to_... failed .' );
End.
```

20.6 File handling functions

ChangeFileExt

Declaration: `Function ChangeFileExt(const FileName, Extension: string): string;`

Description: `ChangeFileExt` changes the file extension in `FileName` to `Extension`. The extension `Extension` includes the starting `.` (dot). The previous extension of `FileName` are all characters after the last `.`, the `.` character included.

If `FileName` doesn't have an extension, `Extension` is just appended.

Errors: None.

See also: `ExtractFileName` ([394](#)), `ExtractFilePath` ([394](#)), `ExpandFileName` ([392](#))

DeleteFile

Declaration: Function DeleteFile(Const FileName : String) : Boolean;

Description: DeleteFile deletes file FileName from disk. The function returns True if the file was successfully removed, False otherwise.

Errors: On error, False is returned.

See also: FileCreate ([396](#)), FileExists ([397](#))

Listing: sysutex/ex31.pp

```
Program Example31;

{ This program demonstrates the DeleteFile function }

Uses sysutils;

Var
  Line : String;
  F, I : Longint;

Begin
  F:= FileCreate ( ' test . txt ' );
  Line := ' Some_string_line . ' #10;
  For I:=1 to 10 do
    FileWrite ( F, Line [1], Length( Line ));
  FileClose (F);
  DeleteFile ( ' test . txt ' );
End.
```

DoDirSeparators

Declaration: Procedure DoDirSeparators(Var FileName : String);

Description: This function replaces all directory separators ' and '/' to the directory separator character for the current system.

Errors: None.

See also: ExtractFileName ([394](#)), ExtractFilePath ([394](#))

Listing: sysutex/ex32.pp

```
Program Example32;

{ This program demonstrates the DoDirSeparators function }
{$H+}

Uses sysutils;

Procedure Testit ( F : String );

begin
  Writeln ( ' Before : ', F);
  DoDirSeparators ( F);
```

```
    Writeln ( ' After _:_:', F);  
end;  
  
Begin  
    Testit ( GetCurrentDir );  
    Testit ( ' c:\ pp\ bin\ win32' );  
    Testit ( '/ usr/ lib / fpc' );  
    Testit ( '\ usr\ lib \ fpc' );  
End.
```

ExpandFileName

Declaration: Function ExpandFileName(Const FileName : string): String;

Description: ExpandFileName expands the filename to an absolute filename. It changes all directory separator characters to the one appropriate for the system first.

Errors: None.

See also: ExtractFileName ([394](#)), ExtractFilePath ([394](#)), ExtractFileDir ([393](#)), ExtractFileDrive ([393](#)), ExtractFileExt ([393](#)), ExtractRelativePath ([394](#))

Listing: sysutex/ex33.pp

```
Program Example33;  
  
{ This program demonstrates the ExpandFileName function }  
  
Uses sysutils ;  
  
Procedure Testit ( F : String );  
  
begin  
    Writeln ( F, '_ expands _to _:_:', ExpandFileName(F));  
end;  
  
Begin  
    Testit ( ' ex33. pp' );  
    Testit ( ParamStr(0));  
    Testit ( '/ pp/ bin / win32/ ppc386' );  
    Testit ( '\ pp\ bin \ win32\ ppc386' );  
    Testit ( '.' );  
End.
```

ExpandUNCFileName

Declaration: Function ExpandUNCFileName(Const FileName : string): String;

Description: ExpandUNCFileName runs ExpandFileName ([392](#)) on FileName and then attempts to replace the driveletter by the name of a shared disk.

Errors:

See also: ExtractFileName ([394](#)), ExtractFilePath ([394](#)), ExtractFileDir ([393](#)), ExtractFileDrive ([393](#)), ExtractFileExt ([393](#)), ExtractRelativePath ([394](#))

ExtractFileDir

Declaration: Function ExtractFileDir(Const FileName : string): string;

Description: ExtractFileDir returns only the directory part of FileName, not including a driveletter. The directory name has NO ending directory separator, in difference with ExtractFilePath (394).

Errors: None.

See also: ExtractFileName (394), ExtractFilePath (394), ExtractFileDir (393), ExtractFileDrive (393), ExtractFileExt (393), ExtractRelativePath (394)

Listing: sysutex/ex34.pp

Program Example34;

{ This program demonstrates the ExtractFileName function }
{ \$H+ }

Uses sysutils ;

Procedure Testit (F : String);

begin

WriteLn (' FileName_#####:', F);
 WriteLn (' Has_Name_#####:', **ExtractFileName** (F));
 WriteLn (' Has_Path_#####:', **ExtractFilePath** (F));
 WriteLn (' Has_Extension_:', **ExtractFileExt** (F));
 WriteLn (' Has_Directory_:', **ExtractFileDir** (F));
 WriteLn (' Has_Drive_#####:', **ExtractFileDrive** (F));

end;

Begin

 Testit (**Paramstr** (0));
 Testit (' /usr/local/bin/mysql');
 Testit (' c:\pp\bin\win32\ppc386.exe');
 Testit (' /pp/bin/win32/ppc386.exe');

End.

ExtractFileDrive

Declaration: Function ExtractFileDrive(const FileName: string): string;

Description: Extract

Errors:

See also: ExtractFileName (394), ExtractFilePath (394), ExtractFileDir (393), ExtractFileDrive (393), ExtractFileExt (393), ExtractRelativePath (394)

For an example, see ExtractFileDir (393).

ExtractFileExt

Declaration: Function ExtractFileExt(const FileName: string): string;

Description: ExtractFileExt returns the extension (including the .(dot) character) of FileName.

Errors: None.

See also: [ExtractFileName \(394\)](#), [ExtractFilePath \(394\)](#), [ExtractFileDir \(393\)](#), [ExtractFileDrive \(393\)](#), [ExtractFileExt \(393\)](#), [ExtractRelativePath \(394\)](#)

For an example, see [ExtractFileDir \(393\)](#).

ExtractFileName

Declaration: `Function ExtractFileName(const FileName: string): string;`

Description: `ExtractFileName` returns the filename part from `FileName`. The filename consists of all characters after the last directory separator character ('/' or '\') or drive letter.

The full filename can always be reconstructed by concatenating the result of [ExtractFilePath \(394\)](#) and `ExtractFileName`.

Errors: None.

See also: [ExtractFileName \(394\)](#), [ExtractFilePath \(394\)](#), [ExtractFileDir \(393\)](#), [ExtractFileDrive \(393\)](#), [ExtractFileExt \(393\)](#), [ExtractRelativePath \(394\)](#)

For an example, see [ExtractFileDir \(393\)](#).

ExtractFilePath

Declaration: `Function ExtractFilePath(const FileName: string): string;`

Description: `ExtractFilePath` returns the path part (including driveletter) from `FileName`. The path consists of all characters before the last directory separator character ('/' or '\'), including the directory separator itself. In case there is only a drive letter, that will be returned.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` and [ExtractFileName \(394\)](#).

Errors: None.

See also: [ExtractFileName \(394\)](#), [ExtractFilePath \(394\)](#), [ExtractFileDir \(393\)](#), [ExtractFileDrive \(393\)](#), [ExtractFileExt \(393\)](#), [ExtractRelativePath \(394\)](#)

For an example, see [ExtractFileDir \(393\)](#).

ExtractRelativePath

Declaration: `Function ExtractRelativePath(Const BaseName, DestName : String): String;`

Description: `ExtractRelativePath` constructs a relative path to go from `BaseName` to `DestName`. If `DestName` is on another drive (Not on Linux) then the whole `Destname` is returned.

Note: This function does not exist in the Delphi unit.

Errors: None.

See also: [ExtractFileName \(394\)](#), [ExtractFilePath \(394\)](#), [ExtractFileDir \(393\)](#), [ExtractFileDrive \(393\)](#), [ExtractFileExt \(393\)](#),

Listing: `sysutex/ex35.pp`

```
Program Example35;

{ This program demonstrates the ExtractRelativePath function }

Uses sysutils;

Procedure Testit ( FromDir, ToDir : String );

begin
    Write ( ' From_', FromDir, ' to _', ToDir, ' via _' );
    WriteLn ( ExtractRelativePath ( FromDir, ToDir ), ' ' );
end;

Begin
    Testit ( '/ pp/ src / compiler ', '/ pp/ bin / win32 / ppc386' );
    Testit ( '/ pp/ bin / win32 / ppc386 ', '/ pp/ src / compiler ' );
    Testit ( ' e:/ pp/ bin / win32 / ppc386 ', ' d:/ pp/ src / compiler ' );
    Testit ( ' e:\ pp\ bin \ win32 \ ppc386 ', ' d:\ pp\ src \ compiler ' );
End.
```

FileAge

Declaration: Function FileAge(Const FileName : String): Longint;

Description: FileAge returns the last modification time of file FileName. The FileDate format can be transformed to TDateTime format with the FileDateToDateTime (380) function.

Errors: In case of errors, -1 is returned.

See also: FileDateToDateTime (380), FileExists (397), FileGetAttr (397)

Listing: sysutex/ex36.pp

```
Program Example36;

{ This program demonstrates the FileAge function }

Uses sysutils;

Var S : TDateTime;
    fa : Longint;
Begin
    fa := FileAge ( ' ex36. pp' );
    If Fa <> -1 then
        begin
            S := FileDateToDateTime ( fa );
            WriteLn ( ' I ' ' m_from_', DateTimeToStr ( S ) )
        end;
End.
```

FileClose

Declaration: Procedure FileClose(Handle : Longint);

Description: FileClose closes the file handle Handle. After this call, attempting to read or write from the handle will result in an error.

Errors: None.

See also: [FileCreate \(396\)](#), [FileWrite \(401\)](#), [FileOpen \(399\)](#), [FileRead \(399\)](#), [FileTruncate \(401\)](#), [FileSeek \(400\)](#)

For an example, see [FileCreate \(396\)](#)

FileCreate

Declaration: `Function FileCreate(Const FileName : String) : Longint;`

Description: `FileCreate` creates a new file with name `FileName` on the disk and returns a file handle which can be used to read or write from the file with the [FileRead \(399\)](#) and [FileWrite \(401\)](#) functions.

If a file with name `FileName` already existed on the disk, it is overwritten.

Errors: If an error occurs (e.g. disk full or non-existent path), the function returns -1.

See also: [FileClose \(395\)](#), [FileWrite \(401\)](#), [FileOpen \(399\)](#), [FileRead \(399\)](#), [FileTruncate \(401\)](#), [FileSeek \(400\)](#)

Listing: `sysutex/ex37.pp`

Program `Example37;`

{ This program demonstrates the FileCreate function }

Uses `sysutils;`

Var `I,J,F : Longint;`

Begin

```
F:= FileCreate ( ' test . dat' );
If F=-1 then
  Halt(1);
For I:=0 to 100 do
  FileWrite (F, I, SizeOf(i));
FileClose (f);
F:= FileOpen ( ' test . dat', fmOpenRead);
For I:=0 to 100 do
  begin
    FileRead ( F, J, SizeOf(J));
    If J<>I then
      Writeln ( ' Mismatch_at_file_position ', I)
    end;
FileSeek (F,0, fsFromBeginning);
Randomize;
Repeat
  FileSeek (F, Random(100)*4, fsFromBeginning);
  FileRead ( F, J, SizeOf(J));
  Writeln ( ' Random_read_: ', j );
Until J>80;
FileClose (F);
F:= FileOpen ( ' test . dat', fmOpenWrite);
I:=50*SizeOf ( Longint );
If FileTruncate (F, I) then
  Writeln ( ' Successfully_truncated_file_to ', I, ' bytes.' );
FileClose (F);
```

End.

FileExists

Declaration: `Function FileExists(Const FileName : String) : Boolean;`

Description: `FileExists` returns `True` if a file with name `FileName` exists on the disk, `False` otherwise.

Errors: None.

See also: `FileAge` ([395](#)), `FileGetAttr` ([397](#)), `FileSetAttr` ([401](#))

Listing: `sysutex/ex38.pp`

```
Program Example38;

{ This program demonstrates the FileExists function }

Uses sysutils;

Begin
  If FileExists(ParamStr(0)) Then
    Writeln ( ' All _is _well , _I _seem _to _exist .' );
End.
```

FileGetAttr

Declaration: `Function FileGetAttr(Const FileName : String) : Longint;`

Description: `FileGetAttr` returns the attribute settings of file `FileName`. The attribute is a OR-ed combination of the following constants:

faReadOnlyThe file is read-only.

faHiddenThe file is hidden. (On LINUX, this means that the filename starts with a dot)

faSysFileThe file is a system file (On LINUX, this means that the file is a character, block or FIFO file).

faVolumeIdVolume Label. Not possible under LINUX.

faDirectoryFile is a directory.

faArchivefile is an archive. Not possible on LINUX.

Errors: In case of error, -1 is returned.

See also: `FileSetAttr` ([401](#)), `FileAge` ([395](#)), `FileGetDate` ([398](#)).

Listing: `sysutex/ex40.pp`

```
Program Example40;

{ This program demonstrates the FileGetAttr function }

Uses sysutils;

Procedure Testit (Name : String);

Var F : Longint;

Begin
  F:= FileGetAttr (Name);
```

```
If F<>-1 then
begin
  Writeln ( ' Testing _:',Name);
  If ( F and faReadOnly)<>0 then
    Writeln ( ' File _is _ReadOnly' );
  If ( F and faHidden)<>0 then
    Writeln ( ' File _is _hidden' );
  If ( F and faSysFile)<>0 then
    Writeln ( ' File _is _a _system _file ' );
  If ( F and faVolumeID)<>0 then
    Writeln ( ' File _is _a _disk _label ' );
  If ( F and faArchive)<>0 then
    Writeln ( ' File _is _artchive _file ' );
  If ( F and faDirectory)<>0 then
    Writeln ( ' File _is _a _directory ' );
end
else
  Writeln ( ' Error _reading _attribites _of _',Name);
end;

begin
  testit ( 'ex40.pp' );
  testit ( ParamStr(0));
  testit ( '.' );
  testit ( '/' );
End.
```

FileGetDate

Declaration: Function FileGetDate(Handle : Longint) : Longint;

Description: FileGetdate returns the filetime of the opened file with filehandle Handle. It is the same as FileAge (395), with this difference that FileAge only needs the file name, while FilegetDate needs an open file handle.

Errors: On error, -1 is returned.

See also: FileAge (395)

Listing: sysutex/ex39.pp

```
Program Example39;

{ This program demonstrates the FileGetDate function }

Uses sysutils ;

Var F,D : Longint;

Begin
  F:= FileCreate ( ' test . dat ' );
  D:= FileGetDate (D);
  Writeln ( ' File _crerated _on _', DateTimeToStr ( FileDateToDateTime (D)));
  FileClose (F);
  DeleteFile ( ' test . dat ' );
End.
```

FileOpen

Declaration: `Function FileOpen(Const FileName : string; Mode : Integer) : Longint;`

Description: `FileOpen` opens a file with name `FileName` with mode `Mode`. `Mode` can be one of the following constants:

fmOpenReadThe file is opened for reading.

fmOpenWriteThe file is opened for writing.

fmOpenReadWriteThe file is opened for reading and writing.

If the file has been successfully opened, it can be read from or written to (depending on the `Mode` parameter) with the `FileRead` (399) and `FileWrite` functions.

Remark that you cannot open a file if it doesn't exist yet, i.e. it will not be created for you. If you want to create a new file, or overwrite an old one, use the `FileCreate` (396) function.

Errors: On Error, -1 is returned.

See also: `FileClose` (395), `FileWrite` (401), `FileCreate` (396), `FileRead` (399), `FileTruncate` (401), `FileSeek` (400)

For an example, see `FileRead` (399)

FileRead

Declaration: `Function FileRead(Handle : Longint; Var Buffer; Count : longint) : Longint;`

Description: `FileRead` reads `Count` bytes from file-handle `Handle` and stores them into `Buffer`. `Buffer` must be at least `Count` bytes long. No checking on this is performed, so be careful not to overwrite any memory. `Handle` must be the result of a `FileOpen` (399) call.

Errors: On error, -1 is returned.

See also: `FileClose` (395), `FileWrite` (401), `FileCreate` (396), `FileOpen` (399), `FileTruncate` (401), `FileSeek` (400)

For an example, see `FileOpen` (399)

FileSearch

Declaration: `Function FileSearch(Const Name, DirList : String) : String;`

Description: `FileSearch` looks for the file `Name` in `DirList`, where `dirlist` is a list of directories, separated by semicolons or colons. It returns the full filename of the first match found.

Errors: On error, an empty string is returned.

See also: `ExpandFileName` (392), `FindFirst` (402)

Listing: `sysutex/ex41.pp`

Program `Example41;`

{ Program to demonstrate the FileSearch function . }

Uses Sysutils ;

Const

```
{ $ifdef linux }
  FN = ' find ' ;
  P = ' .:/ bin :/ usr / bin ' ;
{ $else }
  FN = ' find . exe ' ;
  P = ' c : \ dos ; c : \ windows ; c : \ windows \ system ; c : \ windows \ system32 ' ;
{ $endif }
```

begin

```
  Writeln ( ' find _is _in _:_', FileSearch ( FN, P ));
end.
```

FileSeek

Declaration: Function FileSeek(Handle, Offset, Origin : Longint) : Longint;

Description: FileSeek sets the file pointer on position Offset, starting from Origin. Origin can be one of the following values:

fsFromBeginningOffset is relative to the first byte of the file. This position is zero-based. i.e. the first byte is at offset 0.

fsFromCurrentOffset is relative to the current position.

fsFromEndOffset is relative to the end of the file. This means that Offset can only be zero or negative in this case.

If successful, the function returns the new file position, relative to the beginning of the file.

Remark: The abovementioned constants do not exist in Delphi.

Errors: On error, -1 is returned.

See also: FileClose ([395](#)), FileWrite ([401](#)), FileCreate ([396](#)), FileOpen ([399](#)) FileRead ([399](#)), FileTruncate ([401](#))

Listing: sysutex/ex42.pp

Program Example42;

{ This program demonstrates the FileSetAttr function }

Uses sysutils ;

Begin

```
  If FileSetAttr ( ' ex40 . pp ' , faReadOnly or faHidden ) = 0 then
    Writeln ( ' Successfully _made _file _hidden _and _read-only . ' )
  else
    Writeln ( ' Couldnt ' ' t _make _file _hidden _and _read-only . ' );
```

End.

For an example, see FileCreate ([396](#))

FileSetAttr (Not on Linux)

Declaration: `Function FileSetAttr(Const Filename : String; Attr: longint) : Longint;`

Description: `FileSetAttr` sets the attributes of `FileName` to `Attr`. If the function was successful, 0 is returned, -1 otherwise.

`Attr` can be set to an OR-ed combination of the pre-defined `faXXX` constants.

Errors: On error, -1 is returned (always on linux).

See also: `FileGetAttr` ([397](#)), `FileGetDate` ([398](#)), `FileSetDate` ([401](#)).

FileSetDate (Not on Linux)

Declaration: `Function FileSetDate(Handle, Age : Longint) : Longint;`

Description: `FileSetDate` sets the file date of the file with handle `Handle` to `Age`, where `Age` is a DOS date-and-time stamp value.

The function returns zero of successful.

Errors: On Linux, -1 is always returned, since this is impossible to implement. On Windows and DOS, a negative error code is returned.

See also:

FileTruncate

Declaration: `Function FileTruncate(Handle, Size: Longint) : boolean;`

Description: `FileTruncate` truncates the file with handle `Handle` to `Size` bytes. The file must have been opened for writing prior to this call. The function returns `True` is successful, `False` otherwise.

Errors: On error, the function returns `False`.

See also: `FileClose` ([395](#)), `FileWrite` ([401](#)), `FileCreate` ([396](#)), `FileOpen` ([399](#)) `FileRead` ([399](#)), `FileSeek` ([400](#))

For an example, see `FileCreate` ([396](#)).

FileWrite

Declaration: `Function FileWrite(Handle : Longint; Var Buffer; Count : Longint) : Longint;`

Description: `FileWrite` writes `Count` bytes from `Buffer` to the file with handle `Handle`. Prior to this call, the file must have been opened for writing. `Buffer` must be at least `Count` bytes large, or a memory access error may occur.

The function returns the number of bytes written, or -1 in case of an error.

Errors: In case of error, -1 is returned.

See also: `FileClose` ([395](#)), `FileCreate` ([396](#)), `FileOpen` ([399](#)) `FileRead` ([399](#)), `FileTruncate` ([401](#)), `FileSeek` ([400](#))

For an example, see `FileCreate` ([396](#)).

FindClose

Declaration: Procedure FindClose(Var F : TSearchrec);

Description: FindClose ends a series of FindFirst (402)/FindNext (403) calls, and frees any memory used by these calls. It is *absolutely* necessary to do this call, or huge memory losses may occur.

Errors: None.

See also: FindFirst (402), FindNext (403).

For an example, see FindFirst (402).

FindFirst

Declaration: Function FindFirst(Const Path : String; Attr : Longint; Var Rslt : TSearchRec) : Longint;

Description: FindFirst looks for files that match the name (possibly with wildcards) in Path and attributes Attr. It then fills up the Rslt record with data gathered about the file. It returns 0 if a file matching the specified criteria is found, a nonzero value (-1 on linux) otherwise.

The Rslt record can be fed to subsequent calls to FindNext, in order to find other files matching the specifications.

remark: A FindFirst call must *always* be followed by a FindClose (402) call with the same Rslt record. Failure to do so will result in memory loss.

Errors: On error the function returns -1 on linux, a nonzero error code on Windows.

See also: FindClose (45)FindCloseSys, FindNext (403).

Listing: sysutex/ex43.pp

Program Example43;

{ This program demonstrates the FindFirst function }

Uses sysutils;

Var Info : TSearchRec;
Count : Longint;

Begin

Count:=0;

If FindFirst ('*.pp', faAnyFile, Info)=0 **then**

begin

Repeat

Inc (Count);

With Info **do**

WriteIn (Name:40, Size:15);

Until FindNext(info)<>0;

end;

FindClose (Info);

WriteIn (' Finished _search _Found _', Count, ' _ matches ');

End.

FindNext

Declaration: Function FindNext(Var Rslt : TSearchRec) : Longint;

Description: FindNext finds a next occurrence of a search sequence initiated by FindFirst. If another record matching the criteria in Rslt is found, 0 is returned, a nonzero constant is returned otherwise.

remark: The last FindNext call must *always* be followed by a FindClose call with the same Rslt record. Failure to do so will result in memory loss.

Errors: On error (no more file is found), a nonzero constant is returned.

See also: FindFirst ([402](#)), FindClose ([45](#))

For an example, see FindFirst ([402](#))

GetDirs

Declaration: Function GetDirs(Var DirName : String; Var Dirs : Array of pchar) : Longint;

Description: GetDirs splits DirName in a null-byte separated list of directory names, Dirs is an array of PChars, pointing to these directory names. The function returns the number of directories found, or -1 if none were found. DirName must contain only OSDirSeparator as Directory separator chars.

Errors: None.

See also: ExtractRelativePath ([394](#))

Listing: sysutex/ex45.pp

Program Example45;

{ This program demonstrates the GetDirs function }
{ \$H+ }

Uses sysutils;

Var Dirs : **Array**[0..127] **of** pchar;
 I, Count : longint;
 Dir, NewDir : **String**;

Begin

 Dir := GetCurrentDir;
 WriteLn (' Dir _:_', Dir);
 NewDir := '' ;
 count := GetDirs (Dir , Dirs);
 For I := 0 **to** Count **do**
 begin
 NewDir := NewDir + '/' + **StrPas** (Dirs [I]);
 WriteLn (NewDir);
 end;

End.

RenameFile

Declaration: Function RenameFile(Const OldName, NewName : String) : Boolean;

Description: `RenameFile` renames a file from `OldName` to `NewName`. The function returns `True` if successful, `False` otherwise.

Remark: you cannot rename across disks or partitions.

Errors: On Error, `False` is returned.

See also: `DeleteFile` ([391](#))

Listing: `sysutex/ex44.pp`

```
Program Example44;

{ This program demonstrates the RenameFile function }

Uses sysutils;

Var F : Longint;
    S : String;

Begin
  S:= 'Some_short_file .';
  F:= FileCreate ( ' test.dap' );
  FileWrite (F, S[1], Length(S));
  FileClose (F);
  If RenameFile ( ' test.dap', ' test.dat' ) then
    WriteLn ( ' Successfully_renamed_files .' );
End.
```

SetDirSeparators

Declaration: `Function SetDirSeparators(Const FileName : String) : String;`

Description: `SetDirSeparators` returns `FileName` with all possible `DirSeparators` replaced by `OSDirSeparator`.

Errors: None.

See also: `ExpandFileName` ([392](#)), `ExtractFilePath` ([394](#)), `ExtractFileDir` ([393](#))

Listing: `sysutex/ex47.pp`

```
Program Example47;

{ This program demonstrates the SetDirSeparators function }

Uses sysutils;

Begin
  WriteLn ( SetDirSeparators ( '/ pp\ bin / win32\ppc386' ));
End.
```

20.7 PChar functions

Introduction

Most PChar functions are the same as their counterparts in the `STRINGS` unit. The following functions are the same :

1. `StrCat` (354) : Concatenates two `PChar` strings.
2. `StrComp` (355) : Compares two `PChar` strings.
3. `StrCopy` (355) : Copies a `PChar` string.
4. `StrECopy` (356) : Copies a `PChar` string and returns a pointer to the terminating null byte.
5. `StrEnd` (357) : Returns a pointer to the terminating null byte.
6. `StrIComp` (357) : Case insensitive compare of 2 `PChar` strings.
7. `StrLCat` (358) : Appends at most `L` characters from one `PChar` to another `PChar`.
8. `StrLComp` (358) : Case sensitive compare of at most `L` characters of 2 `PChar` strings.
9. `StrLCopy` (359) : Copies at most `L` characters from one `PChar` to another.
10. `StrLen` (359) : Returns the length (exclusive terminating null byte) of a `PChar` string.
11. `StrLIComp` (360) : Case insensitive compare of at most `L` characters of 2 `PChar` strings.
12. `StrLower` (360) : Converts a `PChar` to all lowercase letters.
13. `StrMove` (361) : Moves one `PChar` to another.
14. `StrNew` (361) : Makes a copy of a `PChar` on the heap, and returns a pointer to this copy.
15. `StrPos` (363) : Returns the position of one `PChar` string in another?
16. `StrRScan` (363) : returns a pointer to the last occurrence of on `PChar` string in another one.
17. `StrScan` (363) : returns a pointer to the first occurrence of on `PChar` string in another one.
18. `StrUpper` (364) : Converts a `PChar` to all uppercase letters.

The subsequent functions are different from their counterparts in `STRINGS`, although the same examples can be used.

StrAlloc

Declaration: `Function StrAlloc(Size: cardinal): PChar;`

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Additionally, `StrAlloc` allocates 4 extra bytes to store the size of the allocated memory. Therefore this function is NOT compatible with the `StrAlloc` (354) function of the `Strings` unit.

Errors: None.

See also: `StrBufSize` (406), `StrDispose` (406), `StrAlloc` (354)

For an example, see `StrBufSize` (406).

StrBufSize

Declaration: Function StrBufSize(var Str: PChar): cardinal;

Description: StrBufSize returns the memory allocated for Str. This function ONLY gives the correct result if Str was allocated using StrAlloc (405).

Errors: If no more memory is available, a runtime error occurs.

See also: StrAlloc (405).StrDispose (406).

Listing: sysutex/ex46.pp

Program Example46;

```
{ This program demonstrates the StrBufSize function }  
{$H+}
```

Uses sysutils;

Const S = 'Some_nice_string';

Var P : Pchar;

Begin

```
P:= StrAlloc (Length(S)+1);  
StrPCopy(P, S);  
Write (P, ' has length ', length(S));  
WriteLn (' and buffer size ', StrBufSize(P));  
StrDispose(P);
```

End.

StrDispose

Declaration: Procedure StrDispose(var Str: PChar);

Description: StrDispose frees any memory allocated for Str. This function will only function correctly if Str has been allocated using StrAlloc (405) from the SYSUTILS unit.

Errors: If an invalid pointer is passed, or a pointer not allocated with StrAlloc, an error may occur.

See also: StrBufSize (406), StrAlloc (405), StrDispose (356)

For an example, see StrBufSize (406).

StrPCopy

Declaration: Function StrPCopy(Dest: PChar; Source: string): PChar;

Description: StrPCopy Converts the Ansistring in Source to a Null-terminated string, and copies it to Dest. Dest needs enough room to contain the string Source, i.e. Length(Source)+1 bytes.

Errors: No checking is performed to see whether Dest points to enough memory to contain Source.

See also: StrPLCopy (407), StrPCopy (362)

For an example, see StrPCopy (362).

StrPLCopy

Declaration: `Function StrPLCopy(Dest: PChar; Source: string; MaxLen: cardinal): PChar;`

Description: `StrPLCopy` Converts maximally `MaxLen` characters of the Ansistring in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the characters.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `L` characters of `Source`.

Errors:

See also: `StrPCopy` ([406](#)).

StrPas

Declaration: `Function StrPas(Str: PChar): string;`

Description: Converts a null terminated string in `Str` to an Ansistring, and returns this string. This string is NOT truncated at 255 characters as is the

Errors: None.

See also: `StrPas` ([362](#)).

For an example, see `StrPas` ([362](#)).

20.8 String handling functions

AdjustLineBreaks

Declaration: `Function AdjustLineBreaks(const S: string): string;`

Description: `AdjustLineBreaks` will change all `#13` characters with `#13#10` on WINDOWS NT and DOS. On LINUX, all `#13#10` character pairs are converted to `#10` and single `#13` characters also.

Errors: None.

See also: `AnsiCompareStr` ([408](#)), `AnsiCompareText` ([408](#))

Listing: `sysutex/ex48.pp`

Program `Example48;`

{ This program demonstrates the AdjustLineBreaks function }

Uses `sysutils;`

Const

`S = 'This_is_a_string'#13' with_embedded'#10' linefeed_and' +
#13'CR_characters';`

Begin

`Writeln ( AdjustLineBreaks (S));`

End.

AnsiCompareStr

Declaration: Function AnsiCompareStr(const S1, S2: string): integer;

Description: AnsiCompareStr compares two strings and returns the following result:

<0 if S1<S2.

0 if S1=S2.

>0 if S1>S2.

the comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to AnsiCompareText (408), the comparison is case sensitive.

Errors: None.

See also: AdjustLineBreaks (407), AnsiCompareText (408)

Listing: sysutex/ex49.pp

Program Example49;

{ This program demonstrates the AnsiCompareStr function }
{ \$H+ }

Uses sysutils;

Procedure TestIt (S1, S2 : **String**);

Var R : Longint;

begin

 R:=AnsiCompareStr(S1, S2);

Write ('', S1, ' is ');

If R<0 **then**

write (' less_than ')

else If R=0 **then**

Write (' equal_to ')

else

Write (' larger_than ');

Writeln ('', S2, ' ');

end;

Begin

 Testit (' One_string ', ' One_smaller_string ');

 Testit (' One_string ', ' one_string ');

 Testit (' One_string ', ' One_string ');

 Testit (' One_string ', ' One_tall_string ');

End.

AnsiCompareText

Declaration: Function AnsiCompareText(const S1, S2: string): integer;

Description:

Description: AnsiCompareText compares two strings and returns the following result:

<0 if S1<S2.

0if S1=S2.

>0if S1>S2.

the comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to `AnsiCompareStr` (408), the comparison is case insensitive.

Errors: None.

See also: `AdjustLineBreaks` (407), `AnsiCompareText` (408)

Listing: sysutex/ex50.pp

Program Example49;

{ This program demonstrates the AnsiCompareText function }
{ \$H+ }

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

begin

 R:= **AnsiCompareText**(S1, S2);

Write ('""', S1, "" is '');

If R<0 **then**

write ('less_than_');

else If R=0 **then**

Write ('equal_to_');

else

Write ('larger_than_');

Writeln ('""', S2, '""');

end;

Begin

 Testit ('One_string ', 'One_smaller_string ');

 Testit ('One_string ', 'one_string ');

 Testit ('One_string ', 'One_string ');

 Testit ('One_string ', 'One_tall_string ');

End.

AnsiExtractQuotedStr

Declaration: `Function AnsiExtractQuotedStr(var Src: PChar; Quote: Char): string;`

Description: `AnsiExtractQuotedStr` Returns `Src` as a string,, with `Quote` characters removed from the beginning and end of the string, and double `Quote` characters replaced by a single `Quote` characters. As such, it reverses the action of `AnsiQuotedStr` (411).

Errors: None.

See also: `AnsiQuotedStr` (411)

Listing: sysutex/ex51.pp

```
Program Example51;

{ This program demonstrates the AnsiQuotedStr function }

Uses sysutils;

Var S : AnsiString;

Begin
  S:= 'He_said _"Hello "_and_walked_on';
  S:= AnsiQuotedStr (Pchar(S), ''' ');
  Writeln (S);
  Writeln (AnsiExtractQuotedStr (Pchar(S), ''' '));
End.
```

AnsiLastChar

Declaration: Function AnsiLastChar(const S: string): PChar;

Description: This function returns a pointer to the last character of S. Since multibyte characters are not yet supported, this is the same as @S[Length(S)].

Errors: None.

See also: AnsiStrLastChar ([413](#))

Listing: sysutex/ex52.pp

```
Program Example52;

{ This program demonstrates the AnsiLastChar function }

Uses sysutils;

Var S : AnsiString;
    L : Longint;

Begin
  S:= 'This_is_an_ansistring.';
  Writeln ( 'Last_character_of_S_is _:', AnsiLastChar(S));
  L:= Longint (AnsiLastChar(S)) - Longint (@S[1]) + 1;
  Writeln ( 'Length_of_S_is _:', L);
End.
```

AnsiLowerCase

Declaration: Function AnsiLowerCase(const s: string): string;

Description: AnsiLowerCase converts the string S to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark On linux, no language setting is taken in account yet.

Errors: None.

See also: [AnsiUpperCase \(416\)](#), [AnsiStrLower \(415\)](#), [AnsiStrUpper \(416\)](#)

Listing: sysutex/ex53.pp

```
Program Example53;

{ This program demonstrates the AnsiLowerCase function }

Uses sysutils;

Procedure Testit ( S : String );

begin
  WriteLn ( S, '_->_', AnsiLowerCase(S) );
end;

Begin
  Testit ( 'AN_UPPERCASE_STRING' );
  Testit ( 'Some_mixed_SString' );
  Testit ( 'a_lowercase_string' );
End.
```

AnsiQuotedStr

Declaration: Function AnsiQuotedStr(const S: string; Quote: char): string;

Description: AnsiQuotedString quotes the string S and returns the result. This means that it puts the Quote character at both the beginning and end of the string and replaces any occurrence of Quote in S with 2 Quote characters. The action of AnsiQuotedString can be reversed by [AnsiExtractQuotedStr \(409\)](#).

Errors: None.

See also: [AnsiExtractQuotedStr \(409\)](#)

For an example, see [AnsiExtractQuotedStr \(409\)](#)

AnsiStrComp

Declaration: Function AnsiStrComp(S1, S2: PChar): integer;

Description: AnsiStrComp compares 2 PChar strings, and returns the following result:

<0 if S1<S2.
0 if S1=S2.
>0 if S1>S2.

The comparison of the two strings is case-sensitive. The function does not yet take internationalization settings into account.

Errors: None.

See also: [AnsiCompareText \(408\)](#), [AnsiCompareStr \(408\)](#)

Listing: sysutex/ex54.pp

```
Program Example54;

{ This program demonstrates the AnsiStrComp function }

Uses sysutils;

Procedure TestIt ( S1,S2 : Pchar);

Var R : Longint;

begin
  R:= AnsiStrComp (S1, S2);
  Write ( ''' , S1, '' is _ ');
  If R<0 then
    write ( ' less_than _ ')
  else If R=0 then
    Write ( ' equal_to _ ')
  else
    Write ( ' larger_than _ ');
  Writeln ( ''' , S2, ''' );
end;

Begin
  Testit ( ' One_string ', ' One_smaller_string ');
  Testit ( ' One_string ', ' one_string ');
  Testit ( ' One_string ', ' One_string ');
  Testit ( ' One_string ', ' One_tall_string ');
End.
```

AnsiStrIComp

Declaration: Function AnsiStrIComp(S1, S2: PChar): integer;

Description: AnsiStrIComp compares 2 PChar strings, and returns the following result:

<0 if S1<S2.

0 if S1=S2.

>0 if S1>S2.

The comparison of the two strings is case-insensitive. The function does not yet take internationalization settings into account.

Errors: None.

See also: [AnsiCompareText \(408\)](#), [AnsiCompareStr \(408\)](#)

Listing: sysutex/ex55.pp

```
Program Example55;

{ This program demonstrates the AnsiStrIComp function }

Uses sysutils;

Procedure TestIt ( S1,S2 : Pchar);
```

```
Var R : Longint;

begin
  R:= AnsiStrIComp (S1,S2);
  Write ( ''' , S1, "' is ' );
  If R<0 then
    write ( ' less_than ' )
  else If R=0 then
    Write ( ' equal_to ' )
  else
    Write ( ' larger_than ' );
  Writeln ( ''' , S2, ''' );
end;

Begin
  Testit ( ' One_string ' , ' One_smaller_string ' );
  Testit ( ' One_string ' , ' one_string ' );
  Testit ( ' One_string ' , ' One_string ' );
  Testit ( ' One_string ' , ' One_tall_string ' );
End.
```

AnsiStrLastChar

Declaration: function AnsiStrLastChar(Str: PChar): PChar;

Declaration: AnsiStrLastChar returns a pointer to the last character of Str. Since multibyte characters are not yet supported, this is the same as StrEnd(Str)-1.

Errors: None.

See also: AnsiLastChar ([410](#))

Listing: sysutex/ex58.pp

```
Program Example58;

{ This program demonstrates the AnsiStrLastChar function }

Uses sysutils;

Var P : Pchar;
    L : Longint;

Begin
  P:= ' This_is_an_PChar_string . ' ;
  Writeln ( ' Last_character_of_P_is : ', AnsiStrLastChar (P));
  L:= Longint ( AnsiStrLastChar (P))- Longint (P)+1;
  Writeln ( ' Length_of_P_( ' , P, ' ) is : ', L);
End.
```

AnsiStrLComp

Declaration: Function AnsiStrLComp(S1, S2: PChar; MaxLen: cardinal): integer;

Description: AnsiStrLComp compares the first Maxlen characters of 2 PChar strings, S1 and S2, and returns the following result:

<0if S1<S2.

0if S1=S2.

>0if S1>S2.

The comparison of the two strings is case-sensitive. The function does not yet take internationalization settings into account.

Errors: None.

See also: [AnsiCompareText \(408\)](#), [AnsiCompareStr \(408\)](#)

Listing: sysutex/ex56.pp

Program Example56;

{ This program demonstrates the AnsiStrLComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar; L : longint);

Var R : Longint;

begin

R:= AnsiStrLComp(S1, S2, L);

Write (' First _', L, ' _ characters _of _"', S1, '" _ are _');

If R<0 **then**

write (' less _than _')

else If R=0 **then**

Write (' equal _to _')

else

Write (' larger _than _');

Writeln (' those _of _"', S2, '" ');

end;

Begin

Testit (' One_string ', ' One_smaller_string ', 255);

Testit (' One_string ', ' One_String ', 4);

Testit (' One_string ', ' 1_string ', 0);

Testit (' One_string ', ' One_string .' , 9);

End.

AnsiStrLIComp

Declaration: Function AnsiStrLIComp(S1, S2: PChar; MaxLen: cardinal): integer;

Description: AnsiStrLIComp compares the first MaxLen characters of 2 PChar strings, S1 and S2, and returns the following result:

<0if S1<S2.

0if S1=S2.

>0if S1>S2.

The comparison of the two strings is case-insensitive. The function does not yet take internationalization settings into account.

Errors: None.

See also: [AnsiCompareText \(408\)](#), [AnsiCompareStr \(408\)](#)

Listing: sysutex/ex57.pp

```
Program Example57;

{ This program demonstrates the AnsiStrLComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : PChar; L : longint);

Var R : Longint;

begin
  R:= AnsiStrLComp (S1, S2, L);
  Write ( ' First _', L, ' _ characters _of _"', S1, '" _ are _' );
  If R<0 then
    write ( ' less _than _' )
  else If R=0 then
    Write ( ' equal _to _' )
  else
    Write ( ' larger _than _' );
  Writeln ( ' those _of _"', S2, '" ' );
end;

Begin
  Testit ( ' One_string ', ' One_smaller_string ', 255);
  Testit ( ' ONE_STRING', ' one_String ', 4);
  Testit ( ' One_string ', ' 1_STRING', 0);
  Testit ( ' One_STRING', ' one_string .', 9);
End.
```

AnsiStrLower

Declaration: `Function AnsiStrLower(Str: PChar): PChar;`

Description: `AnsiStrLower` converts the `PChar` `Str` to lowercase characters and returns the resulting `pchar`. Note that `Str` itself is modified, not a copy, as in the case of [AnsiLowerCase \(410\)](#). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark On linux, no language setting is taken in account yet.

Errors: None.

See also: [AnsiStrUpper \(416\)](#), [AnsiLowerCase \(410\)](#)

Listing: sysutex/ex59.pp

```
Program Example59;

{ This program demonstrates the AnsiStrLower function }

Uses sysutils;
```

```
Procedure Testit ( S : Pchar);  
  
begin  
  Writeln ( S, ' _->_ ', AnsiStrLower (S))  
end;  
  
Begin  
  Testit ( ' AN_UPPERCASE_STRING' );  
  Testit ( ' Some_mixed_STRING' );  
  Testit ( ' a_lowercase_string ' );  
End.
```

AnsiStrUpper

Declaration: Function AnsiStrUpper(Str: PChar): PChar;

Description: AnsiStrUpper converts the PChar Str to uppercase characters and returns the resulting string. Note that Str itself is modified, not a copy, as in the case of AnsiUpperCase (416). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark On linux, no language setting is taken in account yet.

Errors: None.

See also: AnsiUpperCase (416), AnsiStrLower (415), AnsiLowerCase (410)

Listing: sysutex/ex60.pp

```
Program Example60;  
  
{ This program demonstrates the AnsiStrUpper function }  
  
Uses sysutils ;  
  
Procedure Testit ( S : Pchar);  
  
begin  
  Writeln ( S, ' _->_ ', AnsiStrUpper (S))  
end;  
  
Begin  
  Testit ( ' AN_UPPERCASE_STRING' );  
  Testit ( ' Some_mixed_STRING' );  
  Testit ( ' a_lowercase_string ' );  
End.
```

AnsiUpperCase

Declaration: Function AnsiUpperCase(const s: string): string;

Description: AnsiUpperCase converts the string S to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark On linux, no language setting is taken in account yet.

Errors: None.

See also: [AnsiStrUpper \(416\)](#), [AnsiStrLower \(415\)](#), [AnsiLowerCase \(410\)](#)

Listing: sysutex/ex61.pp

```
Program Example60;

{ This program demonstrates the AnsiUpperCase function }

Uses sysutils;

Procedure Testit ( S : String );

begin
  Writeln ( S, '→', AnsiUpperCase(S) )
end;

Begin
  Testit ( 'AN_UPPERCASE_STRING' );
  Testit ( 'Some_mixed_String' );
  Testit ( 'a_lowercase_string' );
End.
```

AppendStr

Declaration: `Procedure AppendStr(var Dest: String; const S: string);`

Description: AppendStr appends S to Dest.

This function is provided for Delphi compatibility only, since it is completely equivalent to `Dest := Dest+S`.

Errors: None.

See also: [AssignStr \(417\)](#), [NewStr \(282\)](#), [DisposeStr \(283\)](#)

Listing: sysutex/ex62.pp

```
Program Example62;

{ This program demonstrates the AppendStr function }

Uses sysutils;

Var S : AnsiString;

Begin
  S:= ' This_is_an_';
  AppendStr(S, ' AnsiString ');
  Writeln ( ' S_=', S, ' ');
End.
```

AssignStr

Declaration: `Procedure AssignStr(var P: PString; const S: string);`

Description: AssignStr allocates S to P. The old value of P is disposed of.

This function is provided for Delphi compatibility only. AnsiStrings are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

Errors: None.

See also: NewStr ([282](#)), AppendStr ([417](#)), DisposeStr ([283](#))

Listing: sysutex/ex63.pp

Program Example63;

{ This program demonstrates the AssignStr function }
{ \$H+ }

Uses sysutils ;

Var P : PString ;

Begin

P:=NewStr('A_first_ansiString ');
Writeln (' Before: P=', P^, '');
AssignStr(P, 'A_Second_ansistring ');
Writeln (' After: P=', P^, '');
DisposeStr(P);

End.

BCDToInt

Declaration: Function BCDToInt(Value: integer): integer;

Description: BCDToInt converts a BCD coded integer to a normal integer.

Errors: None.

See also: StrToInt ([436](#)), IntToStr ([431](#))

Listing: sysutex/ex64.pp

Program Example64;

{ This program demonstrates the BCDToInt function }

Uses sysutils ;

Procedure Testit (L : longint);

begin

Writeln (L, ' -> ', BCDToInt(L));

end;

Begin

Testit(10);
Testit(100);
Testit(1000);

End.

CompareMem

Declaration: `Function CompareMem(P1, P2: Pointer; Length: cardinal): integer;`

Description: `CompareMem` compares, byte by byte, 2 memory areas pointed to by `P1` and `P2`, for a length of `L` bytes.

It returns the following values:

<0 if at some position the byte at `P1` is less than the byte at the same position at `P2`.

0 if all `L` bytes are the same.

3

Errors:

See also:

CompareStr

Declaration: `Function CompareStr(const S1, S2: string): Integer;`

Description: `CompareStr` compares two strings, `S1` and `S2`, and returns the following result:

<0 if `S1`<`S2`.

0 if `S1`=`S2`.

>0 if `S1`>`S2`.

The comparison of the two strings is case-sensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: [AnsiCompareText \(408\)](#), [AnsiCompareStr \(408\)](#), [CompareText \(420\)](#)

Listing: `sysutex/ex65.pp`

Program `Example65;`

```
{ This program demonstrates the CompareStr function }
{$H+}
```

Uses `sysutils;`

Procedure `TestIt (S1, S2 : String);`

Var `R : Longint;`

begin

`R:=CompareStr(S1, S2);`

`Write ( ' ', S1, ' is ' );`

`If R<0 then`

`write ( ' less_than ' )`

`else If R=0 then`

`Write ( ' equal_to ' )`

`else`

`Write ( ' larger_than ' );`

`Writeln ( ' ', S2, ' ' );`

end;

```
Begin
  Testit ( 'One_string ' , 'One_smaller_string ' );
  Testit ( 'One_string ' , 'one_string ' );
  Testit ( 'One_string ' , 'One_string ' );
  Testit ( 'One_string ' , 'One_tall_string ' );
End.
```

CompareText

Declaration: Function CompareText(const S1, S2: string): integer;

Description: CompareText compares two strings, S1 and S2, and returns the following result:

<0if S1<S2.
0if S1=S2.
>0if S1>S2.

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: AnsiCompareText ([408](#)), AnsiCompareStr ([408](#)), CompareStr ([419](#))

Listing: sysutex/ex66.pp

```
Program Example66;

{ This program demonstrates the CompareText function }
{$H+}

Uses sysutils ;

Procedure TestIt ( S1,S2 : String );

Var R : Longint ;

begin
  R:= CompareText(S1, S2);
  Write ( '' , S1, ''_ is _' );
  If R<0 then
    write ( ' less_than _' )
  else If R=0 then
    Write ( ' equal_to _' )
  else
    Write ( ' larger_than _' );
  Writeln ( '' , S2, ''' );
end;

Begin
  Testit ( 'One_string ' , 'One_smaller_string ' );
  Testit ( 'One_string ' , 'one_string ' );
  Testit ( 'One_string ' , 'One_string ' );
  Testit ( 'One_string ' , 'One_tall_string ' );
End.
```

DisposeStr

Declaration: Procedure DisposeStr(S: PString);

Description: DisposeStr removes the dynamically allocated string S from the heap, and releases the occupied memory.

This function is provided for Delphi compatibility only. AnsiStrings are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

Errors: None.

See also: NewStr ([282](#)), AppendStr ([417](#)), AssignStr ([417](#))

For an example, see DisposeStr ([283](#)).

FloatToStr

Declaration: Function FloatToStr(Value: Extended): String;

Description: FloatToStr converts the floating point variable Value to a string representation. It will choose the shortest possible notation of the two following formats:

Fixed format will represent the string in fixed notation,

Decimal format will represent the string in scientific notation.

(more information on these formats can be found in FloatToStrF ([422](#))) FloatToStr is completely equivalent to a FloatToStrF(Value, ffGeneral, 15, 0); call.

Errors: None.

See also: FloatToStrF ([422](#))

Listing: sysutex/ex67.pp

```
Program Example67;

{ This program demonstrates the FloatToStr function }

Uses sysutils;

Procedure Testit (Value : Extended);

begin
  Writeln ( Value, ' -> ', FloatToStr (Value));
  Writeln (- Value, ' -> ', FloatToStr (-Value));
end;

Begin
  Testit (0.0);
  Testit (1.1);
  Testit (1.1 e-3);
  Testit (1.1 e-20);
  Testit (1.1 e-200);
  Testit (1.1 e+3);
  Testit (1.1 e+20);
  Testit (1.1 e+200);
End.
```

FloatToStrF

Declaration: `Function FloatToStrF(Value: Extended; format: TFloatFormat; Precision, Digits: Integer): String;`

Description: `FloatToStrF` converts the floating point number `Value` to a string representation, according to the settings of the parameters `Format`, `Precision` and `Digits`.

The meaning of the `Precision` and `Digits` parameter depends on the `Format` parameter. The format is controlled mainly by the `Format` parameter. It can have one of the following values:

ffcurrency Money format. `Value` is converted to a string using the global variables `CurrencyString`, `CurrencyFormat` and `NegCurrencyFormat`. The `Digits` parameter specifies the number of digits following the decimal point and should be in the range -1 to 18. If `Digits` equals -1, `CurrencyDecimals` is assumed. The `Precision` parameter is ignored.

ffExponent Scientific format. `Value` is converted to a string using scientific notation: 1 digit before the decimal point, possibly preceded by a minus sign if `Value` is negative. The number of digits after the decimal point is controlled by `Precision` and must lie in the range 0 to 15.

ffFixed Fixed point format. `Value` is converted to a string using fixed point notation. The result is composed of all digits of the integer part of `Value`, preceded by a minus sign if `Value` is negative. Following the integer part is `DecimalSeparator` and then the fractional part of `Value`, rounded off to `Digits` numbers. If the number is too large then the result will be in scientific notation.

ffGeneral General number format. The argument is converted to a string using `ffExponent` or `ffFixed` format, depending on which one gives the shortest string. There will be no trailing zeroes. If `Value` is less than 0.00001 or if the number of decimals left of the decimal point is larger than `Precision` then scientific notation is used, and `Digits` is the minimum number of digits in the exponent. Otherwise `Digits` is ignored.

ffnumber Is the same as `ffFixed`, except that thousand separators are inserted in the resultig string.

Errors: None.

See also: `FloatToStr` ([421](#)), `FloatToText` ([423](#))

Listing: `sysutex/ex68.pp`

```

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : Array [ TFloatFormat ] of string [10] =
    ( ' general ', ' exponent ', ' fixed ', ' number ', ' Currency ' );

Procedure Testit ( Value : Extended );

Var I, J : longint;
    FF : TFloatFormat;

begin
    For I:=5 to 15 do
        For J:=1 to 4 do
            For FF:=ffgeneral to ffcurrency do
                begin
                    Write ( Value, '( Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ ff ], ') ');
                    WriteLn ( FloatToStrf ( Value, FF, I, J ));
                end

```



```

    Write ( - Value, '( Prec:␣', I:2, ',␣ Dig:␣', J, ',␣ fmt ␣:␣', Fmt[ ff ], ')␣:␣' );
    Writeln ( FloatToStrf(-Value, FF, I, J));
end;

end;

Begin
  Testit (1.1);
  Testit (1.1 E1);
  Testit (1.1 E-1);
  Testit (1.1 E5);
  Testit (1.1 E-5);
  Testit (1.1 E10);
  Testit (1.1 E-10);
  Testit (1.1 E15);
  Testit (1.1 E-15);
  Testit (1.1 E100);
  Testit (1.1 E-100);
End.

```

FloatToText

Declaration: Function FloatToText(Buffer : Pchar; Value: Extended; Format: TFloatFormat; Precision, Digits: Integer): Longint;

Description: FloatToText converts the floating point variable Value to a string representation and stores it in Buffer. The conversion is governed by format, Precision and Digits. more information on these parameters can be found in FloatToStrF (422). Buffer should point to enough space to hold the result. No checking on this is performed.

The result is the number of characters that was copied in Buffer.

Errors: None.

See also: FloatToStr (421), FloatToStrF (422)

Listing: sysutex/ex69.pp

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : **Array** [TFloatFormat] **of string** [10] =
 (' general ', ' exponent ', ' fixed ', ' number ', ' Currency ');

Procedure Testit (Value : Extended);

Var I, J : longint;
 FF : TFloatFormat;
 S : ShortString;

begin

For I:=5 **to** 15 **do**

For J:=1 **to** 4 **do**

For FF:=ffgeneral **to** ffcurrency **do**

begin

Write (Value, '(Prec:␣', I:2, ',␣ Dig:␣', J, ',␣ fmt ␣:␣', Fmt[ff], ')␣:␣');

```

    SetLength(S, FloatToText (@S[1], Value, FF, I, J));
    Writeln (S);
    Write (- Value, '( Prec: ', I : 2, ', Dig: ', J, ', fmt: ', Fmt[ ff ], ') ');
    SetLength(S, FloatToText (@S[1], - Value, FF, I, J));
    Writeln (S);
end;

Begin
    Testit (1.1);
    Testit (1.1 E1);
    Testit (1.1 E-1);
    Testit (1.1 E5);
    Testit (1.1 E-5);
    Testit (1.1 E10);
    Testit (1.1 E-10);
    Testit (1.1 E15);
    Testit (1.1 E-15);
    Testit (1.1 E100);
    Testit (1.1 E-100);
End.

```

FmtStr

Declaration: Procedure (Var Res: String; Const Fmt : String; Const args: Array of const);

Description: FmtStr calls Format (424) with Fmt and Args as arguments, and stores the result in Res. For more information on how the resulting string is composed, see Format (424).

Errors: In case of error, a EConvertError exception is raised.

See also: Format (424), FormatBuf (430).

Listing: sysutex/ex70.pp

```

Program Example70;

{ This program demonstrates the FmtStr function }

Uses sysutils;

Var S : AnsiString;

Begin
    S:= '';
    FmtStr ( S, ' For some nice examples of formatting see %s. ', [ ' Format' ] );
    Writeln ( S);
End.

```

Format

Declaration: Function Format(Const Fmt : String; const Args : Array of const) : String;

Description: Format replaces all placeholders in Fmt with the arguments passed in Args and returns the resulting string. A placeholder looks as follows:

'%' [Index':'] ['-'] [Width] ['.' Precision] ArgType

elements between single quotes must be typed as shown without the quotes, and elements between square brackets [] are optional. The meaning of the different elements is shown below:

'%' starts the placeholder. If you want to insert a literal % character, then you must insert two of them : %%.

Index ':' takes the Index-th element in the argument array as the element to insert.

'-' tells Format to left-align the inserted text. The default behaviour is to right-align inserted text. This can only take effect if the Width element is also specified.

Width the inserted string must have at least have Width characters. If not, the inserted string will be padded with spaces. By default, the string is left-padded, resulting in a right-aligned string. This behaviour can be changed by the ' - ' character.

'.' Precision Indicates the precision to be used when converting the argument. The exact meaning of this parameter depends on ArgType.

The Index, Width and Precision parameters can be replaced by *, in which case their value will be read from the next element in the Args array. This value must be an integer, or an EConvertError exception will be raised.

The argument type is determined from ArgType. It can have one of the following values (case insensitive):

D Decimal format. The next argument in the Args array should be an integer. The argument is converted to a decimal string,. If precision is specified, then the string will have at least Precision digits in it. If needed, the string is (left) padded with zeroes.

E Scientific format. The next argument in the Args array should be a Floating point value. The argument is converted to a decimal string using scientific notation, using FloatToStrF (422), where the optional precision is used to specify the total number of decimals. (default a value of 15 is used). The exponent is formatted using maximally 3 digits.

In short, the E specifier formats it's argument as follows:

```
FloatToStrF(Argument, ffexponent, Precision, 3)
```

F Fixed point format. The next argument in the Args array should be a floating point value. The argument is converted to a decimal string, using fixed notation (see FloatToStrF (422)). Precision indicates the number of digits following the decimal point.

In short, the F specifier formats it's argument as follows:

```
FloatToStrF(Argument, ffFixed, Precision, 9999, Precision)
```

G General number format. The next argument in the Args array should be a floating point value. The argument is converted to a decimal string using fixed point notation or scientific notation, depending on which gives the shortest result. Precision is used to determine the number of digits after the decimal point.

In short, the G specifier formats it's argument as follows:

```
FloatToStrF(Argument, ffGeneral, Precision, 3)
```

M Currency format. the next argument in the varArgs array must be a floating point value. The argument is converted to a decimal string using currency notation. This means that fixed-point notation is used, but that the currency symbol is appended. If precision is specified, then then it overrides the CurrencyDecimals global variable used in the FloatToStrF (422)

In short, the M specifier formats it's argument as follows:

```
FloatToStrF(Argument, ffCurrency, 9999, Precision)
```

NNumber format. This is the same as fixed point format, except that thousand separators are inserted in the resulting string.

PPointer format. The next argument in the **Args** array must be a pointer (typed or untyped). The pointer value is converted to a string of length 8, representing the hexadecimal value of the pointer.

SString format. The next argument in the **Args** array must be a string. The argument is simply copied to the result string. If **Precision** is specified, then only **Precision** characters are copied to the result string.

Xhexadecimal format. The next argument in the **Args** array must be an integer. The argument is converted to a hexadecimal string with just enough characters to contain the value of the integer. If **Precision** is specified then the resulting hexadecimal representation will have at least **Precision** characters in it (with a maximum value of 32).

Errors: In case of error, an **EConversionError** exception is raised. Possible errors are:

- 1.Errors in the format specifiers.
- 2.The next argument is not of the type needed by a specifier.
- 3.The number of arguments is not sufficient for all format specifiers.

See also: [FormatBuf \(430\)](#)

Listing: sysutex/ex71.pp

```
Program example71;

{$mode objfpc}

{ This program demonstrates the Format function }

Uses sysutils;

Var P : Pointer;
    fmt,S : string;

Procedure TestInteger;

begin
  Try
    Fmt:='[%d]'; S:=Format ( Fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%%]'; S:=Format ( Fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%10d]'; S:=Format ( Fmt,[10]); writeln (Fmt:12, '=>', s);
    fmt:='[%.4d]'; S:=Format ( fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%10.4d]'; S:=Format ( Fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%0:d]'; S:=Format ( Fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%0:10d]'; S:=Format ( Fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%0:10.4d]'; S:=Format ( Fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%0:-10d]'; S:=Format ( Fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%0:-10.4d]'; S:=Format ( fmt,[10]); writeln (Fmt:12, '=>', s);
    Fmt:='[%-*.d]'; S:=Format ( fmt,[4,5,10]); writeln (Fmt:12, '=>', s);
  except
    On E : Exception do
      begin
        Writeln ( ' Exception_caught _:', E. Message);
      end;
  end;
  writeln ( ' Press_enter ');
```

```

    readln;
end;

Procedure TestHexaDecimal;

begin
    try
        Fmt:='%x'; S:=Format ( Fmt,[10]); writeln (Fmt:12,'=>',s);
        Fmt:='%10x'; S:=Format ( Fmt,[10]); writeln (Fmt:12,'=>',s);
        Fmt:='%10.4x'; S:=Format ( Fmt,[10]); writeln (Fmt:12,'=>',s);
        Fmt:='%0:x'; S:=Format ( Fmt,[10]); writeln (Fmt:12,'=>',s);
        Fmt:='%0:10x'; S:=Format ( Fmt,[10]); writeln (Fmt:12,'=>',s);
        Fmt:='%0:10.4x'; S:=Format ( Fmt,[10]); writeln (Fmt:12,'=>',s);
        Fmt:='%0:-10x'; S:=Format ( Fmt,[10]); writeln (Fmt:12,'=>',s);
        Fmt:='%0:-10.4x'; S:=Format ( fmt,[10]); writeln (Fmt:12,'=>',s);
        Fmt:='%-*.x'; S:=Format ( fmt,[4,5,10]); writeln (Fmt:12,'=>',s);
    except
        On E : Exception do
            begin
                Writeln ( ' Exception_caught_:',E.Message);
            end;
    end;
    writeln ( ' Press_enter ');
    readln;
end;

Procedure TestPointer;

begin
    P:=Pointer(1234567);
    try
        Fmt:='[0 x%p]'; S:=Format ( Fmt,[P]); writeln (Fmt:12,'=>',s);
        Fmt:='[0 x%10p]'; S:=Format ( Fmt,[P]); writeln (Fmt:12,'=>',s);
        Fmt:='[0 x%10.4p]'; S:=Format ( Fmt,[P]); writeln (Fmt:12,'=>',s);
        Fmt:='[0 x%0:p]'; S:=Format ( Fmt,[P]); writeln (Fmt:12,'=>',s);
        Fmt:='[0 x%0:10p]'; S:=Format ( Fmt,[P]); writeln (Fmt:12,'=>',s);
        Fmt:='[0 x%0:10.4p]'; S:=Format ( Fmt,[P]); writeln (Fmt:12,'=>',s);
        Fmt:='[0 x%0:-10p]'; S:=Format ( Fmt,[P]); writeln (Fmt:12,'=>',s);
        Fmt:='[0 x%0:-10.4p]'; S:=Format ( fmt,[P]); writeln (Fmt:12,'=>',s);
        Fmt:='%-*.p'; S:=Format ( fmt,[4,5,P]); writeln (Fmt:12,'=>',s);
    except
        On E : Exception do
            begin
                Writeln ( ' Exception_caught_:',E.Message);
            end;
    end;
    writeln ( ' Press_enter ');
    readln;
end;

Procedure TestString;

begin
    try
        Fmt:='%s'; S:=Format(fmt,[' This_is_a_string ']); Writeln (fmt:12,'=>',s);
        Fmt:='%0:s'; s:=Format(fmt,[' This_is_a_string ']); Writeln (fmt:12,'=>',s);
        Fmt:='%0:18s'; s:=Format(fmt,[' This_is_a_string ']); Writeln (fmt:12,'=>',s);
        Fmt:='%0:-18s'; s:=Format(fmt,[' This_is_a_string ']); Writeln (fmt:12,'=>',s);
    
```

```

    fmt:='[%0:18.12 s]'; s:=Format(fmt,[ ' This_is_a_string ']); Writeln (fmt:12, '=>', s);
    fmt:='[%-*.*s]'; s:=Format(fmt,[18,12, ' This_is_a_string ']); Writeln (fmt:12, '=>', s);
except
  On E : Exception do
    begin
      Writeln ( ' Exception_caught _:_', E. Message);
    end;
end;
writeln ( ' Press_enter ');
readln;
end;

```

Procedure TestExponential;

```

begin
  Try
    Fmt:='[%e]'; S:=Format ( Fmt,[1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%10e]'; S:=Format ( Fmt,[1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%10.4e]'; S:=Format ( Fmt,[1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:e]'; S:=Format ( Fmt,[1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:10e]'; S:=Format ( Fmt,[1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:10.4e]'; S:=Format ( Fmt,[1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:-10e]'; S:=Format ( Fmt,[1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:-10.4e]'; S:=Format ( fmt,[1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%-*.*e]'; S:=Format ( fmt,[4,5,1.234]); writeln (Fmt:12, ' _=>', s);
  except
    On E : Exception do
      begin
        Writeln ( ' Exception_caught _:_', E. Message);
      end;
    end;
    writeln ( ' Press_enter ');
    readln;
  end;

```

Procedure TestNegativeExponential;

```

begin
  Try
    Fmt:='[%e]'; S:=Format ( Fmt,[-1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%10e]'; S:=Format ( Fmt,[-1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%10.4e]'; S:=Format ( Fmt,[-1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:e]'; S:=Format ( Fmt,[-1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:10e]'; S:=Format ( Fmt,[-1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:10.4e]'; S:=Format ( Fmt,[-1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:-10e]'; S:=Format ( Fmt,[-1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%0:-10.4e]'; S:=Format ( fmt,[-1.234]); writeln (Fmt:12, ' _=>', s);
    Fmt:='[%-*.*e]'; S:=Format ( fmt,[4,5,-1.234]); writeln (Fmt:12, ' _=>', s);
  except
    On E : Exception do
      begin
        Writeln ( ' Exception_caught _:_', E. Message);
      end;
    end;
    writeln ( ' Press_enter ');
    readln;
  end;

```

Procedure TestSmallExponential ;

begin

Try

```
        Fmt:='[%e]';S:=Format ( Fmt,[0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%10e]';S:=Format ( Fmt,[0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%10.4e]';S:=Format ( Fmt,[0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:e]';S:=Format ( Fmt,[0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:10e]';S:=Format ( Fmt,[0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:10.4e]';S:=Format ( Fmt,[0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:-10e]';S:=Format ( Fmt,[0.0123]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:-10.4e]';S:=Format ( fmt,[0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%-*.e]';S:=Format ( fmt,[4,5,0.01234]);writeln (Fmt:12,'_=>_',s);
```

except

On E : Exception **do**

begin

 WriteLn (' Exception_caught _:',E. Message);

end;

end;

 writeln (' Press_enter ');

 readln;

end;

Procedure TestSmallNegExponential ;

begin

Try

```
        Fmt:='[%e]';S:=Format ( Fmt,[-0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%10e]';S:=Format ( Fmt,[-0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%10.4e]';S:=Format ( Fmt,[-0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:e]';S:=Format ( Fmt,[-0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:10e]';S:=Format ( Fmt,[-0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:10.4e]';S:=Format ( Fmt,[-0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:-10e]';S:=Format ( Fmt,[-0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%0:-10.4e]';S:=Format ( fmt,[-0.01234]);writeln (Fmt:12,'_=>_',s);
        Fmt:='[%-*.e]';S:=Format ( fmt,[4,5,-0.01234]);writeln (Fmt:12,'_=>_',s);
```

except

On E : Exception **do**

begin

 WriteLn (' Exception_caught _:',E. Message);

end;

end;

 writeln (' Press_enter ');

 readln;

end;

begin

 TestInteger ;

 TestHexadecimal ;

 TestPointer ;

 TestExponential ;

 TestNegativeExponential ;

 TestSmallExponential ;

 TestSmallNegExponential ;

end.

FormatBuf

Declaration: Function FormatBuf(Var Buffer; BufLen : Cardinal; Const Fmt; fmtLen : Cardinal; Const Args : Array of const) : Cardinal;

Description: Format

Errors:

See also:

Listing: sysutex/ex72.pp

```
Program Example72;

{ This program demonstrates the FormatBuf function }

Uses sysutils;

Var
  S : ShortString;

Const
  Fmt : ShortString = 'For_some_nice_examples_of_formatting_see_%s.';

Begin
  S:= '';
  SetLength(S, FormatBuf (S[1],255, Fmt[1], Length(Fmt),[ 'Format' ]));
  Writeln (S);
End.
```

IntToHex

Declaration: Function IntToHex(Value: integer; Digits: integer): string;

Description: IntToHex converts Value to a hexadecimal string representation. The result will contain at least Digits characters. If Digits is less than the needed number of characters, the string will NOT be truncated. If Digits is larger than the needed number of characters, the result is padded with zeroes.

Errors: None.

See also: IntToStr ([431](#)), StrToInt

Listing: sysutex/ex73.pp

```
Program Example73;

{ This program demonstrates the IntToHex function }

Uses sysutils;

Var I : longint;

Begin
  For I:=0 to 31 do
    begin
```



```
      Writeln (IntToHex(1 shl I,8));  
      Writeln (IntToHex(15 shl I,8))  
    end;  
End.
```

IntToStr

Declaration: Function IntToStr(Value: integer): string;

Description: IntToStr converts Value to its string representation. The resulting string has only as much characters as needed to represent the value. If the value is negative a minus sign is prepended to the string.

Errors: None.

See also: IntToHex ([430](#)), StrToInt ([436](#))

Listing: sysutex/ex74.pp

```
Program Example74;  
  
{ This program demonstrates the IntToStr function }  
  
Uses sysutils;  
  
Var I : longint;  
  
Begin  
  For I:=0 to 31 do  
    begin  
      Writeln (IntToStr(1 shl I));  
      Writeln (IntToStr(15 shl I));  
    end;  
End.
```

IsValidIdent

Declaration: Function IsValidIdent(const Ident: string): boolean;

Description: IsValidIdent returns True if Ident can be used as a component name. It returns False otherwise. Ident must consist of a letter or underscore, followed by a combination of letters, numbers or underscores to be a valid identifier.

Errors: None.

See also:

Listing: sysutex/ex75.pp

```
Program Example75;  
  
{ This program demonstrates the IsValidIdent function }  
  
Uses sysutils;  
  
Procedure Testit (S : String);
```

```
begin
  Write ( ''' , S, ' is ' );
  If not IsValidIdent(S) then
    Write('NOT ');
  Writeln ( ' a valid identifier ' );
end;

Begin
  Testit ( '_MyObj' );
  Testit ( ' My__Obj1' );
  Testit ( ' My_1_Obj' );
  Testit ( '1 MyObject' );
  Testit ( ' My@Object' );
  Testit ( ' M123' );
End.
```

LastDelimiter

Declaration: Function LastDelimiter(const Delimiters, S: string): Integer;

Description: LastDelimiter returns the *last* occurrence of any character in the set Delimiters in the string S.

Errors:

See also:

Listing: sysutex/ex88.pp

```
Program example88;

{ This program demonstrates the LastDelimiter function }

uses SysUtils;

begin
  Writeln ( LastDelimiter ( '\.:', 'c:\ filename . ext' ));
end.
```

LeftStr

Declaration: Function LeftStr(const S: string; Count: integer): string;

Description: LeftStr returns the Count leftmost characters of S. It is equivalent to a call to Copy(S, 1, Count).

Errors: None.

See also: RightStr ([434](#)), TrimLeft ([437](#)), TrimRight ([438](#)), Trim ([437](#))

Listing: sysutex/ex76.pp

```
Program Example76;

{ This program demonstrates the LeftStr function }
```

Uses sysutils ;

Begin

```
Writeln ( LeftStr ( ' abcdefghijklmnopqrstuvwxyz ',20));  
Writeln ( LeftStr ( ' abcdefghijklmnopqrstuvwxyz ',15));  
Writeln ( LeftStr ( ' abcdefghijklmnopqrstuvwxyz ',1));  
Writeln ( LeftStr ( ' abcdefghijklmnopqrstuvwxyz ',200));
```

End.

LoadStr

Declaration: Function LoadStr(Ident: integer): string;

Description: This function is not yet implemented. resources are not yet supported.

Errors:

See also:

LowerCase

Declaration: Function LowerCase(const s: string): string;

Description: LowerCase returns the lowercase equivalent of S. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the lowercase function of the system unit, and is provided for compatibility only.

Errors: None.

See also: AnsiLowerCase ([410](#)), UpperCase ([439](#)), AnsiUpperCase ([416](#))

Listing: sysutex/ex77.pp

Program Example77;

{ This program demonstrates the LowerCase function }

Uses sysutils ;

Begin

```
Writeln ( LowerCase( ' THIS_WILL_COME_out_all _LoWeRcAsE_!' ));
```

End.

NewStr

Declaration: Function NewStr(const S: string): PString;

Description: NewStr assigns a new dynamic string on the heap, copies S into it, and returns a pointer to the newly assigned string.

This function is obsolete, and shouldn't be used any more. The AnsiString mechanism also allocates ansistrings on the heap, and should be preferred over this mechanism.

Errors: If not enough memory is present, an EOutOfMemory exception will be raised.

See also: AssignStr ([417](#)), DisposeStr ([421](#))

For an example, see AssignStr ([417](#)).

QuotedStr

Declaration: `Function QuotedStr(const S: string): string;`

Description: `QuotedStr` returns the string `S`, quoted with single quotes. This means that `S` is enclosed in single quotes, and every single quote in `S` is doubled. It is equivalent to a call to `AnsiQuotedStr(S, '"')`.

Errors: None.

See also: `AnsiQuotedStr` ([411](#)), `AnsiExtractQuotedStr` ([409](#)).

Listing: `sysutex/ex78.pp`

```
Program Example78;

{ This program demonstrates the QuotedStr function }

Uses sysutils;

Var S : AnsiString;

Begin
  S:= 'He_said _' ' Hello ' ' _and_walked_on' ;
  Writeln ( S);
  Writeln ( ' _ _ becomes' );
  Writeln ( QuotedStr(S));
End.
```

RightStr

Declaration: `Function RightStr(const S: string; Count: integer): string;`

Description: `RightStr` returns the `Count` rightmost characters of `S`. It is equivalent to a call to `Copy(S, Length(S)+1-Count, Count)`.
If `Count` is larger than the actual length of `S` only the real length will be used.

Errors: None.

See also: `LeftStr` ([432](#)), `Trim` ([437](#)), `TrimLeft` ([437](#)), `TrimRight` ([438](#))

Listing: `sysutex/ex79.pp`

```
Program Example79;

{ This program demonstrates the RightStr function }

Uses sysutils;

Begin
  Writeln ( RightStr ( ' abcdefghijklmnopqrstuvwxyz ',20));
  Writeln ( RightStr ( ' abcdefghijklmnopqrstuvwxyz ',15));
  Writeln ( RightStr ( ' abcdefghijklmnopqrstuvwxyz ',1));
  Writeln ( RightStr ( ' abcdefghijklmnopqrstuvwxyz ',200));
End.
```

StrFmt

Declaration: Function StrFmt(Buffer, Fmt : PChar; Const args: Array of const) : PChar;

Description: StrFmt will format `fmt` with `Args`, as the `Format` ([424](#)) function does, and it will store the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain the whole result.

Errors: for a list of errors, see `Format` ([424](#)).

See also: `StrLFmt` ([435](#)), `FmtStr` ([424](#)), `Format` ([424](#)), `FormatBuf` ([430](#))

Listing: sysutex/ex80.pp

```
Program Example80;

{ This program demonstrates the StrFmt function }

Uses sysutils;

Var S : AnsiString;

Begin
  SetLength(S, 80);
  Writeln ( StrFmt (@S[1], ' For some nice examples of formatting see %s.' , [ ' Format' ]));
End.
```

StrLFmt

Declaration: Function StrLFmt(Buffer : PChar; Maxlen : Cardinal; Fmt : PChar; Const args: Array of const) : PChar;

Description: StrLFmt will format `fmt` with `Args`, as the `Format` ([424](#)) function does, and it will store maximally `Maxlen` characters of the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain `MaxLen` characters.

Errors: for a list of errors, see `Format` ([424](#)).

See also: `StrFmt` ([435](#)), `FmtStr` ([424](#)), `Format` ([424](#)), `FormatBuf` ([430](#))

Listing: sysutex/ex81.pp

```
Program Example80;

{ This program demonstrates the StrFmt function }

Uses sysutils;

Var S : AnsiString;

Begin
  SetLength(S, 80);
  Writeln ( StrLFmt (@S[1], 80, ' For some nice examples of formatting see %s.' , [ ' Format' ]));
End.
```

StrToInt

Declaration: `Function StrToInt(const s: string): integer;`

Description: `StrToInt` will convert the string `S` to an integer. If the string contains invalid characters or has an invalid format, then an `EConvertError` is raised.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

Errors: In case of error, an `EConvertError` is raised.

See also: `IntToStr` ([431](#)), `StrToIntDef` ([436](#))

Listing: `sysutex/ex82.pp`

Program `Example82;`

`{ $mode objfpc }`

`{ This program demonstrates the StrToInt function }`

Uses `sysutils;`

Begin

`Writeln ( StrToInt ('1234' ));`

`Writeln ( StrToInt ('-1234' ));`

`Writeln ( StrToInt ('0' ));`

`Try`

`Writeln ( StrToInt ('12345678901234567890' ));`

`except`

`On E : EConvertError do`

`Writeln ( ' Invalid _number _encountered ' );`

`end;`

End.

StrToIntDef

Declaration: `Function StrToIntDef(const S: string; Default: integer): integer;`

Description: `StrToIntDef` will convert a string to an integer. If the string contains invalid characters or has an invalid format, then `Default` is returned.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

Errors: None.

See also: `IntToStr` ([431](#)), `StrToInt` ([436](#))

Listing: `sysutex/ex83.pp`

Program `Example82;`

`{ $mode objfpc }`

`{ This program demonstrates the StrToInt function }`

```
Uses sysutils ;

Begin
  Writeln ( StrToIntDef('1234',0));
  Writeln ( StrToIntDef('-1234',0));
  Writeln ( StrToIntDef('0',0));
  Try
    Writeln ( StrToIntDef('12345678901234567890',0));
  except
    On E : EConvertError do
      Writeln ( ' Invalid _number_encountered ');
  end;
End.
```

Trim

Declaration: Function Trim(const S: string): string;

Description: Trim strips blank characters (spaces) at the beginning and end of S and returns the resulting string.
Only #32 characters are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: TrimLeft ([437](#)), TrimRight ([438](#))

Listing: sysutex/ex84.pp

```
Program Example84;

{ This program demonstrates the Trim function }

Uses sysutils ;
{$H+}

Procedure Testit ( S : String );

begin
  Writeln ( '' , Trim(S), '' );
end;

Begin
  Testit ( '_ _ha_ha_what_gets_lost _?_ ');
  Testit ( '#10#13'haha_ ');
  Testit ( ' _ _ _ _ _ _ _ _ _ _ _ _ ');
End.
```

TrimLeft

Declaration: Function TrimLeft(const S: string): string;

Description: TrimLeft strips blank characters (spaces) at the beginning of S and returns the resulting string.
Only #32 characters are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: [Trim \(437\)](#), [TrimRight \(438\)](#)

Listing: sysutex/ex85.pp

```
Program Example85;

{ This program demonstrates the TrimLeft function }

Uses sysutils;
{$H+}

Procedure Testit (S : String);

begin
  Writeln ( '', TrimLeft(S), '' );
end;

Begin
  Testit ( ' _ _ ha _ ha _ what _ gets _ lost _ ? _ ');
  Testit (#10#13 'haha _ ');
  Testit ( ' _ _ _ _ _ _ _ _ _ _ _ _ ');
End.
```

TrimRight

Declaration: `Function TrimRight(const S: string): string;`

Description: Trim strips blank characters (spaces) at the end of S and returns the resulting string. Only #32 characters are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: [Trim \(437\)](#), [TrimLeft \(437\)](#)

Listing: sysutex/ex86.pp

```
Program Example86;

{ This program demonstrates the TrimRight function }

Uses sysutils;
{$H+}

Procedure Testit (S : String);

begin
  Writeln ( '', TrimRight(S), '' );
end;

Begin
  Testit ( ' _ _ ha _ ha _ what _ gets _ lost _ ? _ ');
  Testit (#10#13 'haha _ ');
  Testit ( ' _ _ _ _ _ _ _ _ _ _ _ _ ');
End.
```

UpperCase

Declaration: `Function UpperCase(const s: string): string;`

Description: `UpperCase` returns the uppercase equivalent of `S`. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the `UpCase` function of the system unit, and is provided for compatibility only.

Errors: None.

See also: `AnsiLowerCase` ([410](#)), `LowerCase` ([433](#)), `AnsiUpperCase` ([416](#))

Errors:

See also:

Listing: `sysutex/ex87.pp`

Program `Example87;`

{ This program demonstrates the UpperCase function }

Uses `sysutils;`

Begin

`WriteLn ( UpperCase( ' this _will _come_OUT_ALL_uPpErCaSe_!' ) );`

End.

Index

Abstract, [283](#)
Accept, [344](#), [346](#)
Access, [167](#)
AddDisk, [41](#)
AddDisk (Linux only), [387](#)
AdjustLineBreaks, [407](#)
Alarm, [168](#)
allocate_ldt_descriptors, [81](#)
allocate_memory_block, [83](#)
AnsiCompareStr, [408](#)
AnsiCompareText, [408](#)
AnsiExtractQuotedStr, [409](#)
AnsiLastChar, [410](#)
AnsiLowerCase, [410](#)
AnsiQuotedStr, [411](#)
AnsiStrComp, [411](#)
AnsiStrIComp, [412](#)
AnsiStrLastChar, [413](#)
AnsiStrLComp, [413](#)
AnsiStrLIComp, [414](#)
AnsiStrLower, [415](#)
AnsiStrUpper, [416](#)
AnsiUpperCase, [416](#)
AppendStr, [417](#)
Arc, [114](#)
arccos, [238](#)
arcosh, [238](#)
arcsin, [239](#)
arctan2, [240](#)
arsinh, [240](#)
artanh, [241](#)
AssignCrt, [26](#)
AssignLst, [341](#)
AssignPipe, [168](#)
AssignStr, [417](#)
AssignStream, [169](#)

Bar, [114](#)
Bar3D, [114](#)
BaseName, [171](#)
BCDToInt, [418](#)
Bind, [346](#), [347](#)

ceil, [241](#)
CFMakeRaw, [171](#)

CFSetISpeed, [172](#)
CFSetOSpeed, [172](#)
ChangeFileExt, [390](#)
Chmod, [173](#)
Chown, [172](#)
Circle, [115](#)
ClearDevice, [115](#)
ClearViewPort, [115](#)
Clone, [174](#)
CloseDir, [176](#)
CloseGraph, [115](#)
ClrEol, [27](#)
ClrScr, [28](#)
CompareMem, [419](#)
CompareStr, [419](#)
CompareText, [420](#)
Connect, [347](#), [348](#)
copyfromdos, [83](#)
copytodos, [83](#)
cosh, [242](#)
cotan, [242](#)
create_code_segment_alias_descriptor, [84](#)
CreateDir, [387](#)
CreateShellArgV, [176](#)
CursorBig, [27](#)
CursorOff, [28](#)
CursorOn, [28](#)
cycletorad, [242](#)

Date, [373](#)
DateTimeToFileDate, [374](#)
DateTimeToStr, [374](#)
DateTimeToString, [375](#)
DateTimeToSystemTime, [376](#)
DateTimeToTimeStamp, [376](#)
DateToStr, [377](#)
DayOfWeek, [377](#)
DecodeDate, [377](#)
DecodeTime, [378](#)
degtograd, [243](#)
degtorad, [243](#)
Delay, [28](#)
DeleteFile, [391](#)
DelLine, [29](#)
DetectGraph, [115](#)

- DirName, 177
- disable, 84
- DiskFree, 42, 388
- DiskSize, 42, 389
- DisposeStr, 283, 421
- DoDirSeparators, 391
- DosExitCode, 43
- dosmemfillchar, 84
- dosmemfillword, 85
- dosmemget, 86
- dosmemmove, 86
- dosmemput, 86
- DosVersion, 43
- DrawPoly, 116
- DumpHeap, 134
- Dup, 177
- Dup2, 178
- dx_load, 56
- Ellipse, 116
- Emms, 268
- enable, 87
- EncodeDate, 378
- EncodeTime, 379
- EnvCount, 44
- EnvStr, 44
- EpochToLocal, 179
- Exec, 45
- Execl, 179
- Execl, 180
- Execlp, 181
- Execv, 182
- Execve, 182
- Execvp, 183
- ExpandFileName, 392
- ExpandUNCFileName, 392
- ExtractFileDir, 393
- ExtractFileDrive, 393
- ExtractFileExt, 393
- ExtractFileName, 394
- ExtractFilePath, 394
- ExtractRelativePath, 394
- Fcntl, 193
- FD_Clr, 184
- FD_IsSet, 185
- FD_Set, 185
- FD_ZERO, 184
- fdClose, 185
- fdFlush, 185
- fdOpen, 186
- fdRead, 187
- fdSeek, 188
- fdTruncate, 188
- fdWrite, 188
- FExpand, 45, 189
- FileAge, 395
- FileClose, 395
- FileCreate, 396
- FileDateToDateTime, 380
- FileExists, 397
- FileGetAttr, 397
- FileGetDate, 398
- FileOpen, 399
- FileRead, 399
- FileSearch, 399
- FileSeek, 400
- FileSetAttr (Not on Linux), 401
- FileSetDate (Not on Linux), 401
- FileTruncate, 401
- FileWrite, 401
- FillEllipse, 116
- FillPoly, 116
- FindClose, 45, 402
- FindFirst, 46, 402
- FindNext, 47, 403
- FloatToStr, 421
- FloatToStrF, 422
- FloatToText, 423
- FLock, 189
- FloodFill, 116
- floor, 244
- FmtStr, 424
- FNMatch, 189
- Fork, 194
- Format, 424
- FormatBuf, 430
- FormatDateTime, 380
- free_ldt_descriptor, 87
- free_memory_block, 87
- free_rm_callback, 87
- FRename, 194
- frexp, 244
- FSearch, 47, 190
- FSplit, 47, 190
- FSSStat, 191
- FStat, 192
- ftok, 142
- get_cs, 88
- get_descriptor_access_rights, 88
- get_ds, 88
- get_linear_addr, 88
- get_meminfo, 89
- get_next_selector_increment_value, 90
- get_page_size, 90
- get_pm_interrupt, 90
- get_rm_callback, 91

get_rm_interrupt, 93
get_run_mode, 94
get_segment_base_address, 94
get_segment_limit, 95
get_ss, 95
GetArcCoords, 117
GetAspectRatio, 117
GetBkColor, 117
GetCBreak, 48
GetColor, 117
GetCurrentDir, 389
GetDate, 48, 195
GetDateTime, 195
GetDefaultPalette, 117
GetDirs, 403
GetDomainName, 196
GetDriverName, 117
GetEGid, 196
GetEnv, 49, 197
GetEpochTime, 197
GetEUid, 197
GetFAttr, 49
GetFillPattern, 118
GetFillSettings, 118
GetFS, 198
GetFTime, 50
GetGid, 198
GetGraphMode, 118
GetHostName, 199
GetImage, 118
GetIntVec, 51
GetLastButtonPress, 270
GetLastButtonRelease, 271
GetLineSettings, 118
GetLocalTimezone, 199
GetLongName, 51
GetLongOpts, 60
GetMaxColor, 118
GetMaxMode, 119
GetMaxX, 119
GetMaxY, 119
GetModeName, 119
GetModeRange, 119
GetMouseState, 271
Getopt, 60
GetPalette, 120
GetPaletteSize, 120
GetPeerName, 349
GetPid, 199
GetPixel, 120
GetPPid, 200
GetPriority, 200
GetShortName, 51
GetSocketName, 349
GetSocketOptions, 350
GetTextSettings, 120
GetTime, 51, 201
GetTimeOfDay, 201
GetTimezoneFile, 202
GetUid, 202
GetVerify, 52
GetViewSettings, 120
GetX, 120
GetY, 121
Glob, 202
global_dos_alloc, 95
global_dos_free, 97
GlobFree, 203
GotoXY, 29
Gpm_AnyDouble, 65
Gpm_AnySingle, 66
Gpm_AnyTriple, 66
Gpm_Close, 66
Gpm_FitValues, 66
Gpm_FitValuesM, 66
Gpm_GetEvent, 67
Gpm_GetLibVersion, 68
Gpm_GetServerVersion, 68
Gpm_GetSnapshot, 68
Gpm_LowerRoi, 69
Gpm_Open, 69
Gpm_PopRoi, 69
Gpm_PushRoi, 69
Gpm_RaiseRoi, 70
Gpm_Repeat, 70
Gpm_StrictDouble, 70
Gpm_StrictSingle, 70
Gpm_StrictTriple, 71
gradtodeg, 245
gradtorad, 245
GraphDefaults, 121
GraphErrorMsg, 121
GraphResult, 121

HideMouse, 272
HighVideo, 30
hypot, 246

ImageSize, 122
IncMonth, 381
InitGraph, 122
InitMouse, 273
inportb, 97
inportl, 97
inportw, 97
InsLine, 30
InstallUserDriver, 122
InstallUserFont, 123

intpower, 246
Intr, 52
IntToHex, 430
IntToStr, 431
IOctl, 203
IOperm, 204
IsATTY, 204
IsLeapYear, 381
IsValidIdent, 431

Keep, 52
KeyPressed, 31
Kill, 206

LastDelimiter, 432
ldexp, 247
LeftStr, 432
Line, 123
LineRel, 123
LineTo, 123
Link, 208
Listen, 350
lnxp1, 247
LoadStr, 433
LocalToEpoch, 209
lock_code, 98
lock_data, 98
lock_linear_region, 98
log10, 248
log2, 248
logn, 249
LongDiv, 285
LongMul, 285
LowerCase, 433
LowVideo, 31
LPressed, 273
LStat, 207

MarkHeap, 134
max, 249
maxIntValue, 250
maxvalue, 250
mean, 251
meanandstddev, 252
min, 253
minIntValue, 253
minvalue, 254
MkFifo, 210
MMap, 210
momentskewkurtosis, 255
MoveRel, 123
MoveTo, 124
MPressed, 274
MSDos, 53

MSecsToTimeStamp, 382
msgctl, 143
msgget, 142
msgrcv, 143
msgsnd, 142
MUnMap, 211

NewStr, 282, 433
Nice, 212
norm, 255
NormVideo, 32
NoSound, 32
Now, 382
npxsetup, 58

Octal, 212
OpenDir, 213
outportb, 99
outportl, 99
outportw, 99
OutText, 124
OutTextXY, 124

PackTime, 53
pause, 214
PClose, 214
PieSlice, 124
POpen, 214
popnstddev, 256
popnvariance, 257
power, 257
PutImage, 124
PutPixel, 125

QuotedStr, 434

radtocycle, 258
rattodeg, 258
rattograd, 259
randg, 259
ReadDir, 215
ReadKey, 33
ReadLink, 215
ReadPort, 217
ReadPortB, 217
ReadPortL, 217
ReadPortW, 218
ReadTimezoneFile, 218
realintr, 100
Rectangle, 125
Recv, 351
RegisterBGIDriver, 125
RegisterBGIFont, 125
RegisterObjects, 283
RegisterType, 283

RemoveDir, 390
RenameFile, 403
RestoreCRTMode, 125
RightStr, 434
RPressed, 274

S_ISBLK, 204
S_ISCHR, 205
S_ISDIR, 205
S_ISFIFO, 205
S_ISLNK, 205
S_ISREG, 206
S_ISSOCK, 206
Sector, 126
SeekDir, 218
seg_fillchar, 100
seg_fillword, 101
seg_move, 102
segment_to_descriptor, 101
Select, 218
SelectText, 219
semctl, 147
semget, 146
semop, 146
Send, 351
set_descriptor_access_rights, 102
set_pm_interrupt, 102
set_rm_interrupt, 103
set_segment_base_address, 104
set_segment_limit, 104
SetActivePage, 126
SetAllPalette, 126
SetAspectRatio, 126
SetBkColor, 126
SetCBreak, 54
SetColor, 127
SetCurrentDir, 390
SetDate, 54
SetDirSeparators, 404
SetExtraInfo, 135
SetFAttr, 54
SetFillPattern, 127
SetFillStyle, 127
SetFTime, 54
SetGraphBufSize, 127
SetGraphMode, 128
SetHeapTraceOutput, 136
SetIntVec, 55
SetLineStyle, 128
SetMouseAscii, 274
SetMouseHideWindow, 275
SetMousePos, 275
SetMouseShape, 276
SetMouseSpeed, 277
SetMouseWindow, 277
SetMouseXRange, 278
SetMouseYRange, 278
SetPalette, 128
SetPriority, 220
SetRGBPalette, 128
SetSocketOptions, 352
SetTextJustify, 129
SetTextStyle, 129
SetTime, 55
SetUserCharSize, 129
SetVerify, 55
SetViewPort, 130
SetVisualPage, 130
SetWriteMode, 130
Shell, 220
shmat, 152
shmctl, 152
shmdt, 152
shmget, 151
ShowMouse, 278
Shutdown, 352
SigAction, 221
Signal, 223
SigPending, 222
SigProcMask, 222
SigRaise, 222
SigSuspend, 223
sincos, 260
sinh, 261
Sock2File, 352
Sock2Text, 353
Socket, 353
SocketPair, 353
Sound, 33
stddev, 261
Str2UnixSockAddr, 353
StrAlloc, 354, 405
StrBufSize, 406
StrCat, 354
StrComp, 355
StrCopy, 355
StrDispose, 356, 406
StrECopy, 356
StrEnd, 357
StrFmt, 435
StrIComp, 357
StringToPPchar, 224
StrLCat, 358
StrLComp, 358
StrLCopy, 359
StrLen, 359
StrLFmt, 435
StrLIComp, 360

-
- StrLower, 360
 - StrMove, 361
 - StrNew, 361
 - StrPas, 362, 407
 - StrPCopy, 362, 406
 - StrPLCopy, 407
 - StrPos, 363
 - StrRScan, 363
 - StrScan, 363
 - StrToDate, 383
 - StrToDateTime, 383
 - StrToInt, 436
 - StrToIntDef, 436
 - StrToTime, 384
 - StrUpper, 364
 - sum, 262
 - sumofsquares, 262
 - sumsandsquares, 263
 - SwapVectors, 55
 - SymLink, 225
 - SysInfo, 226
 - SystemTimeToDateTime, 385

 - tan, 264
 - tanh, 264
 - tb_size, 104
 - TBufStream.Close, 305
 - TBufStream.Done, 304
 - TBufStream.Flush, 305
 - TBufStream.Init, 304
 - TBufStream.Open, 306
 - TBufStream.Read, 306
 - TBufStream.Seek, 306
 - TBufStream.Truncate, 306
 - TBufStream.Write, 307
 - TCDrain, 227
 - TCFlow, 227
 - TCFlush, 228
 - TCGetAttr, 228
 - TCGetPGrp, 229
 - TCollection.At, 311
 - TCollection.AtDelete, 319
 - TCollection.AtFree, 318
 - TCollection.AtInsert, 322
 - TCollection.AtPut, 321
 - TCollection.Delete, 318
 - TCollection.DeleteAll, 316
 - TCollection.Done, 311
 - TCollection.Error, 321
 - TCollection.FirstThat, 314
 - TCollection.ForEach, 320
 - TCollection.Free, 317
 - TCollection.FreeAll, 315
 - TCollection.FreeItem, 319
 - TCollection.GetItem, 313
 - TCollection.IndexOf, 312
 - TCollection.Init, 310
 - TCollection.Insert, 317
 - TCollection.LastThat, 313
 - TCollection.Load, 310
 - TCollection.Pack, 314
 - TCollection.PutItem, 323
 - TCollection.SetLimit, 321
 - TCollection.Store, 322
 - TCSendBreak, 229
 - TCSetAttr, 229
 - TCSetPGrp, 230
 - TDateTime, 373
 - TDosStream.Close, 300
 - TDosStream.Done, 300
 - TDosStream.Init, 300
 - TDosStream.Open, 302
 - TDosStream.Read, 303
 - TDosStream.Seek, 301
 - TDosStream.Truncate, 301
 - TDosStream.Write, 303
 - TellDir, 230
 - TextBackground, 33
 - TextColor, 34
 - TextHeight, 130
 - TextMode, 34
 - TextWidth, 130
 - Time, 385
 - TimeStampToDateTime, 386
 - TimeStampToMSecs, 386
 - TimeToStr, 387
 - TMemoryStream.Done, 308
 - TMemoryStream.Init, 307
 - TMemoryStream.Read, 308
 - TMemoryStream.Truncate, 308
 - TMemoryStream.Write, 309
 - TObject.Done, 291
 - TObject.Free, 291
 - TObject.Init, 290
 - totalvariance, 265
 - transfer_buffer, 105
 - TRect.Assign, 290
 - TRect.Contains, 287
 - TRect.Copy, 287
 - TRect.Empty, 286
 - TRect.Equals, 286
 - TRect.Grow, 289
 - TRect.Intersect, 288
 - TRect.Move, 289
 - TRect.Union, 287
 - TResourceCollection.FreeItem, 334
 - TResourceCollection.GetItem, 333
 - TResourceCollection.KeyOf, 333

TResourceCollection.PutItem, 334
TResourceFile.Count, 335
TResourceFile.Delete, 336
TResourceFile.Done, 335
TResourceFile.Flush, 336
TResourceFile.Get, 335
TResourceFile.Init, 335
TResourceFile.KeyAt, 335
TResourceFile.Put, 336
TResourceFile.SwitchTo, 336
Trim, 437
TrimLeft, 437
TrimRight, 438
TSortedCollection.Compare, 325
TSortedCollection.IndexOf, 325
TSortedCollection.Init, 324
TSortedCollection.Insert, 327
TSortedCollection.KeyOf, 324
TSortedCollection.Load, 324
TSortedCollection.Search, 326
TSortedCollection.Store, 328
TStrCollection.Compare, 330
TStrCollection.FreeItem, 331
TStrCollection.GetItem, 330
TStrCollection.PutItem, 331
TStream.Close, 295
TStream.CopyFrom, 298
TStream.Error, 297
TStream.Flush, 296
TStream.Get, 292
TStream.GetPos, 294
TStream.GetSize, 294
TStream.Open, 295
TStream.Put, 296
TStream.Read, 298
TStream.ReadStr, 295
TStream.Reset, 296
TStream.Seek, 297
TStream.StrRead, 293
TStream.StrWrite, 297
TStream.Truncate, 296
TStream.Write, 298
TStream.WriteStr, 297
TStringCollection.Compare, 329
TStringCollection.FreeItem, 329
TStringCollection.GetItem, 328
TStringCollection.PutItem, 330
TStringList.Done, 337
TStringList.Get, 337
TStringList.Load, 337
TStrListMaker.Done, 338
TStrListMaker.Init, 338
TStrListMaker.Put, 338
TStrListMaker.Store, 338
TTYName, 230
TUnSortedStrCollection.Insert, 332

Umask, 230
Uname, 231
UnLink, 231
unlock_code, 105
unlock_data, 105
unlock_linear_region, 105
UnPackTime, 55
UpperCase, 439
Utime, 231

variance, 265

WaitPid, 232
WhereX, 35
WhereY, 35
Window, 35
WritePort, 233
WritePortB, 233
WritePortL, 233
WritePortW, 234